

# DFSMSdss Storage Administration

Version 2 Release 1

Note	this informatio	n and the prod	uct it support	s, read the info	ormation in "N	otices" on page	655.

© Copyright IBM Corporation 1984, 2015. US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

## Contents

Figures xi	Volume formats	14
Tables xiii	Data set organizations	
About this document xv	Chapter 3. Logical and physical	
Required product knowledge xv	processing and data set filtering	17
z/OS information xvii	Defining logical and physical processing Logical processing	17 17
How to send your comments to IBM xix	Physical processing	
If you have a technical problem xix	Choosing data sets for processing—filtering	
, i	Filtering by data set names	20
Summary of changes xxi	Filtering by data set characteristics	
Summary of changes for z/OS Version 2 Release 1	The FILTERDD keyword	
(V2R1) as updated February 2015 xxi	Uses of filtering	
Summary of changes for z/OS Version 2 Release 1	· ·	
(V2R1) as updated September 2014 xxi	Chapter 4. Invoking DFSMSdss	25
z/OS Version 2 Release 1 summary of changes xxi	Invoking DFSMSdss with ISMF	25
	How to invoke ISMF	
Part 1. DFSMSdss Storage	Invoking DFSMSdss with JCL	25
Administration Guide 1	Invoking DFSMSdss with the application interface	25
Administration Guido I I I I I I I I	User interaction module exit functions	26
Chapter 1. Introduction to the	Chapter F. Brotostina DECMCdoo	
DFSMSdss component of DFSMS 3	Chapter 5. Protecting DFSMSdss	
Understanding the role of DFSMSdss	functions	21
Managing user data with SMS	Protecting DFSMSdss and ISMF functions with	25
Sequential data striping	RACF	
Record counting 4	ISMF functions you might want to protect Setting up the authorization structure	
Installation exit routines 5	Protecting DFSMSdss functions with RACF	21
Authorization checking 5	FACILITY class profiles	20
Managing availability with DFSMSdss 5	Name-hiding	30
Backing up and restoring volumes and data sets . 6	rune mang	00
Using DFSMShsm for backup 6	Chapter 6. Managing availability with	
Using concurrent copy	DFSMSdss	33
Using the stand-alone restore program of		
DFSMSdss	Planning an availability strategy	
Managing data movement with DFSMSdss 8	Disaster recovery	
Moving data	Maintaining vital records	36
Moving data with concurrent copy 9	Archiving data sets	
Moving data with FlashCopy 9	Backing up data sets	
Moving data with SnapShot 9	Logical data set dump	
Converting data to and from SMS management 9	Physical data set dump	
Converting data sets with data movement 9	Renaming data sets during dump processing	
Converting volumes without data movement 10	Backup with concurrent copy	
Managing space with DFSMSdss 10	Using DFSMSdss as a backup utility for CICSVR	42
	A backup scenario	
Chapter 2. Requirements for running		44
DFSMSdss		44
Understanding the operating environment 11	Dumping multivalume data sets	
Storage requirements	Dumping multivolume data sets	
Hardware requirements		47

Dumping VSAM spheres	47	Specifying output volumes	. 93
Dumping indexed VSAM data sets	48	Recovering VM-format volumes	. 94
Dumping SYS1 system data sets	48	Coexistence considerations	. 95
Dumping data sets containing records past the			
last-used-block pointer		Chapter 7. Managing data movement	
Backing up SMS-managed data sets	49	with DFSMSdss	97
Backing up data sets being accessed with record		Preparing for data movement	
level sharing	49	Evaluating the use of logical and physical copy	
Backing up data sets with extended attributes		Controlling what DFSMSdss copies	
Backing up volumes	50	Moving data sets	
Logical volume DUMP	50	Moving volumes	
Physical volume dump	50	Logical data set copy	. <i>99</i> 00
Backing up system volumes	51	Logical data set copy	. 22 100
Backing up VM-format volumes	51	Physical data set copy	100
Dumping data efficiently	51	Selecting output volumes	
Combining volume copy and volume dump to			
reduce your backup window	51	Renaming data sets	104
Space considerations		Expiration date handling	104
Performance considerations	55	SMS to SMS	
Shared DASD considerations		SMS to non-SMS	
Backing up and restoring volumes with		Non-SMS to SMS	
incremental FlashCopy	60	Non-SMS to non-SMS	
Securing your tape backups	62	Defining RACF profiles	
	64	Moving data sets with utilities	
DFSMSdss processing of dump encryption		Moving data sets with concurrent copy	
requests	69	Specifying concurrent copy for COPY requests	
Restoring data sets		Moving data sets with FlashCopy	
Logical data set restore		Designating FlashCopy usage	
DFSMSdss handling of the expiration date		Moving data sets with SnapShot	
during logical restore	75	Moving data sets with special requirements	114
DFSMSdss handling of the data-set-changed		Moving undefined DSORG and empty	
indicator during restore	76	non-VSAM data sets	
Physical data set restore		Moving system data sets	
Coexistence considerations		Moving catalogs	
Restoring data sets with special requirements		O	116
Restoring multivolume data sets and restoring	, 0	Moving multivolume data sets	116
data sets using multiple target volumes (spill		Converting VSAM and non-VSAM data sets to	
volumes)	78	multivolume	118
Restoring integrated catalog facility catalogs		Moving VSAM data sets	
	81	Moving a PDSE	119
Restoring indexed sequential, unmovable, direct,	01	Moving a damaged PDS	120
and absolute track data sets	81	Moving unmovable data sets	120
Restoring an undefined DSORG data set 8		Moving data sets to unlike devices	
Restoring an extended-format VSAM data set	05	Moving indexed sequential data sets	
with stripe count of one	83	Moving direct access data sets	
Restoring a VSAM sphere		Moving GDG data sets	
Restoring a preallocated VSAM cluster 8		Moving SMS-managed data sets	
Restoring the VVDS and the VTOCIX 8		Moving non-SMS-managed data sets	
Restoring a PDSE		Moving to preallocated data sets	126
Restoring a damaged PDS	95	Moving data sets being accessed with record	
Restoring data sets in an SMS-managed	0.5	level sharing	129
environment	0E		129
Converting non-VSAM data sets to multivolume		VTOC considerations for moving volumes	130
· ·		Logical volume copy operation	130
Restoring SMS-managed data sets	00	Physical volume copy operation	
Restoring GDG data sets		Moving volumes with FlashCopy	
Restoring non-SMS-managed data sets	<del>7</del> U	Designating FlashCopy usage	
Logical restore of data sets with phantom catalog	00		133
entries	フリ	~ ,	133
Logical restore of preformatted empty VSAM	01	Choosing space efficient FlashCopy with the	
data sets	71 02	FCSETGTOK keyword	134
Restoring volumes	フム		

Initializing the volume with the FCWITHDRAW keyword	Designating SnapShot usage
consistency group	CONSOLIDATE processing
Moving volumes with SnapShot	DEFRAG options
Designating SnapShot usage	Serialization
Determining why SnapShot cannot be used 138	Security considerations
Moving volumes to like devices of equal capacity 139	Maximizing track utilization by reblocking data
Moving volumes to like devices of greater capacity 139	sets
Moving volumes to unlike devices	
Moving VM-format volumes	Chapter 10. Diagnosing problems in
0	
Chapter 8. Converting data to and	DFSMSdss operations 167
from SMS management 141	Determining the source of the failure: DFSMSdfp, DFSMSdss, or DFSMShsm
Evaluating conversion to SMS management 141	Using keywords to identify the problem 16
Data sets ineligible for conversion to SMS 141	
Data sets ineligible for conversion from SMS 142	Component identification keyword
Volumes eligible for conversion to SMS 142	Type-of-failure and function keywords 16
Conversion by data movement	Module keyword
Converting to SMS management by data	Maintenance-level keyword
movement	Using the IBM Support Center
Conversion from SMS management by data	Using the software support facility
movement	Using IBMLink/ServiceLink
Conversion without data movement	Info/System
Simulating conversion	into, system:
Preparing a volume for conversion 144	Chapter 11. ACS routine information 179
Converting to SMS management without data	ACS variables available during Copy function 17
movement	ACS variables available during RESTORE and
SMS report	CONVERTV processing
Special data set requirements for conversion to	Using SIZE and MAXSIZE variables 18
SMS	Using Size and WAASize variables 10.
VSAM sphere eligibility 146	Chapter 12 Dumping and restoring
Multivolume data sets	Chapter 12. Dumping and restoring
GDG data sets	Linux for System z partitions and
Temporary data sets	volumes
VTOC and VVDS	Preparing to work with Linux volumes 18
Converting from SMS management without data	Understanding the hardware environment 18
movement	Choosing VOLSERs for Linux volumes 18
Special data set requirements for conversion from	Formatting and partitioning Linux volumes 18
SMS	Obtaining authorization for Linux volumes 18
Multivolume data sets	Backing up a Linux volume with partitions 18
GDG data sets	Using DFSMSdss dump and restore commands 18
Temporary data sets	Example 1. DUMP FULL
VTOC and VVDS	Example 2. DUMP FULL with CONCURRENT
Special considerations for using non-SMS-managed	COPY
targets	Example 3. DUMP DATASET
	Example 4. COPY FULL
Chapter 9. Managing space with	Example 5. COPY FULL COPYVOLID
DFSMSdss 151	ALLEXCP
Reclaiming DASD space	
Releasing unused space in data sets	Example 8. COPYDUMP.
Compressing a PDS	Example 8. COPYDUMP
Deleting unwanted data sets 152	FTP
Combining data set extents	Using DFSMSdss stand-alone services
Consolidating free space and extents on volumes 155	Using Dividuss stand-atome services 19
When to run DEFRAG and CONSOLIDATE	Chantar 12 Format of the DECMEdag
functions	Chapter 13. Format of the DFSMSdss
Designating FlashCopy usage 156	dump data set
Preserve Mirror FlashCopy	Format of the DFSMSdss dump data set 19
Determining why FlashCopy cannot be used 157	ADRBMB data area

ADRBMB constants	. 199 . 199	Changing the default DEFRAG processing of checkpointed data sets (OW20285) Setting the percentage to overallocate target data	
ADRTAPB cross-reference		set space (OW27837)	
Chapter 14. DFSMSdss patch area	217		234
	. 217	VALIDATE PDSE option (OW48074)	235
Forcing the use of preallocated VSAM data sets (PN04574)	217	Changing the default maximum number of active	
Ignoring VSAM duplicate key errors (PN05529)	218	parallel subtasks	236
Modifying the timeout period for enqueue lockout		Changing the default initialization processing	
detection (PL84514)	. 219	` '	236
Controlling the wait/retry time for serialization of		Changing the default DEFRAG processing of	225
system resources (PN11523)	. 219	· · · · · · · · · · · · · · · · · · ·	237
Using CONVERTV on data sets with a revoked		Changing the FASTREPLICATION default setting during Copy and Defrag (OA11637)	238
user ID in the RESOWNER field (OY59957)	. 220	Tuning hardware assisted compression (OA13300)	238
Restoring inconsistent PDSE data sets (OY60301)	220	Resetting the data-set-changed indicator during	
Changing default protection status during RESTORE (PN37489)	221	physical full or partial RESTORE operation	
Restoring or copying undefined, multivolume	. 221	(OA20907)	239
SMS-managed data sets (OY63818)	. 221	Requesting that DFSMSdss double-check data set	
Bypassing backup-while-open processing		high used RBA values for LDS data sets (OA23805)	239
(OY63531)	. 222	Enabling or disabling use of the catalog search	240
Bypassing storage and management class		interface for data set name filtering	240
authorization checking during RESTORE	222	VM-formatted volume that was DUMPed by z/OS	
(OY65348)		V1R10 before OA27531 was applied	240
(OY66092)		Adding timestamps to messages	
Using RESET with concurrent copy (OY65555) .		Enabling building appropriate channel programs	241
Forcing RESTORE after message ADR482E		Requesting that DFSMSdss attempt to fix ESDSes	
(OY67532)	. 224	with corrupted RDFs	
Restoring VSAM KSDS or VRRDS after messages		ADRITCHB data area	
ADR789W, ADR364W, and ADR417W (OY67942)	. 224	ADRPTCHB cross-reference	243
Restoring VSAM data sets with expiration date of	225	Don't O. DECMOdos Otomoro	
1999365 (OW00780)	. 223	Part 2. DFSMSdss Storage	
beyond 2000 (OW00780)	. 225	Administration Reference 2	247
Changing default insertion of EOF track during			
COPY with ALLDATA specified (OW15003)		Chapter 15. Specifying DFSMSdss	
Using RESET or UNCATALOG in a logical data set			249
dump (PN60114)		Command syntax	
Changing secondary allocation quantity in format 1		How many subkeywords are allowed?	
DSCB for PDSE data sets (OW07755) Changing reference date default settings during	. 221	Specifying subkeywords in a command data set How to read syntax diagrams	250
data set COPY and RESTORE processing		JCL that you need	
(OW12011)	. 228	How to control DFSMSdss through PARM	
Changing default protection processing during		information in the EXEC statement	254
COPY (OW10314)	. 229	Examples of invoking DFSMSdss with JCL	257
Bypassing management and storage class access			
checks during COPY (PN72592)	. 229	Chapter 16. DFSMSdss	
Changing default handling of invalid tracks		filtering—choosing the data sets you	
created during data set COPY and RESTORE processing (OW08174)	. 230	want processed	
Forcing RESTORE to the same volumes as the	. 200	How DFSMSdss filters data sets	259
source VSAM data set (OW07077)	. 230	Virtual storage access method (VSAM) data set	
Modifying number of volumes allocated for SMS		considerations	
data sets during logical RESTORE and COPY		Filtering by data set names	∠b(
	. 231	names	260
Dumping a keyed VSAM data set that has data	222		
CAs without corresponding index CIs (OW17877)	. 232		

Using a percent sign in partially qualified data set names	
Examples of fully and partially qualified data	COPYDUMP syntax
set names	Explanation of COPYDUMP command
Relative generation filtering	keywords
Some examples of the BY keywords	
Standard catalog search order	
Broken data set considerations	
broken data set considerations	Examples of DEFRAG operations
Chapter 17. Syntax—DFSMSdss	Results of a successful DEFRAG operation 389
	DUMP
function commands	Chariel considerations for dump
What DFSMSdss commands do	DI IMP FILL and DI IMP TRACKS syntax 392
0	DUMP DATASET syntax for logical data set 394
Using DUMP and RESTORE for backup and	DUMP DATASET syntax for physical data set 307
recovery	
Converting to and from Storage Management	Data integrity considerations for full or tracks
Subsystem (SMS) with CONVERTV	dump operation 425
Managing space with COMPRESS,	Format of the output data set 426
CONSOLIDATE, DEFRAG, and RELEASE 27	Examples of full and tracks dump operations 426
Using COPY for partitioned data set (PDS) and	Examples of physical data set dump operations 427
partitioned data set extended (PDSE)	Examples of logical data set dump operations 429
conversions	PRINT command for DFSMSdss 432
Copying DFSMSdss-produced dump data with	PRINT Syntax
COPYDUMP	Explanation of PRINT command keywords 434
Printing for diagnostic purposes with PRINT 27	Examples of print operations
BUILDSA command for DFSMSdss	RELEASE command for DFSMSdss
BUILDSA syntax	
Explanation of BUILDSA command keywords 27	
BUILDSA command examples	Example of a release anaration 451
CGCREATED command for DFSMSdss 27	DESTORE command for DESMEdge 452
CGCREATED syntax	Special considerations for RESTORE
Explanation of CGCREATED command	Data integrity considerations for full or tracks
keywords	454
COMPRESS command for DFSMSdss	PESTOPE FILL and PESTOPE TRACKS
COMPRESS syntax	/8
Explanation of COMPRESS command keywords 27	PESTOPE DATASET command syntax for
Example of compress operations	logical data set
CONSOLIDATE command syntax	RESTURE ITATASET command contay for
Explanation of CONSOLIDATE command	physical data set 458
keywords	Explanation of RESTORE command keywords 459
Example of a CONSOLIDATE operation 29	DESMISASS RESTORE process
CONVERTV command for DFSMSdss	Examples of full and tracks restore operations 495
CONVERTV command syntax	Examples of physical data set restore operations 496
Explanation of CONVERTV command	Examples of logical data set restore operations 499
keywords	95
Examples of CONVERTV operations 29	98 Chapter 18. Syntax—auxiliary
COPY Command for DFSMSdss	
Special Considerations for COPY	
COPY DATASET Command Syntax for Logical	WTO command 503
Data Set	
COPY DATASET Command Syntax for Physical	Scheduling tasks
Data Set	
COPY FULL and COPY TRACKS Syntax 30	
Explanation of COPY Command Keywords 31	
Data Integrity Considerations for Full or Tracks	SET command—setting condition codes and
Copy Operation	
Examples of Full and Tracks Copy Operations 36 Examples of Data Set Copy Operations 36	63 IF-THEN-ELSE command sequence for 64 DFSMSdss—using condition codes 506
Examples of Data Det Copy Operations 30	of Dibitiouss—using condition codes

EOJ command—ending your DFSMSdss step 510	COPY
Chapter 19. DFSMSdss stand-alone	DEFRAG
services 511	DUMP
Preparing to run the stand-alone services program 511	PRINT
Running stand-alone services in 370 mode 511	RELEASE
Running stand-alone services in XA or ESA	RESTORE
mode	
Running stand-alone services with a predefined	Chapter 21. Data
console	integrity—serialization 561
Using a tape library	Volume serialization
Using an automatic cartridge loader	Avoiding lockout
Controlling command sequence processing 516	The WAIT option
IPLing and running the Stand-Alone Services	Data set serialization
Program	Enqueuing—ENQ
IPLing Stand-Alone Services	Dumping HFS data sets
RESTORE—restoring a formatted dump tape 522	zFS data sets
TAPECNTL—rewinding and unloading a tape 527	Dynamic allocation (DYNALLOC) 566
Building the IPL-able core image	Enqueuing versus dynamic allocation of data
BUILDSA function	sets
Understanding BUILDSA command	Read/Write serialization scheme 566
authorization levels	WAIT option
	An example of RESERVE-ENQUEUE processing 570
Chapter 20. Data security and	Backup-while-open data sets (CICS and DFSMStvs) 571
· · · · · · · · · · · · · · · · · · ·	Backup-while-open status definition 572
authorization checking 531	Backup-while-open processing 572
Effects of SPECIAL, OPERATIONS, and DASDVOL 531	Backup-while-open and concurrent copy 574
SPECIAL	TOLERATE (ENQFAILURE) and SHARE
OPERATIONS	considerations 574
DASDVOL	CICS recovery data 574
General data security information	Backup-while-open data sets (IMS) 575
Protecting resources and data sets 533	
Protecting the usage of DFSMSdss 533	Chapter 22. Application programming
Password protection	interface 577
Protected user and group data sets 535	
Generic and discrete profile considerations 536 Security-level, category, and label checking 537	Calling block structure
	User interactions
Protect-all and always-call	
Standard naming conventions	J 11
DFSMSdss temporary data set names 538 Discretely protected multivolume data set 539	Using the cross memory application interface to control DFSMSdss
Erase-on-scratch	System programming information
SMS-managed data set protection	Application interface blocks
	Exit identification block
Logging	Application programming interface restrictions 589
ADMINISTRATOR keyword	Cross-memory application interface restrictions 589
FACILITY class profiles for the	User interaction module exit option descriptions 590
ADMINISTRATOR keyword 542	Function startup (Eioption 00) 590
DFSMSdss volume, data set and catalog access	Reading SYSIN record (Eioption 01)
authority	Printing SYSPRINT record (Eioption 02) 591
Volume access and DASDVOL	Reading physical tape record (Eioption 03) 592
Data set access authorization levels 546	Reading logical tape record (Eloption 04) 592
Protected catalogs	Writing logical tape record (Eioption 05) 593
Non-SMS versus SMS authorization	Writing physical tape record (Eioption 06) 593
System operator authorization, special data set types	Reading disk track (Eioption 07) 593 Writing disk track (Eioption 08) 593
Access authorization for DFSMSdss commands 547	Reading utility SYSPRINT (Eioption 09) 593
CGCREATED	Writing SYSPRINT record (Eioption 10) 594
COMPRESS	Writing WTO message (Eioption 11) 594
CONSOLIDATE	Writing WTO message (Eioption 12) 594
CONVERTY 548	Procenting ADRIJEO record (Figure 13) 595

Function ending (Eioption 14)	Chapter 23. Examples of the application program with the user interaction module (UIM) 625
OPEN/EOV nonspecific tape volume mount (Eioption 17)	Chapter 24. Data set attributes 643
(Eioption 18)	Part 3. Appendixes 647
Volume notification (Eioption 20) 596 Data set verification (Eioption 21) 597 Bypass verification exit (Eioption 22) 597 Data set processed notification exit (Eioption 23) 601 Concurrent copy initialization complete	Appendix A. Coexistence Considerations
(Eioption 24)	Appendix B. Accessibility651Accessibility featuresConsult assistive technologiesKeyboard navigation of the user interfaceDotted decimal syntax diagrams
(Eioption 28)	Notices
Cross reference for ADREID0 617 Example: invoking DFSMSdss by using an	Glossary 659
application program	Index 673

## **Figures**

1.	Output from a Dump of an Integrated Catalog		18.	Output Resulting from a PRINT Command 44	ŧ1
	Facility User Catalog	47	19.	Restore Actions on Non-VSAM Data Sets 49	)(
2.	Output from Restore of Integrated Catalog		20.	DFSMSdss Target Class Selection 49	)4
	Facility User Catalog	80	21.	Stand-Alone Services Restore Process	
3.	SMS Report	146		Overview	. 7
4.	Sample JCL for dumping the contents of a		22.	DFSMSdss Data Security Decisions 54	14
	volume	189	23.	Block Diagram for Backup-While-Open	
5.	Sample JCL for dumping two or more output			Serialization	7]
	tapes at the same time	190	24.	DFSMSdss Application Interface Structure 58	
6.	Sample JCL for DUMP FULL with		25.	DFSMSdss Exit Interface Structure	35
	CONCURRENT COPY	190	26.	The Application Program Process 62	
7.	Sample JCL for DUMP DATASET		27.	Application Interface Program Example 62	26
8.	Sample JCL for dumping all of the Linux		28.	Application Interface Program Example	
	partitions	191		(continued)	27
9.	Sample JCL for making a full volume copy of		29.	Application Interface Program Example	
	a volume	192		(continued)	35
10.	Sample JCL for creating a backup copy of a		30.	User Interaction Module Example 62	
	Linux volume	192	31.	User Interaction Module Example (continued) 63	
11.	Sample JCL for restoring a full volume from a		32.	User Interaction Module Example (continued) 63	
	DFSMSdss dump	193	33.	User Interaction Module Example (continued) 63	
12.	Sample JCL for restoring individual partitions		34.	User Interaction Module Example (continued) 63	
	or data sets	193	35.	User Interaction Module Example (continued) 63	
13.	Sample JCL for renaming data sets to be		36.	User Interaction Module Example (continued) 63	
	restored	194	37.	User Interaction Module Example (continued) 63	
14.	Sample JCL for restoring only one partition of		38.	User Interaction Module Example (continued) 63	
	a volume	195	39.	User Interaction Module Example (continued) 63	
15.	Sample JCL for copying Linux volume		40.	User Interaction Module Example (continued) 63	
	dumps	195	41.	Output Resulting from Use of the UIM Exits 64	
16.	Printed Output Resulting from a Successful		42.	Output Resulting from Use of the UIM Exits	
	DEFRAG Run on nonEAV:	390		(continued)	11
17.	A Section of the Printed Output Resulting				
	from a Successful DEFRAG Run on EAV:	391			

## **Tables**

1.	Minimum Storage Requirements for DFSMSdss	18.	ADRTAPB Mapping Macro	99
	Operations with I/O Buffers below	19.	ADRTAPB Mapping Macro	
	16-Megabyte Virtual	20.	ADRPTCHB Mapping Macro 2	
2.	Minimum Storage Requirements for DFSMSdss	21.	BY Keywords 2	
	Operations with I/O Buffers above	22.	ALLDATA and ALLEXCP Interactions When	
	16-Megabyte Virtual		Copying to LIKE Device	7(
3.	Minimum Storage Requirements for a Restore	23.	ALLDATA and ALLEXCP Interactions When	
	to an Unlike Device		Copying to UNLIKE Device	71
4.	Module Names for DFSMSdss/ISMF Line	24.	Physical Data Set Restore Actions on	
	Operators		SMS-Managed Data Sets 4	92
5.	Module Names for DFSMSdss/ISMF Data Set	25.	Stand-Alone Services Options when Using an	
	Application Commands 28		IBM 3494 or 3495 Tape Library 5	14
6.	RACF FACILITY Class Profile Names for	26.	DFSMSdss FACILITY Class Profiles 5	33
	DFSMSdss Keywords	27.	DASDVOL Access Authority 5	45
7.	RSA private tokens and required cryptographic	28.	Access Authority for the DFSMSdss COPY	
	hardware for decryption 67		Command 5	49
8.	DFSMSdss processing of dump encryption	29.	DFSMSdss COPY Command and RACF	
	requests		Profiles 5	5(
9.	DFSMSdss handling of the data-set-changed	30.	DFSMSdss Copy and Define Discrete Profile	
	indicator during data set restore operations 76		Summary 5	52
10.	Data Mover Selection Matrix for Data Set	31.	Access Authority for the DFSMSdss DUMP	
	Сору		Command 5	54
11.	Default Situation for DFSMSdss to Allocate	32.	Access Authority for the DFSMSdss	
	the SMS-Managed GDG Data Set 123		RESTORE Command 5	
12.	Data Set Erase Table for DEFRAG with z/OS	33.	DFSMSdss Copy and Define Profile Summary 5	57
	Security Server (RACF element) 164	34.	Data Set Enqueue Options for Non-VSAM	
13.	Summary of Type-of-Failure Keywords 169		Data Sets Specified on DFSMSdss Commands. 5	64
14.	Variables Passed to ACS Routines during	35.	•	66
	DFSMSdss Copy Function 179	36.	Resource Serialization 5	68
15.	Variables Passed to ACS Routines during	37.	DFSMSdss Support for IMS	
	DFSMSdss Restore and CONVERTV		Backup-While-Open Data Sets 5	
	Processing	38.	ADREID0 Mapping Macro 6	07
16.	ADRBMB Mapping Macro 198	39.	Data Set Attributes and How They Are	
17.	ADRBMB Mapping Macro 199		Determined 6	43

## About this document

This document describes how to use the DFSMSdss component of DFSMS to perform various storage management tasks. It is intended primarily for storage administrators and system programmers.

This guide also includes information intended to help you diagnose DFSMSdss problems. Before you begin diagnostic procedures, follow these steps to verify that the problem is not the result of incorrect command usage:

- 1. Verify that all of the parameters specified for each command are used correctly; see Part 2, "DFSMSdss Storage Administration Reference," on page 247.
- 2. Correct any errors you might find and resubmit the JCL
- 3. Use this document to build a set of keywords that describes the error and, if all parameters appear to be correctly specified, contact IBM® for assistance.

Related reading: Refer to the following for more information.

- For descriptions and syntax of the DFSMSdss commands, Chapter 17, "Syntax—DFSMSdss function commands," on page 269.
- For information about DFSMSdss messages, *z/OS MVS System Messages*, *Vol* 1 (*ABA-AOM*).

For information about the accessibility features of  $z/OS^{\otimes}$ , for users who have a physical disability, see Appendix B, "Accessibility," on page 651.

## Required product knowledge

To use this document effectively, you should be familiar with:

- DFSMSdfp
- DFSMShsm
- job control language (JCL)
- RACF (a component of Security Server for z/OS)
- IBM Support.

Readers of this publication are presumed to have a background in programming—especially programming with TSO commands—and in z/OS concepts and terms. This book is written primarily for the system programmer and storage administrator, both of whom must understand the information in z/OS DFSMS Introduction before reading this publication.

## z/OS information

This information explains how z/OS references information in other documents and on the web.

When possible, this information uses cross document links that go directly to the topic in reference using shortened versions of the document title. For complete titles and order numbers of the documents for all products that are part of z/OS, see z/OS Information Roadmap.

To find the complete z/OS library, go to the IBM Knowledge Center (http://www.ibm.com/support/knowledgecenter/SSLTBW/welcome).

## How to send your comments to IBM

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or provide any other feedback that you have.

Use one of the following methods to send your comments:

- 1. Send an email to mhvrcfs@us.ibm.com.
- 2. Send an email from the "Contact us" web page for z/OS (http://www.ibm.com/systems/z/os/zos/webqs.html).
- 3. Mail the comments to the following address:

**IBM** Corporation

Attention: MHVRCFS Reader Comments

Department H6MA, Building 707

2455 South Road

Poughkeepsie, NY 12601-5400

US

4. Fax the comments to us, as follows:

From the United States and Canada: 1+845+432-9405

From all other countries: Your international access code +1+845+432-9405

Include the following information:

- · Your name and address.
- · Your email address.
- Your telephone or fax number.
- The publication title and order number:

z/OS V2R1.0 DFSMSdss Storage Administration SC23-6868-02

- The topic and page number that is related to your comment.
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute the comments in any way appropriate without incurring any obligation to you.

IBM or any other organizations use the personal information that you supply to contact you only about the issues that you submit.

## If you have a technical problem

Do not use the feedback methods that are listed for sending comments. Instead, take one of the following actions:

- Contact your IBM service representative.
- Call IBM technical support.
- Visit the IBM Support Portal at z/OS support page (http://www.ibm.com/systems/z/support/).

## **Summary of changes**

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

## Summary of changes for z/OS Version 2 Release 1 (V2R1) as updated February 2015

The following changes are made for z/OS V2R1 as updated February, 2015.

### Changed

These topics are updated for Incremental FlashCopy Version 2, which supports
multiple Incremental FlashCopy targets: "Backing up and restoring volumes
with incremental FlashCopy" on page 60, "Using the FCINCRVERIFY keyword"
on page 61, "Using the FCWAIT keyword" on page 61, and
"FCINCREMENTAL" on page 330.

## Summary of changes for z/OS Version 2 Release 1 (V2R1) as updated September 2014

The following changes are made for z/OS V2R1 as updated September, 2014.

## Changed

- "DUMP command for DFSMSdss" on page 391 includes a ZCOMPRESS keyword, which specifies that DFSMSdss should write the dumped data in compressed format to the output medium using zEDC Services. This decreases the space occupied by the dumped data.
- "Protecting DFSMSdss functions with RACF FACILITY class profiles" on page 29 includes a new profile, STGADMIN.ADR.DUMP.ZCOMPRESS, which protects the use of ZCOMPRESS with the DUMP command.
- "ADRTAPB data area" on page 199
- "ADREID0 data area" on page 607.

## z/OS Version 2 Release 1 summary of changes

See the following publications for all enhancements to z/OS Version 2 Release 1 (V2R1):

- z/OS Migration
- z/OS Planning for Installation
- z/OS Summary of Message and Interface Changes
- z/OS Introduction and Release Guide

## **Part 1. DFSMSdss Storage Administration Guide**

## Chapter 1. Introduction to the DFSMSdss component of DFSMS

DFSMSdss is a direct access storage device (DASD) data and space management tool. DFSMSdss works on DASD volumes only in the z/OS environment.

You can use DFSMSdss to do the following tasks:

- Copy and move data sets between volumes of like and unlike device types. Like
  devices have the same track capacity and number of tracks per cylinder (for
  example, 3380 Model D, Model E, and Model K). In contrast, unlike DASD have
  different track capacities (for example, 3380 and 3390), a different number of
  tracks per cylinder, or both.
- Dump and restore data sets, entire volumes, or specific tracks
- Convert data sets and volumes to and from storage management subsystem (SMS) management
- Compress partitioned data sets
- · Release unused space in data sets
- Reduce or eliminate DASD free space fragmentation by consolidating free space on a volume, or consolidating data set extents.

## Understanding the role of DFSMSdss

To understand the role of DFSMSdss in an SMS environment, you need a basic understanding of SMS. Also, how you use DFSMSdss depends on which other DFSMS components are in use at your site, such as the DFSMShsm component.

## Managing user data with SMS

SMS allows you to match users' data characteristics (like data set organization, size, and format) to the characteristics of storage devices, without requiring users to know or to understand the hardware configuration at your site. With SMS, end users can store and retrieve data without being aware of space limitations, device characteristics, or volume serial numbers.

Using SMS, you can define allocation management criteria for the different types of data at your site. The values you specify identify your users' requirements for space, availability, and performance. You define these values to SMS as:

#### **Data Class**

A named list of data set allocation attributes that SMS assigns to a data set when it is created.

#### **Storage Class**

A named list of data set storage service attributes that identify performance and availability requirements. SMS uses these attributes to control data placement.

#### **Management Class**

A named list of management attributes that SMS uses to control DFSMShsm actions for data set retention, migration, backup, and release of allocated but unused space.

#### Storage Group

A named list of DASD volumes used for allocation of new SMS-managed data sets or for a dummy storage group.

Automatic class selection (ACS) is the SMS mechanism for assigning SMS classes and storage groups (also known as constructs). Depending on the DFSMSdss command you are using, SMS invokes some or all of the ACS routines in the following order:

- 1. Storage class ACS routine
- 2. Management class ACS routine
- 3. Storage group ACS routine

SMS uses the assigned constructs to automatically place and manage data and storage. For example, you can use a storage class to keep performance-sensitive data on high-speed storage devices and use management classes to control the movement of less active data to tape.

If there are WRITE statements in the SMS ACS routines, these are only displayed in the DFSMSdss output when the ACS routines return a nonzero return code. If DFSMSdss processes a data set successfully, then no WRITE messages are displayed.

**Related reading:** For more information about SMS, see the ACS routine information in *z*/*OS DFSMSdfp Storage Administration*.

## Sequential data striping

Extended-format sequential data sets and extended-format VSAM data sets, which must reside on SMS volumes, can be striped. Striping is a subtype of the basic record organizations: sequential and VSAM. With striping, the data is written across multiple volumes, with consecutive "loading units" being striped (applied) to different volumes. The "loading unit" for extended-format sequential data sets is a track. The "loading unit" for striped extended-format VSAM data sets is a control interval (CI).

Striping can reduce the processing time for batch jobs that process large data sets sequentially.

DFSMSdss can dump, restore, copy, or release space from a striped data set.

#### Note:

- 1. DFSMSdss treats a striped data set in the same way as it does other multivolume SMS data sets.
- DFSMSdss can convert a striped extended-format VSAM data set to extended-format during RESTORE processing. DFSMSdss can convert an extended-format sequential data set to sequential during RESTORE or COPY processing.

**Related reading:** For more information about striped data sets, see *z/OS DFSMS Implementing System-Managed Storage*.

## **Record counting**

DFSMSdss provides a means for verifying results of certain operations:

- Sequential extended-data sets—DFSMSdss performs and reports byte counting for logical data set COPY, DUMP, and RESTORE operations. The byte counts are reported in message ADR902I for copy, ADR903I for dump, and ADR906I for restore.
- Indexed VSAM data sets—DFSMSdss performs and reports record counting for logical data set DUMP and RESTORE operations if the VALIDATE support is used during the dump processing. VALIDATE processing is the default for dump.

During dump processing, the record count is reported in message ADR788I. In restore processing, message ADR788I is issued if the restore record count matches the dump count. Message ADR789W is issued if the dump and restore record counts differ and both the dump and restore record counts are provided.

**Related reading:** For more information about these messages, see *z/OS MVS System Messages, Vol 1 (ABA-AOM)*.

#### Installation exit routines

You can customize DFSMSdss by coding exit routines. The following installation exit routines are supplied with DFSMSdss:

#### Authorization installation exit routine (ADRUPSWD)

Forces authorization checking of protected data sets

#### Enqueue installation exit routine (ADRUENQ)

Forces enqueuing of the volume table of contents (VTOC)

#### Options installation exit routine (ADRUIXIT)

Can override any default or user-specified command options in the input stream

#### Reblock installation exit routine (ADRREBLK)

Allows DFSMSdss, during a data set copy or data set restore operation, to use the block size it selects for the target data set.

**Related reading:** For more information about these exit routines, see *z/OS DFSMS Installation Exits*.

## **Authorization checking**

**Related reading:** For information about authorization checking, see Chapter 20, "Data security and authorization checking," on page 531.

## Managing availability with DFSMSdss

DFSMSdss availability management consists of backing up data on DASD to tape and restoring from the backup if the original is lost, damaged, or inadvertently changed.

There are two general forms of backup:

#### Data set backup

Protects against the loss of individual data sets

#### Volume backup

Protects against the loss of a volume.

For data set backup, you can perform incremental backups to help reduce processing time while still meeting your backup requirements. Incremental backup means that data sets are backed up only if they have changed since their last backup.

Volume backups are used to protect against media failure. You can use volume backups in conjunction with incremental data set backups to recover a volume. As a result, you need not do volume backups as frequently. Incremental data set backups should be done daily and volume backups weekly. If a volume is lost for some reason, you can restore from the most recent volume backup and apply incremental data set backups to the volume to bring it back to its most current status.

#### Note:

- 1. If a large format data set is used as the output of a DUMP command, it cannot be used as input to a RESTORE command on a system that is prior to z/OS
- 2. If an extended format data set is used as the output of a DUMP command, it cannot be used as input to a RESTORE command on a system that is prior to z/OS V1R12.

## Backing up and restoring volumes and data sets

You can use the DFSMSdss DUMP command to back up volumes and data sets, and you can use the DFSMSdss RESTORE command to recover them. You can make incremental backups of your data sets by specifying a data set DUMP command with RESET and filtering on the data-set-changed indicator.

In an SMS environment, DFSMSdss saves the class names for the data sets it dumps. When you restore the data set to an SMS-managed volume, DFSMSdss invokes ACS and passes it the class names saved with the data set. Based upon this and other input from DFSMSdss (for example, class names specified with the STORCLAS or MGMTCLAS keywords), ACS assigns SMS constructs to each data set.

Because DFSMSdss restore invokes ACS, you can restore the data sets to SMS-managed volumes. Conversely, data sets backed up as SMS-managed data sets can be restored as non-SMS-managed data sets.

In addition to providing for routine backup requirements, you can use DFSMSdss to back up application data for disaster recovery and vital records purposes. You can back up all the data sets (including data that resides only on primary DASD; you cannot use DFSMSdss to process migrated data sets) that are associated with a particular application for disaster recovery or vital records by using DFSMSdss logical data set dump, and filtering on data set names. If you do not want to perform a separate dump operation for disaster recovery, you can specify more than one OUTDDNAME to create up to 255 separate backup copies when you do your routine backup. These extra copies can then be used for disaster recovery or vital records purposes. The DUMP command can also be used to archive data sets that have not been accessed for long periods of time.

## Using DFSMShsm for backup

The DFSMShsm component of DFSMS provides automated incremental backup, interactive recovery, and inventory of what it backs up. If DFSMShsm is used, you should use DFSMSdss for volume backup of data sets not supported by

DFSMShsm and for dumping SYSRES and special volumes such as the one containing the master catalog. If DFSMShsm is not installed, you can use DFSMSdss for all volume and data set backups.

## Using concurrent copy

Many online databases must be available at all times. If a backup is made while the data is being updated, the backup could be unusable or could require that a log be applied to the restored version to synchronize the data. The alternative is to synchronize all parts of the database and stop all update activity during the backup.

The concurrent copy (CC) function of DFSMSdss is a hardware and software solution that allows you to back up a database or any collection of data at a point in time and with minimum down time for the database. The database is unavailable only long enough for DFSMSdss to initialize a concurrent copy session for the data, which is a very small fraction of the time that the complete backup will take. The copy that is made will not include any of the update activity; it will be as if the backup were made instantaneously when it was requested. After initialization, DFSMSdss releases all the serialization it holds on the data, informs the user that the initialization is complete so that update activity may resume, and begins reading the data.

Be aware, however, that concurrent copy does not remove all data integrity exposures. For example, a DFSMSdss full-volume dump serializes the VTOC of the source volume, but does not serialize the data sets on the volume. This ensures that the existing data sets are not deleted or extended, and new data sets are not allocated. However, there is an exposure in that the data in the existing data sets can be changed. Without concurrent copy, this exposure exists for the entire duration of the dump. With concurrent copy, the exposure exists only during initialization.

#### Note:

- 1. If you are using concurrent copy on VM-format volumes, DFSMSdss does not serialize VM data in any way.
- 2. VM minivolumes are supported if you are using RAMAC Virtual Array (RVA) devices to the extent that they are supported by IBM Extended Facilities Product (IXFP) device reporting.

If a dump requestor does not stop all updating of the data sets during the concurrent copy session initialization, the backup data integrity is compromised.

If a concurrent copy operation fails after signaling that the concurrent copy initialization was complete (and update activity on the data has resumed), it is not possible to recover the data at the point-in-time at which the concurrent copy operation was started. This is because the data may have been updated while the copy operation was progressing.

#### Virtual concurrent copy

DFSMSdss uses virtual concurrent copy (VCC) to provide a concurrent copy-like function when the source device supports data set FlashCopy® or SnapShot.

During virtual concurrent copy, data is "flashed" or "snapped" from the source location to an intermediate location, and the data is gradually copied to the target location through standard I/O methods. The operation is logically complete after the source data is "flashed" or "snapped" to the intermediate location and physically complete after the data is moved to the target media.

The working space data set is used as an intermediate location for virtual concurrent copy. For more information, see "Virtual concurrent copy working space" on page 57.

## Using the stand-alone restore program of DFSMSdss

DFSMSdss stand-alone restore is a single-purpose program. It is designed to help you restore vital system packs during disaster recovery without relying on a z/OS environment.

You can restore the following from a physical dump:

- · A full volume or ranges of tracks
- Your system residence (SYSRES) volume, if your operating system fails to IPL.

**Related reading:** For more information about the DFSMSdss stand-alone restore program, see Chapter 19, "DFSMSdss stand-alone services," on page 511.

## Managing data movement with DFSMSdss

DFSMSdss can help you move data to replace devices, add capacity, and meet performance requirements. The three general types of data movement are data set, volume, and track movement.

## Moving data

Using the DFSMSdss COPY command, you can perform data set, volume, and track movement. The COPY command with DELETE causes DFSMSdss to delete the source data set after it successfully copies the data set.

The full-volume COPY command is useful for moving data between like devices. If you are moving volumes to like devices of larger capacity, generally you need a larger VTOC because the larger device can hold more data sets. DFSMSdss rebuilds indexed VTOCs and recognizes larger VTOCs on target volumes (as long as the target VTOC is outside the range of the source volume) when the VTOCs are moved to a like device of larger capacity.

For moving data between unlike devices, you must use the logical data set COPY command for all the data sets on the volume. DFSMSdss fills the tracks as completely as possible instead of just copying track for track. In addition, if the reblockable indicator is set on, the data set is reblocked to a system-determined block size efficient for the device.

## Moving data in an SMS-managed environment

In an SMS-managed environment, ACS routines and VTOC/Data Set Services (VDSS) determine the target volume in an SMS-managed environment.

DFSMSdss moves data sets to different volumes if their storage groups change. However, even if their storage groups do not change, DFSMSdss might move the data sets to a different location on the same volume or to different volumes. Target volumes selected by the user might not be honored.

If a new, empty volume is added to a storage group, data sets moved into that storage group are likely to be placed on that volume.

If a data set's storage class has the guaranteed-space attribute and the user specifies output volumes, the data set is placed on the SMS volumes specified in the volume list if:

- All SMS-managed volumes specified with the OUTDDNAME or OUTDYNAM keyword belong to the same storage group.
- The ACS storage group routine assigns the data set to the storage group that contains the specified SMS volumes.

**Note:** SMS-managed data sets must be cataloged in the standard order of search.

**Related reading:** For more information about SMS, see *z/OS DFSMSdfp Storage* Administration.

## Moving data with concurrent copy

Concurrent copy and virtual concurrent copy can be used during copy as well as dump.

Related reading: For more information about concurrent copy and how to use it, see "CONCURRENT" on page 316.

## Moving data with FlashCopy

FlashCopy is faster than traditional methods of data movement, especially for moving large amounts of data. DFSMSdss can use the FlashCopy feature of the Enterprise Storage Server® (ESS) to quickly move the data from the source location to the target location. The source devices and the target devices must be in the same ESS, and the data to be moved must not need manipulation.

Related reading: For more information about moving data using FlashCopy, see Chapter 7, "Managing data movement with DFSMSdss," on page 97.

## Moving data with SnapShot

DFSMSdss can use SnapShot to quickly move the data from the source location to the target location. The source and target devices must be in the RAMAC Virtual Array (RVA) and the data must not need to be manipulated. SnapShot is much faster than traditional methods, especially when large amounts of data are moved.

Related reading: For more information about moving data using SnapShot, see Chapter 7, "Managing data movement with DFSMSdss," on page 97.

## Converting data to and from SMS management

DFSMSdss is the primary tool for converting data to and from SMS management. There are two ways of converting data:

- Conversion of data sets with data movement
- · Conversion of volumes without data movement

The following sections briefly describe these two kinds of conversion.

## Converting data sets with data movement

To convert data sets by data movement, use the DFSMSdss COPY or DUMP/RESTORE command. When moving data sets from non-SMS-managed volumes to SMS-managed volumes, DFSMSdss invokes ACS, which may assign class names to the data sets. Alternatively, you can specify the BYPASSACS and STORCLAS keywords with the COPY or RESTORE command to force the data sets to be SMS-managed.

When moving data sets out of SMS management, specify the BYPASSACS and NULLSTORCLAS keywords with the COPY or RESTORE command. DFSMSdss then bypasses ACS and drops the data set's class names. ACS can also make data sets non-SMS-managed.

Related reading: For more information about converting data sets, see Chapter 8, "Converting data to and from SMS management," on page 141.

## Converting volumes without data movement

To convert volumes to and from SMS management without data movement, you can use the DFSMSdss CONVERTV command. This command lets you:

- Prepare a volume for conversion. Using the PREPARE keyword, you can stop new allocations and data set extensions to another volume while still allowing access to the data on the volume.
- Convert a volume to SMS management. Using the SMS keyword, you can convert a volume and all its data sets to SMS management.
- Convert a volume from SMS management. Using the NONSMS keyword, you can remove a volume and its data sets from SMS management.
- Simulate conversion. Using the TEST keyword, you can verify that the volume and its data sets are eligible for conversion and see what class names ACS would assign to the data sets.

**Related reading:** For more information about converting volumes, see Chapter 8, "Converting data to and from SMS management," on page 141.

## Managing space with DFSMSdss

DFSMSdss provides the following functions to help you manage DASD space:

#### **COMPRESS**

Compresses your partitioned data sets by taking unused space and consolidating it at the end of the data set. To make the unused space available for other data sets, you must use the RELEASE command. This does not apply to PDSEs.

#### **CONSOLIDATE**

Performs data set extent consolidation or reduction on a volume.

#### **DEFRAG**

Consolidates the free space on a volume to help prevent out-of-space abends on new allocations.

#### **DUMP/RESTORE**

Deletes unwanted data sets and combines data set extents. (You can also use the COPY command to combine data set extents.)

#### **RELEASE**

Releases the unused space in sequential, partitioned, and extended-format VSAM data sets for use by other data sets.

**Related reading:** For more information about managing space, see Chapter 9, "Managing space with DFSMSdss," on page 151.

## Chapter 2. Requirements for running DFSMSdss

This topic describes the requirements for running DFSMSdss.

## Understanding the operating environment

DFSMSdss is exclusive to z/OS and is available only as a component of z/OS.

You can run the DFSMSdss stand-alone restore program on an IBM System  $z^{\otimes}$  server in S/390 $^{\otimes}$  mode, or on an IBM System 390 server in S/390 mode or S/370 mode. The available modes are dependent on your CPU type and model.

Additionally, you can run the DFSMSdss stand-alone restore program on a z/VM<sup>®</sup> virtual machine in XA mode.

## Storage requirements

In most cases, you can let DFSMSdss determine the amount of storage it uses for an operation. Sometimes, however, you might want closer control of the amount of storage DFSMSdss uses. Use the storage estimates in this topic as a starting point for determining minimum region sizes in which DFSMSdss can run. Table 1 on page 12 and Table 2 on page 12 show the minimum storage requirements, in bytes, to run each DFSMSdss operation. Table 3 on page 12 shows the minimum storage requirements, in bytes, to restore partitioned and VSAM data sets to unlike devices. The legend for Table 1 on page 12, Table 2 on page 12, and Table 3 on page 12 is displayed beneath Table 3 on page 12. The values include the storage required to load the DFSMSdss program into the region.

Storage requirements depend on your operating system configuration and your device and data set characteristics. The storage requirement estimates shown for the COPY, DUMP, and RESTORE commands are only for the full-volume copy, dump, and restore operations; they might vary for a data set operation.

If DFSMSdss determines that the storage requirements are greater than the storage available during processing, DFSMSdss issues error message ADR376E to indicate this. The out-of-storage condition might cause abend 80A during DFSMSdss postprocessing.

If you use buffers above 16 megabytes virtual storage, the buffer size is allocated independently of the region size.

If you use the PARALLEL command to run two or more DFSMSdss tasks concurrently, the total storage required is the sum of the storage required for all functions to be run in parallel. However, because DFSMSdss is reentrant, the DFSMSdss code is not duplicated in storage. Therefore, do not include the DFSMSdss load module size more than once.

Table 1. Minimum Storage Requirements for DFSMSdss Operations with I/O Buffers below 16-Megabyte Virtual

DFSMSdss	
Command	Storage Requirements
COMPRESS	dsssize + (2 * trksize of largest device) + (number of additional volumes, up to five * copysize)
CONVERTV	dsssize + (buffersize * 5)
COPY (FULL)	dsssize + (trksize * 5)
COPYDUMP	dsssize + (buffersize * 5)
DEFRAG	dsssize + (trksize * 5) + (16KB if VSAM present) + (1KB * number of non-VSAM entries in VVDS)
DUMP (FULL) OPT(1)	dsssize + (buffersize * 7)
DUMP (FULL) OPT(2)	dsssize + (buffersize * 6)
DUMP (FULL) OPT(3)	dsssize + (buffersize * 15)
DUMP (FULL) OPT(4)	dsssize + (buffersize * (3 * trk/cyl))
PRINT	dsssize + (3 * trksize)
RELEASE	dsssize + trksize
RESTORE (FULL)	dsssize + copysize + (buffersize * 6)

Table 2. Minimum Storage Requirements for DFSMSdss Operations with I/O Buffers above 16-Megabyte Virtual

DFSMSdss Command	Storage Below 16MB Virtual	Storage Above 16MB Virtual
COMPRESS	dsssize + (number of additional volumes, up to five * copysize)	2 * trksize of largest device
CONVERTV	dsssize	buffersize * 5
COPY (FULL)	dsssize	trksize * 5
COPYDUMP	dsssize	buffersize * 5
DEFRAG	dsssize + (16KB if VSAM present) + (1KB * number of non-VSAM entries in VVDS)	(trksize * 5) + (152 * number of data set extents) + (144 * number of VSAM components) + (48 * number of non-VSAM data sets)
DUMP (FULL) OPT(1)	dsssize	buffersize * 7
DUMP (FULL) OPT(2)	dsssize	buffersize * 6
DUMP (FULL) OPT(3)	dsssize	buffersize * 15
DUMP (FULL) OPT(4)	dsssize	buffersize * (3 * trk/cyl)
PRINT	dsssize	3 * trksize
RELEASE	dsssize	trksize
RESTORE (FULL)	dsssize	buffersize * 6

Table 3. Minimum Storage Requirements for a Restore to an Unlike Device

Type of Data Set	Storage Requirements
Partitioned Data Sets	dsssize + (((trksize + 64) * 5) + 8KB)
VSAM Data Sets	dsssize + (((trksize + 64) * 5) + (2 * maximum record size) + (3 * buffspace))

**Legend:** This legend applies to Table 1 on page 12, Table 2 on page 12, and Table 3 on page 12.

**KB** 1024 bytes.

#### dsssize

DFSMSdss load module size, 2065KB.

#### copysize

IEBCOPY load module size + IEBCOPY storage requirements below the 16MB line (that is, 1MB minimum, or 2MB if the data set being compressed has more than 1000 members).

#### buffersize

256KB is the default for I/O to tape unless DFSMSdss is forced to use a smaller size. Otherwise, it is the maximum of the largest trksize used or 32KB.

#### buffspace

Buffer space specified in the DEFINE command when the data set was allocated.

#### trksize

The size, in bytes, of a track on your DASD volume.

#### trks/cyl

The number of tracks per cylinder on your DASD volume.

## Hardware requirements

You can use DFSMSdss with all IBM DASD, magnetic tape devices, system consoles, printers, and card readers that are supported by DFSMS.

#### Note:

- 1. VSAM-extended addressability requires a cached storage subsystem that has concurrent copy-capable licensed internal code.
- 2. DFSMSdss does not support virtual input/output (VIO) devices.
- 3. When running DFSMSdss operations against storage devices that do not support 64-bit real addressing, you must tell DFSMSdss not to use the I/O buffers that can be backed above the 2–gigabyte bar. This can be done by either specifying ZBUFF64R=OFF on the EXEC statement in your JCL or by turning off the UFPZB64R bit in ADRUFO block with the Options Installation Exit Routine, ADRUIXT.

#### **Volume formats**

You can use DFSMSdss with the following DASD volume formats:

- Volumes with indexed VTOCs, see "Indexed VTOC" on page 14 for details.
- · Volumes with nonindexed VTOCs
- OS/VS minivolumes in a VM environment
- VM-formatted volumes (full or mini) with an OS-compatible VTOC beginning on track zero, record five.

All DASD volumes used by DFSMSdss must be initialized by Device Support Facilities (ICKDSF) and be mounted and online.

Note: You cannot use concurrent copy on minivolumes of any format unless they are on an RVA. However, you can use concurrent copy on full VM-format volumes that contain minivolumes to the extent that they are supported by IBM Extended Facilities Product (IXFP) device reporting.

### **Indexed VTOC**

DFSMSdss recognizes three different formats for a VTOC index:

- SYS1.VTOCIX.Vvolser
- SYS1.VTOCIX.volser
- SYS1.VTOCIX.Volser.

If the first character of a VOLSER is numeric, DFSMSdss renames it (or prefixes it) so that the VOLSER begins with the letter "V." For example:

- If a VOLSER is 12345, DFSMSdss renames it to V12345
- If a VOLSER is 123456, DFSMSdss renames it to V23456.

## Data set organizations

DFSMSdss can copy, dump, and restore data sets of the following types:

- DB2<sup>®</sup>
- · Direct access
- EXCP (execute channel program)
- Partitioned, including:
  - PDS (partitioned data set)
  - PDSE (partitioned data set extended)
  - HFS (hierarchical file system) data set
- Sequential, including extended-format data sets and Large Format data sets
- VSAM data sets that are cataloged in an ICF catalog, including:
  - ESDS (entry-sequenced data set)
  - KSDS (key-sequenced data set)
  - KSDS with key ranges
  - LDS (linear data set)
  - RRDS (relative record data set)
  - VRRDS (variable relative record data set)
  - Extended-format ESDS, KSDS, LDS, RRDS, and VRRDS, including striped ESDS, KSDS, LDS, RRDS, and VRRDS
  - Extended-addressable VSAM ESDS, KSDS, LDS, RRDS, and VRRDS, including striped ESDS, KSDS, LDS, RRDS, and VRRDS
  - zFS (z/OS File System) data set
- Unmovable data set types (PSU, POU, DAU, ABSTR, ISU, and direct with OPTCD=A).

#### Note:

- 1. DFSMSdss does not provide conversion between non-extended-format VSAM and extended-format VSAM.
- 2. DFSMSdss cannot be used to process migrated data sets.
- 3. DFSMSdss cannot be used to process VSAM data sets that are cataloged in a catalog that is outside of the standard order of search.

### Temporary data set names

DFSMSdss must allocate the following temporary data sets to perform certain functions such as copy and restore. The high-level qualifiers of those data set names can be protected, and your installation must ensure that these temporary data sets can be allocated.

#### Message data set—

Allocated by DFSMSdss to store messages. This data set lets DFSMSdss print out messages by task rather than intermixing them. This data set is deleted when DFSMSdss completes the operation. System-generated temporary names are used.

#### Special DEFRAG or CONSOLIDATE data set—

Allocated by DFSMSdss to contain information about relocated DASD extents. The data set name is in the following format:

SYS1.DFDSS.DEFRAG.xxxxxxxx.volser.DUMMY

where *xxxxxxxx* represents 8 bytes of X'FF', and *volser* is the volume serial number of the volume being defragmented. The data set is deleted when the DEFRAG or CONSOLIDATE operation ends successfully.

If the operation is interrupted (for example, if DFSMSdss is canceled), the data set is left on the volume. To delete the data set, repeat the DEFRAG or CONSOLIDATE operation. Before doing so, however, observe the following considerations:

- Determine whether you need to convert the index VTOC (IXFORMAT) volume to a non-indexed VTOC (OSFORMAT) before rerunning the DEFRAG or CONSOLIDATE operation. Otherwise, the volume free space values might be incorrect.
- Use the hexadecimal qualifier to prevent the deletion of this data.

#### Temporary copied data sets

Allocated by DFSMSdss when a copy is performed and deleted when the copy is completed.

The format of the temporary name depends on the number of qualifiers of the data set being copied:

Number of qualifiers (n)	Temporary name
1	dsnhlq.Atidasid. <i>chmmsstt</i>
2	First 2 qualifiers.Atidasid.chmmsstt
>2	First 3 qualifiers.Atidasid.chmmsstt

The next to last qualifier, Atidasid, is a combination of a fixed "A" character followed by a task id (tid) and an address space id (asid).

The last qualifier is chmmsstt where *c* is:

Target cluster name
 Target data component name
 Target index component name
 Source cluster name
 Source data component name
 Source index component name

- P Source path name
- **Q** Target path name

and hmmsstt is the time stamp information in low-order hours digits (h), minutes (mm), seconds (ss), and hundredths of a second (tt).

**Note:** In the course of copying data sets, DFSMSdss renames the source data set using the above conventions. Whenever DFSMSdss renames a data set that is protected by RACF<sup>®</sup>, a component of the Security Server for z/OS, to a temporary name a RACF profile must exist for the temporary data set name.

### Temporary copied catalogs

Allocated by DFSMSdss when it copies a catalog. When DFSMSdss copies a catalog, two temporary data sets are used.

First, DFSMSdss allocates a temporary data set into which records are temporarily exported. The export data set name format is:

 ${\tt CATHLQ.EXPORT.T} hmmsstt$ 

· where,

### **CATHLQ**

The first three high-level qualifiers of the catalog that is being copied.

hmmsstt

The time-stamp information in low-order hours digits (h), minutes (mm), seconds (ss), and hundredths of a second (tt).

Second, DFSMSdss allocates a temporary catalog. The temporary catalog name format is:

CATHLQ.Thmmsstt

· where,

#### **CATHLO**

The first four high-level qualifiers of the catalog being copied.

hmmsstt

The time-stamp information in low-order hours digits (h), minutes (mm), seconds (ss), and hundredths of a second (tt).

#### Dummy data set-

Allocated by DFSMSdss when copying or restoring volumes and an indexed-VTOC needs rebuilding or the volume free-space values need recalculating. The data set name is in the following format:

SYS1.VTOCIX.DSS.TEMP.volser

where *volser* is the volume serial number of the restored volume. Allocation of this data set is never successful because DFSMSdss uses dummy allocation values.

# Chapter 3. Logical and physical processing and data set filtering

Before you begin using DFSMSdss, you should understand the difference between logical and physical processing and how to use data set filtering to select data sets for processing. This topic describes these two aspects of DFSMSdss.

### **Defining logical and physical processing**

DFSMSdss can perform two kinds of processing when executing COPY, DUMP, and RESTORE commands:

- Logical processing operates against data sets independently of physical device format.
- *Physical processing* moves data at the track-image level and operates against volumes, tracks, and data sets.

Each type of processing offers different capabilities and advantages.

During a restore operation, the data is processed the same way it is dumped because physical and logical dump tapes have different formats. If a data set is dumped logically, it is restored logically; if it is dumped physically, it is restored physically. A data set restore operation from a full-volume dump is a physical data set restore operation.

### Logical processing

A logical copy, dump, or restore operation treats each data set and its associated information as a logical entity, and processes an entire data set before beginning the next one.

Each data set is moved by tracks from the source device and is potentially written to the target device as a set of data records, allowing data movement between devices with different track and cylinder configurations. Checking of data record consistency is not performed during dump operations.

DFSMSdss performs logical processing if:

- You specify the DATASET keyword with the COPY command. A data set copy is always a logical operation, regardless of how or whether you specify input volumes.
- You specify the DATASET keyword with the DUMP command, and either no input volume is specified, or LOGINDDNAME, LOGINDYNAM, or STORGRP is used to specify input volumes.
- The RESTORE command is performed, and the input volume was created by a logical dump.

DFSMSdss uses catalogs or VTOCs to select data sets for logical processing. If you do not specify input volumes, DFSMSdss uses the catalogs to select data sets for copy and dump operations. If you specify input volumes using the LOGINDDNAME, LOGINDYNAM, or STORGRP keywords on the COPY or DUMP command, DFSMSdss uses VTOCs to select data sets for processing.

Note: To copy or dump entire multivolume data sets, you do not need to specify all the volumes in the LOGINDDNAME or LOGINDYNAM volume list. However, you must specify the SELECTMULTI keyword with either the FIRST or ANY subkeywords.

### When to use logical processing

Use logical processing for the following situations:

- Data is copied to an unlike device type. Logical processing is the only way to move data between unlike device types.
- Data that may need to be restored to an unlike device is dumped. Data must be restored the same way it is dumped. This is particularly important to bear in mind when making backups that you plan to retain for a long period of time (such as vital records backups). If a backup is retained for a long period of time, it is possible that the device type it originally resided on will no longer be in use at your site when you want to restore it. This means you will have to restore it to an unlike device, which can be done only if the backup was made logically.
- Aliases of VSAM user catalogs are to be preserved during copy and restore functions.
  - Aliases are not preserved for physical processing.
- · Unmovable data sets or data sets with absolute track allocation are moved to different locations.
- Multivolume data sets are processed.
- VSAM and multivolume data sets are cataloged as part of DFSMSdss processing.
- Data sets are deleted from the source volume after a successful dump or copy operation.
- Non-VSAM and VSAM data sets are renamed after a successful copy or restore operation.
- You want to rename data sets through the application program interface (API) during logical dump processing.
- You want to control the percentage of space allocated on each of the output volumes for copy and restore operations.
- You want to copy and convert a PDS to a PDSE or vice versa.
- You want to copy or restore a data set with an undefined DSORG to an unlike device.
- You want to keep together all parts of a VSAM sphere.

# Physical processing

Physical processing moves data based on physical track images. Because data movement is carried out at the track level, only target devices with track sizes equal to those of the source device are supported. Physical processing operates on volumes, ranges of tracks, or data sets. For data sets, it relies only on volume information (in the VTOC and VVDS) for data set selection, and processes only that part of a data set residing on the specified input volumes.

#### Note:

1. VSAM data sets are *not* cataloged during physical processing within SMS or non-SMS environments. The CATALOG keyword is ignored for VSAM data sets during physical restore. Use IDCAMS DEFINE RECATALOG to catalog the data sets after the physical restore.

2. The RENAME keyword is only supported for non-VSAM data sets during physical data set restore. VSAM Alternate Indexes (AIX) cannot be renamed during physical data set copy or restore.

DFSMSdss performs physical processing when the following conditions exist:

- You specify the FULL or TRACKS keyword with the COPY or DUMP command. This results in a physical volume or physical tracks operation.
  - Attention: Take care when invoking the TRACKS keyword with the COPY and RESTORE commands. The TRACKS keyword should be used only for a data recovery operation. For example, you can use it to "repair" a bad track in the VTOC or a data set, or to retrieve data from a damaged data set. You cannot use it in place of a full-volume or a logical data set operation. Doing so could destroy a volume or impair data integrity.
- You specify the DATASET keyword on the COPY or DUMP command and input volumes with the PHYSINDDNAME or PHYSINDYNAM keyword. This produces a physical data set copy or physical data set dump.
- The RESTORE command is executed and the input volume is created by a physical dump operation.

### When to use physical processing

Use physical processing when the following conditions exist:

- Backing up system volumes that you might want to restore with the DFSMSdss stand-alone restore program (for physical dump tapes only).
- · Performance is an issue.
  - Generally, the fastest way—measured by elapsed time—to copy or to dump an entire volume is with a physical full-volume command. This is primarily because minimal catalog searching is necessary for physical processing.
- Substituting one physical volume for another or recovering an entire volume. With a COPY or RESTORE (full-volume or track) command, the volume serial number of the input DASD volume can be copied to the output DASD volume.
- Dealing with I/O errors. Physical processing provides the capability to copy, dump, and restore a specific track or range of tracks.
- Dumping or copying between volumes of the same device type but different capacity.

# Data integrity considerations

In some circumstances, DFSMSdss can detect and correct inconsistencies while processing data. For example, DFSMSdss checks to verify the reliability of a partitioned data set (PDS) directory before it uses the PDS. You can also use the CHECKVTOC keyword to instruct DFSMSdss to perform additional consistency checking on the VTOC before data processing begins on that volume.

If you are creating backups as part of disaster recovery preparedness, you may want to take additional steps to ensure the validity of that data. You can establish validity before you invoke DFSMSdss, or as part of the DFSMSdss invocation.

Note: Periodically running the Access Method Services DIAGNOSE function to reorganize VSAM data sets establishes validity before you invoke DFSMSdss. However, not specifying the NOPACK keyword establishes validity as part of the DFSMSdss invocation. In this case, DFSMSdss verifies the PDS directory. If you specify the CHECKVTOC keyword, DFSMSdss performs consistency checking on the VTOC.

The choice between logical and physical processing depends on the expected type of abnormal condition (if any). Neither processing mode provides a significantly higher level of data integrity. Logical processing and physical processing are simply different views of the same data. One mode could detect a condition that the other mode would miss. For example, a frequent PDS abnormal condition that does not cause problems during physical processing might cause problems during logical processing. On average, the selected DFSMSdss processing mode should closely mirror the mode in which you typically access data. Generally, logical processing is the most applicable choice.

### Broken data set considerations

Broken data sets are data sets that do not comply with defined z/OS data set standards. These include data sets for which catalog entries, VTOC entries, or VSAM volume data set (VVDS) entries are either missing or invalid. DFSMSdss might not properly select broken data sets for processing because it relies on the validity of these structures during filtering.

### Choosing data sets for processing—filtering

You can select data sets for DFSMSdss processing by filtering on specified criteria. DFSMSdss can filter on fully qualified or partially qualified data set names (by using the INCLUDE or EXCLUDE keyword) and on various data set characteristics (by using the BY keyword).

You can filter data sets with any of the following commands:

- COMPRESS
- CONSOLIDATE
- · Data set copy
- Logical data set copy
- Logical data set dump
- · Logical data set restore
- Physical data set copy
- Physical data set dump
- Physical data set restore
- RELEASE

At least one of the INCLUDE, EXCLUDE, or BY parameters must be specified with the above commands.

Note: DFSMSdss cannot serialize all of the data sets being considered during filter processing. It is possible that, between the time when DFSMSdss does the filtering and builds the list of data sets to process and the time when DFSMSdss actually processes the data sets, some or all of the data sets may be moved, deleted, or migrated. The status of the moved, deleted, or migrated data sets will therefore have changed by the time they are processed, which may in turn cause the DFSMSdss operation to fail.

The following sections briefly describe what can be filtered and how to use the available criteria.

# Filtering by data set names

Using the INCLUDE or EXCLUDE keyword, you can filter on fully qualified or partially qualified data set names. A fully qualified data set name is one in which all qualifiers are completely spelled out. For example:

```
(INCLUDE(SYS1.UTIL3.LOAD))
```

A partially qualified data set name is one in which the qualifiers are not completely spelled out. Using asterisks (\*) and percent signs (%), you can select data sets without specifying their fully qualified names.

The single asterisk (\*) is used in place of one qualifier. For example:

```
(INCLUDE(ABC.*.LOAD))
```

This partially qualified name matches ABC.DEF.LOAD and ABC.XYZ.LOAD. The single \* is also used to indicate that only part of a qualifier has been specified. For example, if you want to filter using only the first three characters of the first qualifier of a name, specify it as follows:

```
(INCLUDE(SYS*.**))
```

This partially qualified name matches data sets whose first qualifier was SYS1 and SYS1A. The other qualifiers in the data set name are ignored.

When used with other qualifiers, the double asterisk (\*\*) indicates that one or more leading, trailing, or middle qualifiers do not exist or they do not play a role in the selection process. For example:

```
(INCLUDE(**.LOAD))
```

This partially qualified name selects any data set with LOAD as its last qualifier (such as data sets named LOAD, ABC.LOAD, and ABC.DEF.LOAD).

The percent sign (%) is used as an ignore character. Each % sign represents one character in the name being filtered, and any character in that position is ignored. One or more % signs can be specified in any qualifier. For example:

```
(INCLUDE(SYS1.A%%B))
```

This partially qualified name matches SYS1.AZZB and SYS1.AXYB, but not SYS1.AXXXB.

# Filtering by data set characteristics

The BY parameter can filter for the following data set characteristics:

Keyword

Criteria

ALLOC

Allocation type (cylinder, track, block, absolute track, or movable)

#### **CATLG**

Whether a data set is cataloged or not (using the standard catalog search order)

#### **CREDT**

Creation date (absolute or relative)

#### **DATACLAS**

Data class for SMS

#### **DSCHA**

Whether the data-set-changed indicator is on

#### **DSORG**

Data set organization (SAM, PAM, PDS, PDSE, BDAM, EXCP, HFS, ISAM, VSAM, or zFS)

#### **EXPDT**

Expiration date (absolute or relative)

#### **EXTNT**

Number of extents

**FSIZE** Data set size (number of allocated or used tracks)

#### **MGMTCLAS**

Management class for SMS

#### **MULTI**

Whether the VTOC shows that the data set is single-volume or multivolume (allocated single-volume data sets that have never been opened and are not cataloged may be selected as multivolume).

#### **REFDT**

Last-referenced date (absolute or relative)

### **STORCLAS**

Storage class for SMS

You can use any of the following operators with the BY keyword:

### Operator

Meaning

EQ or =

Equal to

LT or <

Less than

LE or <=

Less than or equal to

GT or >

Greater than

GE or >=

Greater than or equal to

NE or  $\neg =$ 

Not equal to

When you specify multiple arguments for an NE operation, DFSMSdss selects only those data sets not matching any of the arguments. When you specify multiple arguments for an EQ operation, DFSMSdss selects those data sets matching any of the arguments.

### Some examples of filtering by data set characteristics

If you use the following specification of the BY keyword, DFSMSdss selects all data sets allocated in cylinders:

```
BY( ALLOC, EQ, CYL )
```

You can specify more than one criterion with the BY keyword. The following example selects all data sets allocated in cylinders and whose management class is MCNAME1:

```
BY(( ALLOC,EQ,CYL ) ( MGMTCLAS,EQ,MCNAME1 ))
```

You can specify multiple arguments for any of the filtering criteria. The following example selects all data sets that have a data class of DCNAME1 or DCNAME2:

```
BY( DATACLAS, EQ, (DCNAME1, DCNAME2) )
```

### The FILTERDD keyword

The FILTERDD keyword must be used if you have more than 255 entries in the INCLUDE, EXCLUDE, or BY filtering lists. The FILTERDD keyword specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set that contains the filtering criteria to be used. This is in the form of card-image records, in DFSMSdss command syntax, that contain the INCLUDE, EXCLUDE, and BY keywords.

# Uses of filtering

You will make the best use of filtering by data set names if you use meaningful naming conventions. Your naming conventions should allow you to identify large groups of data sets that can be treated similarly. With such conventions, you can use data set name filtering to select large groups of data sets against which you can run DFSMSdss functions.

Suppose you are a storage administrator and you want to do a daily backup of all payroll data sets that have changed since they were last backed up. If the data sets you want to back up have some identifying qualifiers (for example, PAYROLL.FEDTAX), you can select them by coding:

Filtering by data set characteristics also lets you process large groups of data sets. You can use BY criteria to:

- Filter on the data-set-changed indicator to back-up only those data sets that have not been backed up since they were last updated.
- Filter to select uncataloged data sets for deletion as a means of enforcing cataloging.
- Filter to select data sets whose expiration date passed for deletion.
- Filter on the last referenced date to archive or delete data sets that have not been referenced for a long period of time (for example, 18 months).
- Filter on data set size to ensure that when you use the COMPRESS and RELEASE commands, you compress and release space only in data sets where the savings may be significant.
- Filter on management class to perform space management (if in an SMS-managed environment).

It is possible to pass DFSMSdss filtering criteria in a data set by using the FILTERDD keyword. If you do this, the data set should have the following characteristics:

- · RECFM=F or FB
- LRECL=80
- BLKSIZE=80 for F (or a multiple of 80 for FB).

# **Chapter 4. Invoking DFSMSdss**

You can use the following methods to invoke DFSMSdss:

- Interactive Storage Management Facility (ISMF)
- Job control language (JCL)
- The application interface.

### Invoking DFSMSdss with ISMF

You can use the menu-driven panels of ISMF to build job streams for many DFSMSdss space management and backup functions. ISMF supports the DFSMSdss commands COMPRESS, CONVERTV, COPY, DEFRAG, DUMP, RELEASE, and RESTORE.

The information you supply on ISMF panels is used to build and submit job streams like those you generate using JCL and DFSMSdss commands. Using ISMF panels, you do not have to remember DFSMSdss keywords and syntax. Simply fill in the values you want on the panels, and ISMF generates the job stream. You can then either submit the job or save the job stream for later use.

Using ISMF panels, you can build a list of data sets or volumes according to criteria that you provide. The list provides information about each volume or data set (for example, allocated space and percent of unused space). You can use the list to analyze and manage your data and storage more efficiently.

### How to invoke ISMF

You invoke ISMF by logging on to TSO. If ISMF is installed as an option on the ISPF Master Application Menu or as an option on the ISPF/PDF Primary Option Menu, specify the selection option that corresponds to ISMF. You can use ISMF to perform DFSMSdss functions against one or more data sets or volumes on a list you create. Extensive help screens are available for all the DFSMSdss functions supported by ISMF.

**Related reading:** For more information, see *z/OS DFSMS Using the Interactive Storage Management Facility*.

# Invoking DFSMSdss with JCL

DFSMSdss is controlled by JCL statements and DFSMSdss commands. You can use the JCL statements to invoke DFSMSdss and to define the data sets used and created by it. The JCL defines the DFSMSdss commands that specify and control tasks.

**Related reading:** For JCL information and examples, see the topic on specifying DFSMSdss commands in Chapter 15, "Specifying DFSMSdss commands," on page 249.

# Invoking DFSMSdss with the application interface

This topic documents General-Use Programming Interface and Associated Guidance Information.

You can invoke DFSMSdss from an application program by using the application interface. This allows you, for example, to gather statistical or auditing information and to specify control variables.

The application interface allows you to:

- · Fully utilize the invocation capabilities of DFSMSdss when the ATTACH, LINK, or CALL system macro is specified in your application program.
- Optionally, specify a list of parameters to be used by DFSMSdss during the processing caused by that invocation.
- Optionally, interact with DFSMSdss during processing of user installation options after the installation options exit has been called.
- Optionally, interact with DFSMSdss during the processing at convenient points where input/output (I/O) operations are being performed.

**Note:** DFSMSdss runs as an authorized problem program (nonsupervisor state); any program invoking DFSMSdss must also be authorized and in non-supervisor state.

Related reading: For more information about the application interface, see Chapter 22, "Application programming interface," on page 577.

### User interaction module exit functions

When DFSMSdss is invoked from an application program, you can use the user interaction module (UIM) to interact with DFSMSdss at points where I/O operations are being performed. UIM exit functions can be used to:

- Replace, insert, delete, or modify a SYSIN record after DFSMSdss has read it or a SYSPRINT record when DFSMSdss is ready to print it.
- Replace, insert, delete, or modify a write-to-operator message before DFSMSdss writes it.
- Insert a statistics record during a logical dump operation.
- Modify the installation options specified in the ADRUFO control block to override the specified options.
- Bypass password and expiration-date checking, or reject the tape volume and request a scratch tape, when DFSMSdss is ready to open a tape.
- Request a specific volume serial when a nonspecific tape is passed to DFSMSdss.
- Get information about the data set being allocated.
- End a task or processing of individual data sets.
- Bypass authority checking for individual data sets. This includes both RACF and password authorization.
- Bypass serialization checking of individual data sets.
- Show the status of the concurrent copy initialization.
- Specify some information on how a new target data is allocated.

Related reading: For more information about UIM exit functions, see Chapter 23, "Examples of the application program with the user interaction module (UIM)," on page 625.

# **Chapter 5. Protecting DFSMSdss functions**

You can protect DFSMSdss/ISMF functions and some DFSMSdss keywords. This topic discusses the functions of DFSMSdss for which you can control access through the RACF element of z/OS Security Server.

### Protecting DFSMSdss and ISMF functions with RACF

You can set authorization levels for the following ISMF elements by using the program control feature of the z/OS Security Server RACF component:

- ISMF itself
- Each of the ISMF applications
- The individual line operators and commands

The RACF report process and logging process for each ISMF function that you identify also includes the RACF element for authorization checking. You can also use standard RACF authorization checking to limit access to individual data sets, volumes, or catalogs. Used in conjunction with program control, authorization checking ensures that the appropriate ISMF data and functions are available to users when they need them.

### ISMF functions you might want to protect

Program control allows you to determine the ISMF functions to which users have access. The authorization scheme you set up can apply to both individual users and user groups. The ISMF functions you can protect fall into two general categories: line operators and commands.

With program control, you can set up authorization levels for each category. You can also vary the level within a category to suit the needs of your site. Before you set up an authorization structure, consider the following:

- Do you want all users at your site to have access to ISMF?
- Do you want all users to have access to the data set, volume, or profile applications?
- · Are there line operators or commands to which you want to limit access?

# Setting up the authorization structure

RACF program control checks authorization before allowing access to an ISMF function. Protection for each function is based on the authorization level of the load module that contains the function. A user is allowed to execute an ISMF function (for example, the RESTORE list command) when one of the following is true:

- The user is authorized to execute the load module corresponding to the function requested. Authorization is defined as READ level access or greater.
- The user's RACF profile has the OPERATIONS attribute.
- The user's group is authorized to execute the load module.
- The universal access authority (UACC) for the load module is READ or greater. This makes the load module available to anyone who can access ISMF.

### Finding the DFSMSdss/ISMF module names

### **Programming Interface Information**

The names of the load modules for DFSMSdss/ISMF are stored in command tables in both the panel library, DGTPLIB, and the load library, DGTLLIB. The load module names are listed in Table 4 and Table 5. The module names are found in the DGTSMMD1 member of the panel library.

Table 4 lists the names for the corresponding line operators. The module names for line operators are found in the DGTTLPD3 member of the load library. Table 5 lists the names for commands. These names are in the DGTTCTD2 member of the load library.

Table 4. Module Names for DFSMSdss/ISMF Line Operators

Line Operator	Data Set Application Module Name	Volume Application Module Name
CGCREATE	_	DGTFCG01
COMPRESS	DGTFCM01	DGTFCS01
CONSOLID	_	DGTFCI01
CONVERTV	_	DGTFCN01
COPY	DGTFCY01	DGTFCV01
DEFRAG	_	DGTFDF01
DUMP	DGTFDP01	DGTFDM01
RELEASE	DGTFRL01	DGTFRV01
RESTORE	DGTFRT01	DGTFRO01

Table 5. Module Names for DFSMSdss/ISMF Data Set Application Commands

Command	Module Name
COMPRESS	DGTFCP01
COPY	DGTFCO01
DUMP	DGTFDU01
RELEASE	DGTFRE01
RESTORE	DGTFRR00

To view the command table, you need to know the data set names that your site uses for the panel library and the load library. The installation of DFSMSdss/ISMF puts the panel library in SYS1.DGTPLIB and the load library in SYS1.DGTLLIB. However, your site's postinstallation procedures might involve moving the DFSMSdss/ISMF libraries. If they were moved, you can determine the data set name by issuing the TSO LISTALC command and scanning the low-level qualifiers for DGTPLIB and DGTLLIB.



Note: DFSMSdss does not have special support for name hiding. You can prevent the disclosure of names by DFSMSdss by moving DFSMSdss to a protected library that only authorized users can access.

### Protecting DFSMSdss/ISMF modules

The steps used to protect DFSMSdss/ISMF modules are listed below:

- 1. To define the modules you want to protect, use the RDEFINE command or the ISPF RACF entry panels. When you define the modules to RACF, supply the name of the load module you want to protect, the name of the data set that contains the module, and the volume serial number of the volume that contains the data set. Each module you identify is added to the profile for the PROGRAM general resource class. You have several options when you define modules:
  - If you want to define several modules at the same time, you can use asterisk notation. For example, DGT\* means all the modules beginning with the letters DGT.
  - You can add an access list with user IDs, group names with their associated access authority to the profile, or both.
  - You can define the UACC to give default access to all users or to none.
  - You can use the AUDIT parameter to set up RACF logging or to bypass it.
- 2. To allow users to execute an application, line operator, or command, use the PERMIT command.

For more information about how to perform these steps and the options you have using program control, refer to *z*/*OS* Security Server RACF Security Administrator's Guide.

### Protecting DFSMSdss functions with RACF FACILITY class profiles

Besides protecting DFSMSdss/ISMF functions, you can also protect certain DFSMSdss keywords and functions. You do so by defining RACF FACILITY class profiles and restricting access to those profiles. Table 6 lists these keywords and functions, and their associated RACF FACILITY class profiles.

For a given command or parameter, protection occurs when both of the following conditions are met:

- · RACF FACILITY class is active
- The indicated profile has been defined.

When the RACF FACILITY class is active and one of the profiles listed in Table 6 is defined, you must have READ access authority to use the indicated command or keyword. Otherwise, anyone can use the indicated command or keyword. If RACF FACILITY class checking is not set up for these keywords, any DFSMSdss user can use them.

Table 6. RACF FACILITY Class Profile Names for DFSMSdss Keywords

Keyword or Function	Profile Name
BYPASSACS with COPY	STGADMIN.ADR.COPY.BYPASSACS
BYPASSACS with RESTORE	STGADMIN.ADR.RESTORE.BYPASSACS
CGCREATED	STGADMIN.ADR.CGCREATE
CONCURRENT with COPY	STGADMIN.ADR.COPY.CNCURRNT
CONCURRENT with DUMP	STGADMIN.ADR.DUMP.CNCURRNT
CONSOLIDATE	STGADMIN.ADR.CONSOLID
CONVERTV	STGADMIN.ADR.CONVERTV
DEFRAG	STGADMIN.ADR.DEFRAG

Table 6. RACF FACILITY Class Profile Names for DFSMSdss Keywords (continued)

Keyword or Function	Profile Name
DELETECATALOGENTRY with RESTORE	STGADMIN.ADR.RESTORE.DELCATE
FCCGFREEZE with COPY	STGADMIN.ADR.COPY.FCFREEZE
FCFASTREVERSERESTORE with COPY	STGADMIN.ADR.COPY.FCFRR
FCSETGTOK with COPY	STGADMIN.ADR.COPY.FCSETGT
FCTOPPRCPRIMARY with COPY	STGADMIN.ADR.COPY.FCTOPPRCP
FCTOPPRCPRIMARY with DEFRAG	STGADMIN.ADR.DEFRAG.FCTOPPRCP
FlashCopy with CONSOLIDATE	STGADMIN.ADR.CONSOLID.FLASHCPY
FlashCopy with COPY	STGADMIN.ADR.COPY.FLASHCPY
FlashCopy with DEFRAG	STGADMIN.ADR.DEFRAG.FLASHCPY
IMPORT with RESTORE	STGADMIN.ADR.RESTORE.IMPORT
INCAT(catname) with COPY	STGADMIN.ADR.COPY.INCAT
INCAT(catname) with DUMP	STGADMIN.ADR.DUMP.INCAT
INCAT(catname) with RELEASE	STGADMIN.ADR.RELEASE.INCAT
NEWNAMEUNCONDITIONAL with DUMP	STGADMIN.ADR.DUMP.NEWNAME
PROCESS(SYS1) with COPY	STGADMIN.ADR.COPY.PROCESS.SYS
PROCESS(SYS1) with DUMP	STGADMIN.ADR.DUMP.PROCESS.SYS
PROCESS(SYS1) with RELEASE	STGADMIN.ADR.RELEASE.PROCESS.SYS
RESET with DUMP	STGADMIN.ADR.DUMP.RESET
RESET(YES) with RESTORE	STGADMIN.ADR.RESTORE.RESET.YES
TOLERATE(ENQF) with COPY	STGADMIN.ADR.COPY.TOLERATE.ENQF
TOLERATE(ENQF) with DUMP	STGADMIN.ADR.DUMP.TOLERATE.ENQF
TOLERATE(ENQF) with RESTORE	STGADMIN.ADR.RESTORE.TOLERATE.ENQF
ZCOMPRESS with DUMP	STGADMIN.ADR.DUMP.ZCOMPRESS

You can bypass this type of RACF FACILITY class checking with the DFSMSdss installation options exit routine that your installation may be using.

For more information about the installation options exit routine, refer to z/OSDFSMS Installation Exits.

For more information about RACF class profiles, refer to z/OS Security Server RACF Security Administrator's Guide.

# Name-hiding

DFSMSdss has no special support for the name-hiding function. Your installation is responsible for protecting DFSMSdss functions and resources from unauthorized users. You can use the existing procedures to limit the use of DFSMSdss function by authorized users. For example, you can prevent disclosing names by placing DFSMSdss in a protected library that only authorized users can use.

For more information about how to protect a library, refer to "Protecting DFSMSdss/ISMF modules" on page 29.

# Chapter 6. Managing availability with DFSMSdss

One of the major functions of DFSMSdss is the backup and recovery of data. Using the DUMP and RESTORE commands, you can backup and recover data sets and volumes. You can also use the DUMP and RESTORE commands on ranges of tracks. However, this is usually done as a means of diagnosing I/O errors rather than as a means of backing up and recovering data.

# Planning an availability strategy

In planning your overall availability strategy, you should consider the following types of backup:

**Backup of volumes and data sets**—The general type of backup to guard against users accidentally losing or incorrectly changing their data sets and against losing volumes because of hardware failures.

**Disaster recovery backup**—Backup to protect against the loss of all your data in a major disaster at your site. These backups are stored off site and, in the event of a major disaster, are recovered at another site.

**Vital records backup**—Backup copies of data sets kept to meet externally imposed retention requirements, such as tax records.

**Archival**—Backup of data that is unused for a long period of time. You remove the data from DASD and retain it on tape in case it is needed again.

DFSMSdss is a flexible backup and recovery tool. You can use DFSMSdss by itself to perform all backups listed above or to complement other backup and recovery tools.

# **Backup and recovery**

General backup should be done at both the data set and the volume level. To protect against users accidentally deleting or changing their data sets, it is usually more efficient to do incremental backup (logical backup of those data sets that changed since they were last backed up). Incremental backups minimize processing time because you are not backing up every data set. Logical backup lets you restore data sets to unlike devices.

### Data set backup

For data set backup, you need to consider the frequency of backup and the number of versions you want to keep. A number of factors can influence this decision, such as:

- The rate at which the data changes.
- The ease or difficulty of rebuilding the data (for example, it is easier to rebuild an object library than a source library).
- The importance of the data. For data that is extremely important to your business, you might want to keep extra backup versions.

### Volume backup

Volume backup is necessary to guard against losing a volume, but it need not be done often if you are doing incremental backup on a regular basis. If you lose a volume, you can recover from the latest volume backup, and then recover data sets from incremental backups to return the volume to its status before the failure. This form of recovery is sometimes referred to as forward recovery. To perform it,

however, you must have a record of all of your backups. The DFSMShsm component keeps its own inventory of the data sets it backs up and can perform forward recovery using that inventory. DFSMSdss prints the names of the data sets it dumps and the serial number and data set sequence number of the tape volumes on which the dump begins and ends. You must use this printed record to perform forward recovery with DFSMSdss.

### Backup and recovery in an SMS-managed environment

Two kinds of data exist in an SMS-managed environment: SMS-managed and non-SMS-managed data. DFSMSdss can help you fulfill your availability requirements for both kinds of data.

SMS-managed data: The DFSMShsm component can perform automatic volume backup (by invoking DFSMSdss) and incremental backup on SMS-managed data. Each data set is assigned a management class that indicates how often DFSMShsm should back it up and how many versions of the backup to keep. Using DFSMShsm this way lets you manage availability at the data set level.

If DFSMShsm is not installed, you can use DFSMSdss to back up and recover data sets and volumes. By filtering on management class name and the data-set-changed indicator, you can perform incremental backup on all the data sets belonging to a particular management class. To facilitate this backup procedure, you can set up a DFSMSdss job to run periodically.

Non-SMS-managed data: Typically, non-SMS-managed data is data that SMS does not support or data that is in transition from non-SMS to SMS management. If it is data that SMS does not support, you can probably still use DFSMSdss to back it up and recover it, because DFSMSdss supports many kinds of data that SMS does not. If it is data in transition to SMS management, you can use DFSMShsm or DFSMSdss to back up and recover it until it is placed under SMS management.

### Backup and recovery in a non-SMS-managed environment

If SMS is not active, you are in a non-SMS-managed environment. For availability management, the data in this environment can be treated much the same as the non-SMS-managed data in an SMS-managed environment. DFSMSdss can be used to back up and recover it at the data set and volume level.

# Disaster recovery

Disaster recovery backups are made specifically for recovering data and applications following a disaster. Never rely on your regular backup data sets (for example, DFSMShsm or DFSMSdss incremental backups) for disaster recovery. Disaster recovery backups require special considerations that normally do not apply to other types of backups.

### Storing at a remote site

A basic difference between regular backups and disaster recovery backups is that disaster recovery backups must be transported to a different site. The remoteness of the recovery site depends upon the type of disaster you are preparing for (in the case of a fire, the recovery site can be around the corner; in the case of an earthquake or flood, it should be many miles away). The fact that the backups must be taken to another site means that they must be on a portable media: tape.

**Note:** You can also automatically transmit backups to another site.

### Using logical data set dump

Because the environment at the remote site might differ from your environment, you should ensure that your disaster recovery backups can be restored in a different environment. In general, it is recommended that you use the logical data set DUMP command and filter on the data set name to make disaster recovery backups. Logical data set dump processing allows you to back up only your critical data sets and to restore to unlike devices.

Making logical data set dumps for disaster recovery backup requires a naming convention or some other method to identify your critical data sets. If, for example, you establish the convention of having the letters CRIT as the first four characters in the first qualifier of critical data sets, you can back them up for disaster recovery as follows:

```
DUMP -
DATASET(INCLUDE(CRIT*.**) -
BY(MGMTCLAS, EQ, MCNAME)) -
OUTDDNAME(TAPE) -
COMPRESS
```

If for some reason you must do volume dumps for disaster recovery, you should do logical volume dumps instead of physical volume dumps. That way, you can restore the backups to unlike devices. You can perform logical volume dumps by using DATASET (INCLUDE(\*\*)) and either the LOGINDDNAME or LOGINDYNAM keyword with the DUMP command.

### Back up only critical data sets

You should back up only data sets that are critical to your operation. For example:

- Critical application data sets
- RACF inventory data sets
- System data sets
- Catalogs

Because you normally back up only critical data sets for disaster recovery, the amount of data you have to back up is only a small percentage of all your data. To identify those data sets that you want backed up for disaster recovery, you should create a unique naming convention.

If you have DFSMShsm installed on your system, the recommended method of disaster backup is to use aggregate backup and recovery support (ABARS).

To maintain versions of your disaster recovery backups, you can use generation data group (GDG) dump data sets.

When recovering after a disaster, you might need to use the DELETECATALOGENTRY or IMPORT keywords or both. For information about using these keywords, refer to "Logical restore of data sets with phantom catalog entries" on page 90.

For more information about ABARS, refer to *z/OS DFSMShsm Storage Administration*.

### Maintaining vital records

Vital records are maintained to meet external retention requirements (such as legal requirements).

Like disaster recovery backups, vital records are kept at a remote site and therefore should reside on tape. Vital records are usually an even smaller percentage of all data than disaster recovery backups. Unlike disaster recovery backups, vital records are rarely necessary for normal processing.

Vital records are usually kept for long periods of time. The device they originally resided on may no longer be in use at the time of recovery, and you may need to restore them to unlike devices. Therefore, vital records should be dumped logically so they can be restored to unlike devices. As with disaster recovery, using logical data set DUMP processing requires a naming convention or some other method to identify data sets for dumping.

If, for example, you establish the convention of having the letters VR as the first two characters in the first qualifier of data sets to be backed up for vital records purposes, you can dump them as follows:

```
DUMP -
DATASET(INCLUDE(VR*.**) -
BY(MGMTCLAS, EQ, MCNAME)) -
OUTDDNAME(TAPE) -
COMPRESS
```

### **Archiving data sets**

Archived data sets are data sets created to remove data from active status. This data is placed on alternate storage media because it is not currently being used but may be used in the future. Archived data sets are usually used for long-term retention.

You can use DFSMSdss to archive data sets by periodically filtering on last-referenced date and then dumping and deleting data sets that have not been referenced for long periods of time. This frees space for data that is being accessed more frequently and requires the faster access time of DASD. Because archived data sets might not be recovered for a long time, they should be dumped logically so they can be restored to unlike devices.

For example, the following logical DUMP command results in the archiving of all data sets in management class MCNAME1 that have not been referred to since April 10, 1999:

```
DUMP -

DATASET(BY((REFDT LT 99100)(MGMTCLAS EQ MCNAME1))) -

OUTDDNAME(TAPE1) -

DELETE -

COMPRESS -

PURGE
```

### Backing up data sets

With the DUMP command, you can dump DASD data to a sequential data set, which can be a generation in a generation data group (GDG). The storage medium for the sequential data set can be tape or DASD. The output data set must be a standard format sequential data set and cannot use any extended-format features, such as compression. If the output resides on DASD, it may be a Large Format data set.

DFSMSdss can dump data sets both logically and physically. Data sets are located by searching either the catalog or the VTOC.

You can select data sets for dump processing based on data set names and numerous data attributes, as discussed in Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259.

To perform incremental backups with DFSMSdss, you can filter with BY(DSCHA,EQ,1) to dump only data sets that have changed since the last dump was taken. If you also code the RESET keyword, DFSMSdss changes the data-set-changed indicator (DSCHA) after successfully dumping the data set. For more information about the RESET keyword, refer to "Backup with concurrent copy" on page 40.

#### Note:

- 1. If you are using DFSMSdss on data sets that DFSMShsm is also backing up, you should not use the RESET keyword because it might cause confusion as to which backup is the most current.
- 2. DFSMSdss does not permanently record the names of candidate volumes during dump processing.

The data-set-changed indicator and the last-referenced date (REFDT) are supported for VSAM and non-VSAM data sets.

Temporary data sets might be included in the data set list at the beginning of a DFSMSdss job. These data sets are created and deleted by other jobs that are running while DFSMSdss is running. Because they are temporary, these data sets can disappear before DFSMSdss finishes. DFSMSdss can issue a message informing the user what happened only at the time DFSMSdss tries to access the data sets. To hold all the data sets in a volume for the entire DFSMSdss execution, write an enqueue installation exit to enqueue the volume for the entire job.

When you create backups of data sets with the DUMP command, you can make multiple (up to 255) dump copies with a single DUMP command. This is done by specifying multiple ddnames on the OUTDDNAME parameter. To specify multiple ddnames on the OUTDDNAME parameter, you could code:

```
DUMP -
DATASET(INCLUDE(**) -
BY(MGMTCLAS,EQ,MCNAME1)) -
OUTDDNAME(TAPE1,TAPE2,TAPE3) -
COMPRESS
```

This technique can be helpful if you want to create several backup copies to be used for different purposes.

Unless overridden by the installation options exit routine, DFSMSdss continues dumping while at least one output copy does not have an output error. In the event of an abend, however, DFSMSdss ends without completing any backups.

For more information about the data-set-changed indicator and REFDT, refer to *z/OS DFSMS Installation Exits*.

### Logical data set dump

If you specify the DATASET keyword with the DUMP command and do not specify input volumes, DFSMSdss performs a logical data set dump using information in the catalogs to select data sets. For example, the following DUMP command results in a logical data set dump:

```
DUMP -
DATASET(INCLUDE(**) -
BY(DSCHA,EQ,YES)) -
OUTDDNAME(TAPE1) -
COMPRESS
```

If you specify the DATASET keyword with the LOGINDDNAME, LOGINDYNAM, or STORGRP keywords, DFSMSdss performs a logical data set dump by using information in the VTOCs to select data sets. For example, the following DUMP command results in a logical data set dump of all the single volume data sets on volume 338001:

```
DUMP -
DATASET(INCLUDE(**)) -
LOGINDYNAM(338001) -
OUTDDNAME(TAPE) -
COMPRESS
```

The following data sets cannot be processed by logical data set dump or restore operations:

- VSAM data sets not cataloged in an integrated catalog facility catalog
- Page, swap, and SYS1.STGINDEX data sets
- VSAM Volume Data Sets (VVDS)
- Partitioned data sets containing location-dependent information that does not reside in note lists or in the directory.

**Note:** DFSMSdss cannot be used to dump data sets with a volume serial of MIGRAT. The recommended method of dumping migrated data sets is to use ABARS.

# Physical data set dump

If you specify DATASET and INDDNAME or INDYNAM, DFSMSdss performs a physical data set dump. For instance, the following DUMP command results in a physical data set dump:

```
DUMP -
INDDNAME(DASD1) OUTDDNAME(TAPE) -
DATASET(INCLUDE(**)) -
COMPRESS -
OPTIMIZE(4)
```

When multiple input volumes are specified for a physical data set dump operation, multiple logical files (logical volumes) are created for each physical DASD source volume.

DFSMSdss facilitates backup and recovery procedures for physical data set dumps by printing the names of data sets dumped, and the serial and data set sequence numbers of the backup tape volumes on which the dump of a DASD volume begins and ends.

A physical data set dump or restore operation cannot process the following data sets:

- KSDSs with key ranges. Logical processing should be used for this type of data set.
- Extended-format VSAM data sets, including extended-addressable VSAM data sets. Use logical processing for these types of data sets.
- VSAM data sets not cataloged in an integrated catalog facility catalog.
- Page, swap, and SYS1.STGINDEX data sets.

**Note:** When dumping multivolume data sets, take care to ensure that all volumes where the data set resides are dumped at the same time and restored at the same time. Dumping parts of a multivolume data set and then restoring them may leave the entire data set or those parts unusable. In particular, keyed VSAM data sets are easily damaged by such an operation.

# Renaming data sets during dump processing

You can specify new names for dumped data sets through the NEWNAMEUNCONDITIONAL keyword on the DUMP command. With this keyword you assign new names to data sets during dump processing, rather than renaming them later during restore processing. You might find NEWNAMEUNCONDITIONAL to be useful if your installation keeps its dumped data sets cataloged to avoid name contention between the data sets that are backed up (dumped) and the production data sets.

The NEWNAMEUNCONDITIONAL keyword can only be used when invoking DFSMSdss through the Application Programming Interface (API).

To assign a new name for a data set, you can specify a source data set with a corresponding new name. For VSAM data sets, DFSMSdss derives VSAM component names based on whether or not the name assigned for the VSAM cluster is currently cataloged in the standard order of search. If the data set is not cataloged, or the installation requests DFSMSdss to bypass checking to determine if the new cluster name is cataloged in the standard order of search by the way of the ADRUFO field, then DFSMSdss uses the same criteria that it uses for the RENAME or RENAMEUNCONDITIONAL keywords to determine the new names for the VSAM components (refer to "Renaming data sets" on page 102). For example, DFSMSdss might append .DATA (for a data component) and .INDEX (for an index component) to the new cluster name when deriving the new VSAM component names. If the new named data set is cataloged in the standard order of

search, DFSMSdss associates the component names and the catalog name in the dump records for the new named data set.

Data sets that do not meet the NEWNAMEUNCONDITIONAL criteria retain their original names.

For the other dump records in the ADRTAPB Data Area, DFSMSdss associates the source SMS constructs and volume serial numbers from the source data set.

To use the NEWNAMEUNCONDITIONAL keyword, you do not require access authority to the source (READ) or the target (ALTER) data sets and their catalogs. Instead, renaming data sets is authorized through the existing ADMINISTRATOR keyword and is protected by the RACF FACILITY class, STGADMIN.ADR.STGADMIN.DUMP.NEWNAME. This profile does not permit you to delete a data set. Also, DFSMSdss propagates any passwords retrieved from the source data set to the new named data set.

#### Note:

- 1. If you specify the NEWNAMEUNCONDITIONAL keyword with the SPHERE keyword to process a base VSAM cluster, DFSMSdss processes the entire VSAM sphere and assigns a new name to associated alternate indexes and paths. If you do not specify rename filter criteria for all of the data sets in the sphere, DFSMSdss issues an error message and does not process the source data set.
- 2. If the new name filter has errors, DFSMSdss does not process the data set. The new name is truncated to fit 44 characters. If it ends with a period, that period is also truncated.
- 3. You cannot change the number of qualifiers unless you use fully-qualified names, for example, NEWNAMEUNCONDITIONAL((A.B.C,A.B.C.D)). If the new name is not fully qualified, it must contain the same number of qualifiers as the old name. For example, given the old name filter DATE.\*\*, the new name filter DATE.\*.\*.LIST, DATE.MARCH.TODAY.OLDLIST is renamed, but DATE.MARCH.OLDLIST is not.
- 4. GDG relative generation filtering cannot be used for old or new names.

For more information about dump records, refer to "ADRTAPB data area" on page 199.


For more information about ADRUFO installation options exit routine, refer to z/OS DFSMS Installation Exits.

For more information about specifying the NEWNAMEUNCONDITIONAL keyword, refer to "NEWNAMEUNCONDITIONAL" on page 413.

# Backup with concurrent copy

#### **Programming Interface Information**

DFSMSdss provides the concurrent copy function to allow you to backup data while minimizing the amount of time in which the data is unavailable. The database or application determines an appropriate time to start a backup, for example, when the data is in a known state and update activity is stopped. You can invoke DFSMSdss directly or through the DFSMSdss application program interface (API) to do a concurrent copy of the entire database. After initialization, DFSMSdss releases any serialization it holds on the data sets and prints a message to SYSPRINT and the console that the concurrent copy operation is logically complete. If you invoke DFSMSdss through the API, DFSMSdss informs the caller through the UIM exit option, Eioption 24, and the application can resume normal operation.



If for any reason data cannot be processed with concurrent copy (for example, the hardware being used does not support concurrent copy), DFSMSdss optionally uses normal backup methods and does not release the serialization until the backup is completed.

If the source device supports data set FlashCopy or SnapShot, DFSMSdss optionally uses the FlashCopy or SnapShot to provide virtual concurrent copy.

For more information on concurrent copy and virtual concurrent copy, refer to "Performance considerations" on page 55.

### Specifying concurrent copy for DUMP requests

On the DFSMSdss DUMP command, you can specify that DFSMSdss is to use the concurrent copy function to process data. To do so, you specify the CONCURRENT keyword, and, optionally, one of several available sub-keywords to indicate the type of concurrent copy to be used and whether DFSMSdss can use other methods of data movement. If you do not specify the CONCURRENT keyword, your DUMP request does not use concurrent copy.

The CONCURRENT keyword applies to all of the data being dumped. You cannot apply this function to a subset of the data being processed.

If you specify the CONCURRENT keyword, DFSMSdss might use a function equivalent to the cache-based concurrent copy, called *virtual concurrent copy*. During virtual concurrent copy, data is "flashed" or "snapped" from the source location to an intermediate location, and then copied to the target location using standard I/O. The operation is logically complete after the source data is "flashed" or "snapped" to the intermediate location and physically complete after the data is moved to the target media.

If the source volume supports data set FlashCopy, DFSMSdss uses FlashCopy to provide virtual concurrent copy. If the source volume is a RAMAC Virtual Array (RVA), DFSMSdss uses SnapShot. For more information about virtual concurrent copy, refer to "Using concurrent copy" on page 7.

**Attention:** Use concurrent copy only during periods of light update activity for the data sets or volumes involved. Performing cache-based concurrent copy operations against many large data sets when there is also heavy update activity (such as reorganizing data sets or initializing the volume the data sets reside on) might result in a shortage of storage, because data is transferred to z/OS data space storage faster than DFSMSdss can process it. When you use multiple simultaneous concurrent copy tasks to process large, heavily updated data sets, you might also experience long run times and contention for SYS.DATA.SPACE.LATCH.SET. You must ensure that during the concurrent copy operation another system does not reserve volumes that are to be processed. You must also ensure that jobs and address spaces that are to use the concurrent copy are assigned a WLM service class with a high execution velocity. Do not assign a discretionary goal to concurrent copy work. You should spread multiple concurrent copy jobs across as many LPARs as possible and avoid the use of PARALLEL mode in DFSMSdss.

#### Note:

- 1. To help ensure data integrity, do not update the data during concurrent copy initialization.
- 2. If a concurrent copy operation fails after signaling that the concurrent copy initialization is complete (and update activity on the data has resumed), you cannot recover the data to the point-in-time at which the concurrent copy operation was started. The data might have been updated while the copy operation was progressing.
- 3. VM mini-volumes are supported if you are using RVA devices to the extent that they are supported by IBM Extended Facilities Product (IXFP) device reporting.
- 4. The use of concurrent copy and virtual concurrent copy with the DFSMSdss DUMP command is controlled by the RACF FACILITY class profile, STGADMIN.ADR.DUMP.CNCURRNT.

For information about specifying CONCURRENT and other DUMP command keywords, refer to "DUMP command for DFSMSdss" on page 391.

#### Invocation from an application program

Usage of the concurrent copy function can also be controlled through the installation options exit, a product-sensitive programming interface intended for customer use.

For more information about the installation options exit, refer to z/OS DFSMS Installation Exits.

For more information about the CONCURRENT keyword, refer to "CONCURRENT" on page 316.

# Using DFSMSdss as a backup utility for CICSVR

CICSVR users can choose DFSMSdss as their backup utility by specifying the CICSVRBACKUP keyword. DFSMSdss notifies the CICSVR server address space every time that a CICSVR backup is made for a VSAM base cluster. CICSVR stores the backup information in its recovery control data set (RCDS). This enables CICSVR to manage backups that are made by DFSMSdss. Through the CICSVR dialog panels, CICSVR provides data set, forward recovery automation by using backups that DFSMSdss makes.

To use the DFSMSdss DUMP command to make CICSVR backups, you must create DFSMSdss DUMP jobs that can be regularly submitted with a production planning

system. Specify the CICSVRBACKUP keyword on the logical data set DUMP command. The output data set name must be unique each time the job is run so that multiple backup copies can be maintained.

You can also use the DFSMSdss COPY command to make CICSVR backups. There are advantages to using the COPY command instead of the DUMP command:

- You can use data set FlashCopy to create the backup instantaneously when the data set resides on an ESS that supports data set FlashCopy. You can use data set FlashCopy to recover the data set instantaneously to a data set FlashCopy-capable ESS.
- You can use SnapShot to create the backup instantaneously when the data set resides on a RAMAC Virtual Array (RVA). You can use SnapShot to recover the data set instantaneously to an RVA device.

To use the DFSMSdss COPY function to make CICSVR backups, you must create DFSMSdss COPY jobs that can be regularly submitted with a production planning system. Specify the CICSVRBACKUP and RENAMEUNCONDITIONAL keywords on the data set COPY command. CICSVR provides DFSMSdss with a new name for each VSAM base cluster that is copied when the CICSVRBACKUP keyword is specified. DFSMSdss uses the CICSVR-generated new name instead of the one you specify.

For more information about using the CICSVRBACKUP keyword on the DUMP command, refer to "CICSVRBACKUP" on page 401.

For more information about using different methods to generate a unique output data set name, refer to CICS VSAM Recovery Implementation Guide.

For more information about the CICSVR generated new name and the required RENAMEUNCONDITIONAL specification, refer to CICS VSAM Recovery Implementation Guide.

# A backup scenario

As discussed in "Backup and recovery" on page 33, you should consider using a combination of incremental and volume backup to fulfill your general availability requirements. Some ways to implement this strategy are:

 Dump a full volume at a given interval—perhaps once a week. Use the RESET keyword to reset the data-set-changed indicator. To do full-volume dumps of two volumes at once (in parallel, which is most effective if tapes are on separate channels), code the following:

```
PARALLEL
DUMP INDYNAM(111111) OUTDD(TAPE1) RESET OPTIMIZE(1)
DUMP INDYNAM(222222) OUTDD(TAPE2) RESET OPTIMIZE(2)
```

Dump only changed data sets at a shorter interval—perhaps daily.

```
DUMP LOGINDY((111111),(2222222)) OUTDD(TAPE3) RESET -
OPTIMIZE(3) DATASET(INCLUDE(**) -
BY(DSCHA,EQ,YES))
```

• Use data set naming conventions to set up a dumping scheme that takes account of the relative importance of the data. For example, include CRIT in the

first-level qualifier of all your critical data sets. With this convention in place, you can back up your critical data sets as follows:

```
DUMP LOGINDY((111111),(222222)) OUTDD(TAPE4) RESET -
OPTIMIZE(4) DATASET(INCLUDE(CRIT*.**) -
BY(DSCHA,EQ,YES))
```

Other naming conventions can also be used to identify groups of data sets. For instance, you can use department numbers, charge numbers, user initials, or project codes to identify data sets you want to dump together.

For data set operations, SYSPRINT contains the names of all the data sets that were dumped for each run. You should keep them for reference if you have to restore a data set and you want it to be at the latest level. This prints a listing of all the data sets that might be on the restore tape, and you can now find the latest dumped version of a particular data set.

### Backing up data sets with special requirements

Some data sets require special processing when they are backed up. The sections below describe how to back up data sets that have special requirements.

### **Dumping HFS data sets**

The following topics present guidelines for backing up an HFS data set with either logical data set dump or physical data set dump.

### Logical dump

Back up mounted HFS data sets with logical data set dump. Logical data set dump provides the quiesce serialization mechanism (BPX1QSE) to ensure data integrity. The quiesce ability allows you to dump an HFS data set while it is in use, as long as you run the dump job on the same system that the HFS data set is currently mounted on.

For more information about the serialization of HFS data sets, refer to Chapter 21, "Data integrity—serialization," on page 561.

### Physical dump

Physical dump does not provide the quiesce serialization mechanism, and it is not recommended for backing up mounted HFS data sets. If you do perform a physical dump of an HFS, do not specify the SHARE keyword. The SHARE keyword applies to the SYSDSN ENQ, and therefore does not provide protection against updates during dump.

**Attention:** Exercise caution if you use TOL(ENQF) during a physical dump of HFS data sets. Unlike other types of data sets, if an HFS is updated during a physical dump with TOL(ENQF), a subsequent restore will likely result in an unusable data set.

# Dumping zFS data sets

The following topics present guidelines for backing up an zFS data set with either logical data set dump or physical data set dump.

### Logical dump

Back up mounted zFS data sets with logical data set dump. Logical data set dump provides the quiesce serialization mechanism (BPX1PCT) to ensure data integrity. The quiesce ability allows you to dump a zFS data set while it is in use, as long as you run the dump job on the same system that the zFS data set is currently mounted on.

### Physical dump

Physical dump does not provide the quiesce serialization mechanism, and it is not recommended for backing up mounted zFS data sets.

**Attention:** Exercise caution if you use TOL(ENQF) during a physical dump of zFS data sets. Unlike other types of data sets, if a zFS data set is updated during a physical dump with TOL(ENQF), a subsequent restore will likely result in an unusable data set.

### **Dumping multivolume data sets**

An important advantage of DFSMSdss as a backup tool is that it can back up multivolume data sets without having to specify any or all of the input volumes. If you do not specify any input volumes (you are using catalog filtering), multivolume data sets will be automatically processed in their entirety. The catalogs are scanned to select an entire data set; that is, the data set is processed in its entirety from all the volumes it resides on. Logical processing consolidates the extents of the data set in one dump data set for you.

If you specify input volumes using the LOGINDDNAME or LOGINDYNAM volume list, a data set is selected based on the following criteria:

- When you either specify SELECTMULTI(ALL) or specify input volumes without specifying the SELECTMULTI keyword, *all* of the volumes that contain a part of a non-VSAM or VSAM cluster must be in the volume list.
  - For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:
  - Specify SPHERE and you must list all parts of the base cluster in the volume list.
  - Do not specify SPHERE and you must list all parts of the base cluster and the associated indexes in the volume list.
- When you specify SELECTMULTI(ANY), *any part* of the non-VSAM data set or VSAM base cluster can be on a volume in the volume list.
  - For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:
  - Specify SPHERE and you must list any part of the base cluster in the volume list.
  - Do not specify SPHERE and you must list any part of the base cluster and the associated alternate indexes in the volume list.
- When you specify SELECTMULTI(FIRST), the volume list must include the volume that contains the *first part* of either the non-VSAM data set or the primary data component of the base cluster for a VSAM sphere.
  - For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:
  - Specify SPHERE and you must list the volume that contains the first extent of the data component for the base cluster in the volume list.

- Do not specify SPHERE and you must specify the following information in the volume list:
  - The volume that contains the first extent of the data component for the base cluster.
  - The volume that contains the first extent of the data component for the associated alternate indexes.

Guideline: You are not required to specify the SELECTMULTI option when you build a list of volumes using the STORGRP keyword. The volume list contains all of the volumes in a storage group.

The following is an example of the DUMP command with SELECTMULTI specified:

```
DUMP
   DATASET(INCLUDE(**)) -
   SELECTMULTI -
   LOGINDYNAM(338001) -
   OUTDDNAME (TAPE) -
   COMPRESS
```

SELECTMULTI works only for logical data set dumps. If you dump a multivolume data set physically, you must ensure that the segments from all the volumes are dumped together. If you dump a multivolume data set physically, it is dumped from all the volumes that are passed. The output dumped data contains a logical file for each selected volume.

A DFSMSdss logical data set dump operation attempts to ensure that all parts of a multivolume non-VSAM data set exist. In cases where a part of the data set is missing, such as an inadvertent scratching of the VTOC entry on a volume, DFSMSdss issues an error message and discontinues processing the data set.

DFSMSdss cannot process the following non-VSAM data sets because they are missing one or more parts:

- Multivolume data sets whose catalog volume order differs from the VTOC volume order
- Single volume data sets with the same name that are cataloged as one multivolume data set
- Multivolume data sets whose last volume indicator in the VTOC entry is not set.

A multivolume data set standard user label is not supported.

# Dumping integrated catalog facility user catalogs

Another important use of DFSMSdss as a backup tool is the backing up of integrated catalog facility user catalogs and their aliases (using logical data set dump). The user catalog name must be fully qualified with the INCLUDE keyword on the DUMP command. The LOCK attribute of an integrated catalog facility user catalog is dumped. The LOCK status is preserved if the catalog does not exist at restore time. Otherwise, the LOCK status of the existing catalog is used.

The following example shows the JCL used to dump an integrated catalog facility user catalog. RACF access to the catalog is not required if you have RACF DASDVOL update access or if the installation authorization exit routine bypasses authorization checking.

Figure 1 shows printed output produced by the dump.

```
PAGE 0001
               5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                                      1999.211 14:54
   DUMP
      DS(INCL(TEST.CAT.PUBSEXMP)) -
      OUTDDNAME (TAPE)
ADR101I (R/I)-RI01 (01), TASKID 001 HAS BEEN ASSIGNED TO COMMAND 'DUMP '
ADR109I (R/I)-RI01 (01), 1999.211 14:54:32 INITIAL SCAN OF USER CONTROL STATEMENTS COMPLETED.
ADR016I (001)-PRIME(01), RACF LOGGING OPTION IN EFFECT FOR THIS TASK
ADR006I (001)-STEND(01), 1999.211 14:54:32 EXECUTION BEGINS
ADR801I (001)-DTDSC(01), DATA SET FILTERING IS COMPLETE. 1 OF 1 DATA SETS WERE SELECTED: 0 FAILED
                           SERIALIZATION AND 0 FAILED FOR OTHER REASONS.
ADR454I (001)-DTDSC(01), THE FOLLOWING DATA SETS WERE SUCCESSFULLY PROCESSED
                           CLUSTER NAME TEST.CAT.PUBSEXMP
                            CATALOG NAME
                                            SYS1.MVSRES.MASTCAT
                            COMPONENT NAME TEST.CAT.PUBSEXMP
                            COMPONENT NAME TEST.CAT.PUBSEXMP.CATINDEX
ADRO06I (001)-STEND(02), 1999.211 14:54:32 EXECUTION ENDS
ADR0131 (001)-CLTSK(01), 1999.211 14:54:32 TASK COMPLETED WITH RETURN CODE 0000
ADR0121 (SCH)-DSSU (01), 1999.211 14:54:32 DFSMSDSS PROCESSING COMPLETE. HIGHEST RETURN CODE IS 0000
```

Figure 1. Output from a Dump of an Integrated Catalog Facility User Catalog

For more information about the LOCK attribute, refer to *z/OS DFSMS Managing Catalogs*.

For more information about the installation authorization exit routine, refer to *z/OS DFSMS Installation Exits*.

# **Dumping non-VSAM data sets that have aliases**

DFSMSdss does not support INCLUDE filtering of non-VSAM data sets using an alias. To include a non-VSAM data set that has an alias for dump processing, you must use the data set's real name, as shown in the VTOC. DFSMSdss does not detect or preserve aliases of non-VSAM data sets. You will need to redefine the aliases after the data set is dumped and restored.

# **Dumping VSAM spheres**

Using the SPHERE keyword, you can dump an entire VSAM sphere (base cluster and all associated alternate index clusters and paths). To dump the base cluster and the other components, all you need to specify is the base cluster name.

An example of the DUMP command with the SPHERE keyword is:

```
DUMP -

OUTDDNAME(TAPE) -

DATASET(INCLUDE(PARTS.VSAM1)) -

SPHERE -

PSWD(PARTS.VSAM1/MASTUPW1) -

COMPRESS
```

Note: You should be aware that you cannot restore a sphere unless it is dumped as a sphere with the SPHERE keyword.

### Dumping indexed VSAM data sets

Indexed VSAM data sets (such as key sequenced or variable relative record data sets) can be logically dumped either without regard for the track contents or with validity checking of each track as the tracks are written. If dumped in the latter format, they must be restored on a system that supports the validate function.

The VALIDATE keyword, which is the default, specifies that the index and data track contents are to be validated as the tracks are dumped. Spanned record errors and split errors are detected and reported, but the dump continues. If other errors are detected, a message is issued and the dump stops.

The validate function can be overridden with the NOVALIDATE keyword, which specifies that no validation is done as the tracks are dumped. Some errors may not be detected until the data set is restored.

Note: Extended-format VSAM data sets cannot be dumped with the NOVALIDATE keyword.

### Dumping SYS1 system data sets

DFSMSdss allows data sets with a high-level qualifier of SYS1 to be dumped, deleted, and uncataloged. You must use the PROCESS(SYS1) keyword with the DUMP command. The SYS1.VVDS and SYS1.VTOCIX data sets are an exception to this processing.

SYS1.VVDS and SYS1.VTOCIX data sets can be physically, but not logically, dumped. Also, the SYS1.VVDS data set cannot be deleted or uncataloged.

Guideline: To limit the use of the PROCESS keyword, it is recommended that the PROCESS keyword be protected by a security program, such as RACF.

For more information about the RACF FACILITY class profile, refer to z/OS Security Server RACF Security Administrator's Guide.

# Dumping data sets containing records past the last-used-block pointer

Some data sets on your system may contain records past the last-used-block pointer in the data set's VTOC entry. This could be a result of a data set not being properly closed or an application that accesses data in such a way as to bypass the updating of this field. In this case, special consideration needs to be given to these data sets as DFSMSdss recognizes this block pointer as the end of the used space in the data set and, therefore, the end of the real data.

Using the ALLDATA or ALLEXCP keyword will result in all the allocated space being dumped for applicable data sets. This includes all the data up to the last block pointer as well as all the data to the end of the allocated space. However, whether or not all the data is restored depends on data set characteristics and device characteristics during the restore. For example, if the data set must be reblocked (either because the target is an unlike device, the REBLOCK keyword is specified, or the data set is marked reblockable) only the used space will actually be restored. This limitation is due to the fact that any residual data (that is in the unused portion of the data set) will likely have different characteristics than the

real data (that is in the used portion of the data set). This inconsistency would result in data incompatibilities causing the restore to fail, and thereby inhibiting the ability to restore the real data. Because of this, DFSMSdss will only restore the data in the used portion of the data set when the data characteristics must change.

If you require that all of the unused space is restored, then you should ensure that the data set is restored to a like device type and not reblocked or compressed. (Compress is the default for PDS data sets on restore unless you use the NOPACKING keyword.) In this case, the characteristics of the data do not change, and DFSMSdss will restore all the allocated space.

### Backing up SMS-managed data sets

When backing up data sets in an SMS-managed environment, you need to think about some special conditions in addition to those discussed under "Backing up data sets" on page 37. The following sections discuss how you can back up SMS-managed data sets in an SMS-managed environment.

In most cases, you should let DFSMShsm back up SMS-managed data sets for you. However, if you do not have DFSMShsm or if you prefer not to rely on it for all your backup requirements, you can use DFSMSdss to back up your SMS-managed data sets.

#### Filter on class names

DFSMSdss can select data sets for dump processing based on their storage, management, and data class names. Because management class is the construct that contains a data set's availability attributes, you might want to filter on it when selecting data sets for dump processing.

If you want to back up data sets in a particular management class, you can filter on the management class name. For example, if you want to perform incremental backup on data sets in management classes MCNAME1 and MCNAME2, specify the DUMP command as follows:

```
DUMP -
    DATASET(INCLUDE(**) -
        BY((MGMTCLAS, EQ, (MCNAME1, MCNAME2)) (DSCHA, EQ, YES))) -
    OUTDDNAME(OUTVOL1)
```

### Class names saved

DFSMSdss saves the class names of the data sets it dumps. These names are then used as input to ACS routines when the data set is restored.

# Backing up data sets being accessed with record level sharing

During logical data set dump operations of SMS-managed VSAM data sets, DFSMSdss communicates with VSAM RLS to perform quiesce processing of data sets that are being accessed by another job using Record Level Sharing (RLS).

By default, DFSMSdss does not use timeout protection during RLS quiesce processing. You can control whether or not DFSMSdss uses timeout protection during RLS quiesce processing and what the timeout value should be using the DSSTIMEOUT parameter of the IGDSMSxx PARMLIB member.

You can also change the timeout value without IPLing the system using the SETSMS DSSTIMEOUT(*nnnnn*) command.

For more information about the RLS timeout value used during DFSMSdss operations, refer to *z/OS DFSMSdfp Storage Administration*.

For more information about the SETSMS command, refer toz/OS MVS System Commands.

### Backing up data sets with extended attributes

When you use DFSMSdss to back up data sets with the extended attributes variable DS1EATTR set in the VTOC, you must make sure that these data sets can be restored into an environment that supports them. If the vendor attributes in the F9 DSCB are essential to the validity of the data set, make sure that the environment in which they might be restored has EAVs to support these F9 fields.

### Backing up volumes

With DFSMSdss, you can back up volumes either logically or physically. If the volume is to be restored to an unlike device, you must dump it logically.

For information about using DFSMSdss to back up Linux for System z partitions and volumes, refer to Chapter 12, "Dumping and restoring Linux for System z partitions and volumes," on page 185.

### Logical volume DUMP

To perform a logical volume dump, you specify DATASET(INCLUDE(\*\*)) with either LOGINDDNAME or LOGINDYNAM. LOGINDDNAME identifies the input volume that contains the data sets to be dumped. LOGINDYNAM specifies that the volumes containing data sets to be dumped be dynamically allocated.

Here is an example of how you specify the DUMP command to perform a logical volume dump:

```
DUMP DATASET(INCLUDE(**)) -
LOGINDDNAME(DASD1) -
OUTDDNAME(TAPE)
```

**Note:** Certain data sets can be restored only to like devices even though they were dumped logically.

# Physical volume dump

To perform a physical volume dump, specify the DUMP command with INDDNAME or INDYNAM and OUTDDNAME. Because FULL is the default keyword for the DUMP command, you need not specify it. Unallocated tracks are not dumped. The following example shows how you can specify the DUMP command to physically back up a volume:

```
DUMP INDDNAME(DASD1) OUTDDNAME(TAPE)
```

# **Backing up system volumes**

If you plan to use the DFSMSdss stand-alone restore program to restore a volume without the use of a host system environment, you must dump the volume physically. In addition, when doing a full physical volume dump to back up a system residence volume, you must use JCL to invoke DFSMSdss.

You cannot use the DFSMSdss stand-alone restore program with an encrypted tape. DFSMSdss does not interface with the Encryption Key Manager or the Tape Controller and therefore the correct keys cannot be provided to the controller to decrypt data. If you attempt to use a stand-alone restore with an encrypted tape, DFSMSdss issues message ADRY3501I to indicate that the dump data set resides on an encrypted tape and thus, cannot be read with the stand-alone restore program. DFSMSdss also issues message ADRY509D to prompt the operator to continue or end the function.

# **Backing up VM-format volumes**

You can use DFSMSdss to back up VM-format volumes that are accessible to your z/OS system. The volumes must have OS-compatible VTOCs starting on track zero, record five. DFSMSdss can only retrieve device information from the OS-compatible VTOC; it cannot interpret any VM-specific information on the volume.

Use the CPVOLUME keyword and specify the range of tracks to be backed up with the TRACKS keyword. You can use concurrent copy on VM-format volumes by specifying the CONCURRENT keyword. Because DFSMSdss cannot check access authorization for VM data, CPVOLUME is only allowed with the ADMINISTRATOR keyword.

Exercise caution when using DFSMSdss to back up VM-format volumes, because DFSMSdss does not serialize any VM data in any way. You cannot use the DFSMSdss stand-alone restore program to restore dumps of VM-format volumes.

# **Dumping data efficiently**

When backing up data, you can specify both the OPTIMIZE and the COMPRESS keywords to improve performance and save dump space. The two keywords can be used together.

A selective data set dump operation saves space, while a full-volume dump operation saves time. The same applies to the COMPRESS keyword. It saves dump space, but involves some processing overhead. In general, if you are dumping to tape, saving space is probably less of a concern than performance. Usually, saving space is important only when it results in using fewer tapes to store the data. Using fewer tapes reduces the number of tape mounts that are necessary to recover the data.

# Combining volume copy and volume dump to reduce your backup window

You can use physical full volume copy in conjunction with FlashCopy or SnapShot to reduce the amount of time that your data is unavailable when you back it up.

Full volume copy, in conjunction with FlashCopy or SnapShot, can produce a copy of a volume in seconds. Then, DFSMSdss can dump the copy to tape while your applications are accessing the data on the original volume.

For more information about full volume copy, FlashCopy, and SnapShot, refer to "Moving volumes" on page 99.

## Combining the functions

To combine the volume copy and volume dump functions to reduce your backup windows, perform the following procedure:

- 1. Stop application access to the volumes.
- 2. Copy the volumes by using full volume copy. Do not specify FASTREPLICATION(NONE). The copies complete very quickly if DFSMSdss can use FlashCopy or SnapShot.
- 3. Enable application access to the volumes.
- 4. Backup the copies to tape using full volume dump.

### Special considerations

When you combine the volume copy function with the volume dump function, you must give consideration to how you will use the following keywords:

- DUMPCONDITIONING
- FCNOCOPY
- FCWITHDRAW

These keywords are described in the sections that follow.

**DUMPCONDITIONING** — Allows you to make a copy of the source volume in a full volume copy operation—including volume index information—while keeping the target volume online. Use this keyword when you want to create a copy of the source volume for backup purposes, rather than to allow applications to use the target volume.

With DUMPCONDITIONING in effect, the volume serial number of the target volume does not change, and the target volume remains online after the copy. The VVDS and VTOC index names on the target volume do not change to match the target volume serial number; they continue to match the source volume serial number.

In Step 2, for example, you can include the DUMPCONDITIONING keyword on the full volume copy command to allow the target volume to remain online for dumping.

The target of a full volume copy operation using DUMPCONDITIONING is referred to as a conditioned volume. A full volume dump of a conditioned volume appears as if it were dumped from the original source volume of the copy operation. However, if the conditioned volume is copied back using DUMPCONDITIONING, conditioning is not performed on the original source volume. Instead, DFSMSdss recognizes that it is copying from the target of a previous conditioned-backup and recovers the original source volume.

For example, suppose that you specify the DUMPCONDITIONING keyword when you perform a full volume copy of volume VOL001 to volume VOL002. If you then perform a full volume dump of VOL002 to tape, the output appears as if you had dumped VOL001 directly. Now suppose that you copy VOL002 back to VOL001. Here, the VOL002 volume serial number is not copied to VOL001's volume label, because DFSMSdss treats VOL002 as a copy of VOL001.

This example assumes that the source volume VOL001 has an indexed VTOC. If the source volume does not have an indexed VTOC, a full volume dump of the

conditioned volume VOL002 would not look as if it was dumped from the original source volume VOL001. Rather, it would be an exact image of the conditioned volume. A subsequent full volume restore with the COPYVOLID keyword specified results in the target volume having the same serial number as the conditioned volume.

**FCNOCOPY/FCWITHDRAW** — Using these two keywords in your procedure is recommended when you use FlashCopy.

- You can specify the FCNOCOPY keyword on the COPY command to prevent the ESS subsystem from performing a full physical copy of the volume. Doing so can save subsystem resources and can help to avoid affecting the performance of other I/O operations done by the ESS subsystem.
- You can specify the FCWITHDRAW keyword on the DUMP command to cause DFSMSdss to withdraw the FlashCopy relationship after the volume has been successfully dumped. Doing so frees the subsystem resources that are used to maintain the FlashCopy relationship.

During DUMP FULL and DUMP TRACKS operations, DFSMSdss invokes ICKDSF to initialize the source volume of the DUMP operation at the end of dump processing, when all of the following conditions are true:

- FCWITHDRAW is specified
- The VTOC tracks on the source volume of the DUMP operation are the target of a FlashCopy relationship
- If TRACKS is specified, it designates one extent range that represents the entire volume
- The volume is not a VM-format volume (CP volume)
- The volume supports data set FlashCopy or space efficient FlashCopy.

**Note:** If you perform a dump operation with FCWITHDRAW specified, and the dump source volume is shared between multiple systems, ensure that the DASD is offline to all systems except the one performing the dump.

Timing is an important factor in the successful use of these keywords. In your procedure, allow only a short amount of time to elapse between the completion of step 2 (copy function) and the start of step 4 (backup function). Here, you can specify the FCNOCOPY keyword in step 2 and the FCWITHDRAW keyword in step 4.

Do not use the FCNOCOPY and FCWITHDRAW keywords if the backup (step 4) will not be performed within a reasonable amount of time after the copy (step 2). Otherwise, the use of FlashCopy consumes the subsystem resources for an extended amount of time.

#### **Restrictions:**

• For cases in which the FlashCopy target volume could not be initialized during FCWITHDRAW processing, using the FCNOCOPY keyword on the full volume copy and the FCWITHDRAW keyword on the full volume dump leaves the target volume (of the copy) in an indeterminate state. Some tracks on the volume might contain data from the source volume; other tracks might contain residual data from the target volume that existed before the copy. This indeterminate state can cause problems when accessing the target volume following the dump, if the VTOC locations of the source volumes and the target volumes are different before the copy. To avoid this problem, do one of the following:

- Ensure that the VTOC locations for the source volumes and the target volumes are the same before you initiate the copy.
- Add an ICKDSF INIT step for the target volume of the COPY in step 2. Add this step after step 4 (Backup the copies to tape using full volume dump). The target volume of the copy initializes and returns to a consistent state.
- The FCWITHDRAW keyword is not supported for volumes attached at device address X'0000'.

#### Related information:

For more information about the DUMPCONDITIONING keyword, refer to "DUMPCONDITIONING" on page 325.

For more information about the FCNOCOPY keyword, refer to "FCNOCOPY" on page 333.

For more information about the FCWITHDRAW keyword, refer to "FCWITHDRAW" on page 406.

For information about ICKDSF, refer to Device Support Facilities (ICKDSF) User's Guide and Reference.

# Space considerations

Using larger block sizes saves dump space and improves performance by minimizing the number of I/O operations performed during a dump operation.

The default block size for output records that are written to tape is the optimum block size for the output device (262 144 is the maximum). You can change this default to 32 760 by using the installation options exit routine. Refer to the discussion of system-determined block size in z/OS DFSMS Using Data Sets for a description of the optimum block sizes of the supported tape devices.

For more information about the installation options exit routine, refer to z/OSDFSMS Installation Exits.

For output records that are written to DASD, the block size is the track length of the output volume for devices whose track length is less than 32KB. It is one half the track length for devices whose track length is greater than 32KB. You can select a different block size for tape or DASD by coding DCB=BLKSIZE=block size in the corresponding data set definition (DD) statement. The minimum block size is 7 892 bytes; the maximum is 32 760 bytes.

Note: To include the block size specification in the tape label, specify the BLKSIZE parameter in the tape DD statement.

You can also use the following options to save dump space:

- Dump only the used space (the default if you do not use keywords ALLDATA or ALLEXCP), instead of all allocated space, in sequential and partitioned data sets or in data sets with a null DSORG field. For VSAM key sequenced data sets, the VALIDATE keyword (the default) dumps only the used data instead of all of the allocated space.
- Use the COMPRESS keyword.

#### Note:

1. DFSMSdss ignores the COMPRESS keyword if you specify it during a logical data set dump for physical sequential extended-format data sets.

- 2. If your tape drive has the improved data recording capability (IDRC) and you want to use hardware data compaction, you do not need to use the COMPRESS keyword with the DUMP command. If you want software compression, specify the COMPRESS keyword, but you do not need to specify DCB=TRTCH=COMP in the JCL. In most cases, hardware data compaction without software data compression gives the best performance. However, you can use software compression and hardware compaction at the same time.
- Perform incremental data set backup instead of volume backup. This reduces the amount of dumped data and decreases processing time.
- When dumping to DASD, specify an output dump data set that is extended format in the compressed format. Avoid specifying the COMPRESS or HWCOMPRESS keywords when the output dump data set is extended format in the compressed format. Performance could be degraded since the data may be compressed twice.

## **Performance considerations**

This information provides tips for improving the performance of copy and dump operations.

#### **DUMP**

Dump to tape, where the larger block size reduces the number of I/O operations.

- Use OPTIMIZE(2), (3), or (4) to read more than one track per read operation. This results in the reading of two tracks, five tracks, or a full cylinder, respectively. The default, OPTIMIZE(1), reads one track at a time. OPTIMIZE(2), (3), or (4) results in less elapsed time and fewer I/O operations on the DASD device whenever the load on the tape channel is low enough and the tape speed is high enough to keep pace with the data being read from the DASD volume. To obtain the best performance with DFSMSdss and 3592's, specify OPTIMIZE(4).
- Use the PARALLEL feature to simultaneously dump multiple DASD volumes. **Guideline:** Simultaneous dumping occurs only when the output goes to separate output devices. If the OUTDDNAME keyword specifies the same device, DFSMSdss runs the steps serially.

#### Concurrent copy

To get an exact copy of your data at a specific time, do not update it during the concurrent copy (CC) initialization.

CC initialization includes the time DFSMSdss spends filtering data sets. Therefore, the more precisely you specify the data sets to be processed, the sooner the initialization is completed and the sooner you can update your data again. Here are some ways to reduce initialization time:

- Keep data to be dumped by one DUMP command cataloged in one catalog, if possible.
- Do not specify the DYNALLOC keyword if you do not need dynamic allocation for your data sets.
- Specify fully or almost fully qualified data set names. This reduces the amount of time that DFSMSdss spends searching the catalogs for data sets to process.
- Specify smaller groups of data sets to process together in a DFSMSdss operation.
- Minimize the use of wildcards with the INCLUDE keyword.
- Minimize the use of sophisticated BY filtering to determine the data to be processed.

- Ensure that DFSMSdss can obtain serialization on all data sets being processed.
- Specify WAIT(0,0) to prevent DFSMSdss from waiting for serialization when it cannot be obtained.
- Do not specify the NOTIFYCONCURRENT keyword if you do not need notification of each data set included in the CC session.
- Do not specify the SPHERE keyword if you are not processing VSAM spheres.
- Use the ADMINISTRATOR keyword or DASDVOL RACF protection (where applicable) to bypass authorization checks for each data set being processed.
- Ensure that the volumes containing the VTOC and catalog entries for the data sets to be processed have caching enabled. Also ensure that the catalogs involved are enabled for the in-storage cache (ISC) or the catalog data space cache (CDSC).
- Ensure that data sets being processed have not been migrated by DFSMShsm.

CC uses storage in the control unit cache and in the processor. Here are some ways to minimize the storage needed:

- Limit the amount of data included in the CC operation.
- Use CC during periods of low update activity (as most backups are currently done today).
- Concentrate the update activity in a subset of the data being processed by CC.

## Concurrent copy storage requirements

The concurrent copy (CC) support for the 3990 Model 6 Storage Control uses z/OS data spaces to contain track image copies of the data being processed by the DFSMSdss. The data spaces are backed by expanded storage and local paging spaces. The amount of expanded storage and local paging space required for CC usage is dependent on a number of variables. Based on simulations and test scenarios, a typical data space size is about 10% of the amount of data being dumped or copied with CC.

If your data space size exceeds this nominal value, you may need to consider the following planning guidelines for determining how much expanded storage or local paging space may be required for the following CC functions:

- Full volume and tracks copy; and full volume, tracks and physical data set dump operations:
  - All volumes are processed on a track-by-track basis by DFSMSdss. The data space requirements can vary from 0% for a volume that has no updates during the DFSMSdss operation to 100% if the entire volume is updated before DFSMSdss can process it. For example, a 3390–3 that is 80% full (2671 cylinders) may require up to 2671 cylinders of data space storage if the volume is completely rewritten before DFSMSdss can process it. An example of this situation would be that a volume contains many VSAM data sets and a reorganization is done for all of the VSAM data sets on the volume while the CC job is being run for the volume.
- Logical data set copy and dump processing of non-VSAM data sets and nonindexed VSAM data sets (for example, VSAM ESDS), logical data set copy of indexed VSAM data sets (for example, VSAM KSDS), and logical data set dump of indexed VSAM data sets processed with NOVALIDATE are described as follows:

These data sets are processed on a track-by-track basis by DFSMSdss. The data space is used to contain updates for tracks that have not yet been processed by DFSMSdss. The data space requirements can vary from 0% for a data set that has no updates during the DFSMSdss operation to 100% if the entire data set is updated before DFSMSdss can process it. For example, a 50-cylinder data set

may require up to 50 cylinders of data space storage if the data set is completely rewritten before DFSMSdss can process it.

• Logical data set dump of indexed VSAM data set (for example, VSAM KSDS) processed with VALIDATE is described below:

These data sets are processed with numerous accesses to sequence set information in the index component and track-by-track accesses to the data component. In all cases, update activity to either the data component or the index component maintains a copy of the updated track in the data space until the track is either processed by DFSMSdss or the dump operation is ended for all data sets.

Index component tracks that do not contain sequence set information and data component tracks that are beyond the high used relative byte address are included in the CC operation but are never read by DFSMSdss. If those tracks are updated, they will remain in the data space for the duration of the dump operation for all data sets. If the data set has the sequence set information imbedded in the data component (using the IMBED attribute), no additional (nonupdated) tracks are maintained in the data space. If the data set has the sequence set information in the index component, then all index component tracks containing sequence set information will be maintained in the data space (whether they were updated or not) for the duration of the dump processing for the data set. For example, if the index for a VSAM data set is 20 cylinders and the data is 2500 cylinders, plan paging space of 20 cylinders for the index component.

Based on the update activity during the dump operation, plan to use a paging space of between 0 and 2500 cylinders for the data. The most data space is used when doing a complete reorganization while dumping the VSAM data set. This requires 2520 cylinders of space. If only 10% of the data will change during the operation, you will need 20 cylinders for the index and 250 cylinders for the data or 270 cylinders of paging space.

In using CC against aggregate groups, determine the data space storage requirements based on the expected update rate to the data sets during the dump operations. Failure to allocate sufficient local paging space may result in system failures due to insufficient paging storage.

**Note:** All storage requirements will be in addition to the working set of storage required by *all* other applications active (including all other CC operations) during the execution of the DFSMSdss CC operation.

## Virtual concurrent copy working space

DFSMSdss might use virtual concurrent copy for storage devices that support SnapShot or data set FlashCopy when the CONCURRENT keyword is specified with the DFSMSdss commands. During virtual concurrent copy, data is "flashed" or "snapped" from the source location to the intermediate location, and then copied to the target location using standard I/O. The operation is logically complete after the source data is "flashed" or "snapped" to the intermediate location and physically complete after the data is moved to the target media.

### Virtual concurrent copy using SnapShot:

Before you can use the SnapShot function for virtual concurrent copy, you must ensure that working space is available by allocating working space data sets (WSDS) on one or more volumes in the same RAMAC Virtual Array (RVA) subsystem as the source data sets. System Data Mover (SDM) uses the working space data sets as the intermediate location for virtual concurrent copy.

The naming convention for these working space data sets is:

SYS1.ANTMAIN.Ssysname.SNAPnnnn.

Variable sysname is the system identifier and nnnn is a four-digit decimal number in the value range 0001-9999. If the system identifier is eight characters, 'S' replaces the first character.

The SnapShot working space data sets must be physical sequential, non-extended-format, single volume, and cataloged. SDM performs a numerically sequential catalog search for each data set, starting with hlq.ANTMAIN.Ssysname.SNAP0001 until a data set is found or until it encounters a catalog locate error, indicating that the data set was not found. SDM does not use working space data sets with the naming convention beyond the data set that was not found. The SnapShot working space data sets can be SMS-managed or non-SMS-managed. You cannot allocate VSAM or multivolume data sets as SnapShot working space data sets.

If you want to allocate secondary space, you must extend the data set by filling it with data before you start the DFSMSdss job. System Data Mover (SDM) does not extend a working space data set. SDM holds an enqueue for the data set when the SnapShot operation uses working space data set and releases the enqueue after SnapShot operation finishes using the data set. You can reallocate or extend a working space data set only when SDM does not have the data set enqueued. SDM uses the new reallocated or extended data set on subsequent runs of the SnapShot operation.

You can add more working space data sets after ANTMAIN completes the initialization process. SDM uses these data sets the first time it encounters an out-of-working-space condition during a SnapShot operation. When this condition occurs, SDM refreshes the list of working space data sets by performing a catalog search that starts with SYS1.ANTMAIN.Ssysname.SNAP0001.

The LRECL and block size can be any valid combination. The tracks within the data set are used as the target of SnapShot operations, and you should not try to access them using normal data access methods.

## Virtual concurrent copy using FlashCopy:

Before you can use the FlashCopy function for virtual concurrent copy, you must ensure that working space is available by allocating working space data sets (WSDS) on one or more volumes in the same, data set FlashCopy enabled, storage subsystem as the source data sets. System Data Mover (SDM) uses the working space data sets as the intermediate location for virtual concurrent copy.

The naming convention for using these working space data sets is:

#### hlq.ANTMAIN.FCWKnnnn

Variable *hlq* is the high level qualifier that you specify in the SDM PARMLIB member and *nnnn* is a four-digit decimal number in the value range 0000–9999. If you use both VSAM and physical sequential data sets, you must specify unique nnnn component of the name across both kinds of data sets.

The working space data sets must be cataloged. SDM performs a catalog search for usable working space data sets that match the naming convention. You must

allocate data sets as single-volume, non-indexed VSAM data sets such as LDS and ESDS, or non-extended-format sequential data sets. You can use extended-format non-indexed VSAM data sets. The data sets can be SMS-managed or non-SMS-managed.

If you want to allocate secondary space, you must extend the data set by filling it with data before you start the DFSMSdss processing. System Data Mover (SDM) does not extend a working space data set. SDM holds an enqueue for the data set when the FlashCopy operation uses working space data set and releases the enqueue after FlashCopy operation finishes using the data set. You can reallocate or extend a working space data set only when SDM does not have the data set enqueued. SDM uses the new reallocated or extended data set on subsequent runs of the FlashCopy operation.

You can add more working space data sets after ANTMAIN completes the initialization process. SDM uses these data sets the first time it encounters an out-of-working-space condition. When this condition occurs during a FlashCopy operation, SDM refreshes the list of working space data sets by performing a catalog search for data set names that match the naming convention.

The LRECL and block size can be any valid combination. The VSAM control interval (CI) size can be any value. SDM uses the tracks within the data set as the target of FlashCopy operations, and you should not try to access them using normal data access methods.

#### Common working space data sets considerations:

To ensure that unauthorized users cannot access sensitive data, IBM recommends that your installation use RACF, or an equivalent security product, to protect the working space data sets.

You must allocate data sets on a volume in each storage subsystem that you are using for virtual concurrent copy. If you define more than one device type on the storage subsystem, you must allocate a working space data set on each device type that contains a data set that you intend to process using SnapShot or FlashCopy.

You must allocate at least one working space data set, if a system or device type for concurrent copy operation runs simultaneously from more than one system and accesses data on the same storage subsystem. For example, you must allocate three working space data sets to process data on an RVA subsystem from three z/OS systems, on devices of each device type containing data processed with concurrent copy.

The total size of all working space data sets that you allocate on each storage subsystem should be equal to or exceed the largest total amount of data to be processed in a single DFSMSdss COPY or DUMP operation on that storage subsystem. If there is insufficient space, the concurrent copy initialization for one or more data sets in the job fails.

For more information about virtual concurrent copy and working space data sets, refer to *z/OS DFSMS Advanced Copy Services*.

## Read DASD I/O pacing

You can tune the performance of a system by pacing the DFSMSdss read DASD I/O operations. Pacing reduces the channel utilization and lets other I/O (for

example, from the database application) be processed in a more timely fashion. The pacing is done by waiting a specified amount of time before issuing each channel program that reads from DASD.

Note: The additional wait time does not apply to error recovery channel programs or concurrent copy I/O. The System Data Mover dynamically controls pacing for concurrent copy I/O.

**Invocation from a customer program:** The value of the READIOPACING parameter can also be controlled through the installation options exit, a product-sensitive programming interface intended for customer use.

For more information about the installation options exit, refer to z/OS DFSMS Installation Exits.

## Shared DASD considerations

Shared DASD presents volume and data set serialization problems not encountered in nonshared DASD environments. Care should be taken when you enlist data set operations if programs operating in another processor might be accessing the data sets at the same time.

A data set can be dumped from one processor while being processed from another. The dumped version may be partially updated on JES2 systems. This same exposure is present on a full dump operation.

# Backing up and restoring volumes with incremental **FlashCopy**

You can use Incremental FlashCopy to create an initial point-in-time copy of a source volume and refresh the target volume by copying only the changed data. Incremental FlashCopy operates at the full volume level.

After the initial full volume copy of the source volume to the target volume, the FlashCopy relationship remains (persists) between the source and target volume pair and the changes on the source and target volumes since the last point-in-time copy are tracked. When you refresh the target volume at a new point-in-time, only the changed tracks are copied. Incremental FlashCopy helps reduce the physical background copy time when only a subset of the data on the source or target has changed.

The direction of the refresh can be reversed when you indicate the original target now becomes the source and the original source becomes the target. If the new target is the source of a Multiple Incremental FlashCopy relationship (Incremental FlashCopy Version 2), before reversing the direction of the FlashCopy, you must withdraw any other relationships. Only the changed data since the last point-in-time copy is copied. If no updates were made to the target since the last incremental copy, the reverse of FlashCopy direction can be used to restore the original source back to the previous point-in-time state.

## Using the FCINCREMENTAL keyword

You can use the FCINCREMENTAL keyword for a COPY FULL or COPY TRACKS CPVOLUME commands to perform an initial full volume copy if no Incremental FlashCopy relationship exists between the volume pair. If there is an existing Incremental FlashCopy relationship between the volume pair, DFSMSdss copies the changed tracks in the new direction specified on the INDDNAME/INDYNAM and

## Using the FCINCREMENTALLAST keyword

You can use the FCINCREMENTALLAST keyword on the COPY FULL or COPY TRACKS CPVOLUME commands to copy the changed tracks when there is an Incremental FlashCopy relationship between the volume pair.

FCINCREMENTALLAST specifies that the new FlashCopy relationship is to be non-persistent and change recording is to be stopped after the final increment has been established. The FlashCopy relationship ends when background copy for the final increment has completed.

## Using the FCINCRVERIFY keyword

You can use the FCINCRVERIFY(NOREVERSE | REVERSE) keyword to verify that the existing Incremental FlashCopy direction is what you expected. DFSMSdss fails the copy attempt if the existing direction is not as expected or the original source volume has existing Incremental FlashCopy relationships.

## Using the FCWAIT keyword

When you reverse the direction of an Incremental FlashCopy, the storage facility requires that the previous background copy be completed. You can specify the FCWAIT keyword with a query interval value in seconds and a number of retries value to direct DFSMSdss to wait for background copy completion before initiating the new Incremental FlashCopy.

#### Note:

| |

| |

- 1. Incremental FlashCopy Version 2 supports up to the maximum number of full volume flashcopies allowed for a source, which is 12. The initial Incremental FlashCopy support, known as Incremental FlashCopy Version 1, allows only 1 full volume FlashCopy to be incremental. A Version 1 Incremental FlashCopy relationship can coexist with Version 2 Incremental FlashCopy relationships.
- 2. Incremental FlashCopy is only possible with a persistent relationship. With persistent relationships, the relation between the source and target is maintained after the background copy has completed.
- 3. DFSMSdss allows you to copy full volumes to target devices of greater capacity. However, if the original FlashCopy target volume is bigger than the source volume, you cannot reverse the FlashCopy direction.
- 4. When you specify DUMPCONDITIONING with FCINCREMENTAL, the volume serial number of the target volume does not change, and the target volume remains online after the copy. A subsequent incremental copy can be made without additional procedure.
- 5. When you specify COPYVOLID with FCINCREMENTAL, the volume serial number of the target volume is changed to match the source's. When the volume serial number on a DASD volume is changed, the operator is notified. The operating system then initiates a demount of the volume. Before performing a subsequent incremental copy using DFSMSdss, the offline volume's volume serial number must be changed through a utility such as ICKDSF and the volume must be varied online.
- 6. The PURGE keyword might be required on subsequent incremental copies.

## Usage scenario 1: periodic dump to tape

The following example describes how Incremental FlashCopy can be used to create periodic backups to tapes.

- Step 1 Copy volume VOL00A->VOL00B by performing initial Incremental FlashCopy from volume VOL00A to VOL00B. Background copy task copies all the tracks on the source volume to the target volume.
  - COPY FULL INDYNAM(VOLOOA) OUTDYNAM(VOLOOB) DUMPCONDITIONING -ADMIN PURGE FCINCREMENTAL
- · Step 2 Backup volume VOL00A by performing full volume dump from volume VOL00B to tape.
  - DUMP FULL INDYNAM(VOLOOB) OUTDD(TAPEO1)
- Step 3 Allow update to volume VOL00A
- Step 4 Refresh volume VOL00B by performing subsequent Incremental FlashCopy from volume VOL00A to volume VOL00B. Background copy task copies changed tracks from volume VOL00A to VOL00B.
  - COPY FULL INDYNAM(VOLOOA) OUTDYNAM(VOLOOB) DUMPCONDITIONING -ADMIN PURGE FCINCREMENTAL
- Step 5 Repeat steps 2-4.

## Usage scenario 2: check-point batch processing with incremental FlashCopy

Below is an example of how DFSMSdss Incremental FlashCopy can be used in check-point batch processing. DFSMSdss Incremental FlashCopy does not inhibit target writes. To be able to restore the original source to the state of the previous point-in-time copy, the user must not have written to the target volume after DFSMSdss finished the previous copy operation. To improve performance, the user can also specify the optional ADMINISTRATOR keyword.

- Step 1 Backup volume VOL00A->VOL00B by performing initial Incremental FlashCopy from volume VOL00A to VOL00B. Background copy task copies all the tracks on the source volume to the target volume.
  - COPY FULL INDYNAM(VOLOOA) OUTDYNAM(VOLOOB) DUMPCONDITIONING -ADMIN PURGE FCINCREMENTAL
- Step 2 Start batch application which makes updates to volume VOL00A.
- Step 3 Backup volume VOL00A->VOL00B by performing subsequent Incremental FlashCopy. Background copy task copies only updated tracks from volume VOL00A to volume VOL00B.
  - COPY FULL INDYNAM(VOLOOA) OUTDYNAM(VOLOOB) DUMPCONDITIONING -ADMIN PURGE FCINCREMENTAL
- Step 4 Start batch application which makes updates to volume A.
- Step 5 When batch updates are incomplete or the batch job ends abnormally, tell DFSMSdss to wait for background copy completion (here, we use a query interval value of 30 seconds and 10 retries) and perform Incremental FlashCopy in reversed direction to restore the previous point-in-time copy (made in step 3). Background copy task copies only updated tracks from volume VOL00B to VOL00A. The user indicates the original source (VOL00A) is now the target and the original target (VOL00B) is now the source on the DFSMSdss COPY command. FCINCREMENTAL indicates Change Recording and Persistent Relationship should continue.
  - COPY FULL INDYNAM(VOLOOB) OUTDYNAM(VOLOOA) DUMPCONDITIONING -ADMIN PURGE FCINCREMENTAL FCWAIT(30,10)

Optionally, FCINCRVERIFY(REVERSE) can be specified to verify that the Incremental FlashCopy direction is what was expected:

COPY FULL INDYNAM(VOLOOB) OUTDYNAM(VOLOOA) DUMPCONDITIONING -ADMIN PURGE FCINCREMENTAL -FCINCRVFY(REVERSE) FCWAIT(30,10)

- Step 6 Restart batch application which makes updates to volume VOL00A.
- Step 7 When batch application errors occur, perform Incremental FlashCopy without reversing the direction. There is no need to wait for background copy completion.

COPY FULL INDYNAM(VOL00B) OUTDYNAM(VOL00A) DUMPCONDITIONING - ADMIN PURGE FCINCREMENTAL

Restart batch application which updates volume VOL00A.

If batch application errors occur again, repeat step 7.

- Step 8 Upon successful batch application completion, perform Incremental FlashCopy in reversed direction and make a new backup copy of VOL00A:
   COPY FULL INDYNAM(VOL00A) OUTDYNAM(VOL00B) DUMPCONDITIONING -ADMIN PURGE FCINCREMENTAL FCWAIT(30,10)
- Step 9 Restart batch application which updates volume VOL00A.

For more information, refer to "FCINCREMENTAL" on page 330, "FCINCREMENTALLAST" on page 331, "FCINCRVERIFY" on page 332, and "FCWAIT" on page 337.

For more information about Incremental FlashCopy and Persistent FlashCopy, refer to *z*/*OS DFSMS Advanced Copy Services*.

# Securing your tape backups

Data encryption is an important tool for protecting against the possible misuse of confidential information that could occur should tapes be lost or stolen. Unless the possessor of the tape has the required key, any encrypted data on the tape will remain confidential and will be unreadable. Thus, securing tape backups should be part of your installation's overall security plan.

You can secure your tape backups either through *tape device encryption* (with an encryption-capable tape drive) or through *host-based encryption* — that is, by requesting that DFSMSdss encrypt the data before writing it to the dump data set on DASD or tape (during a DUMP or COPYDUMP operation).

With tape device encryption, you secure data by using encryption capable tape drives that encrypt data as the output is written to tape during DUMP and COPYDUMP functions. To request that a tape device encrypt data, you specify JCL DD keywords or DATACLAS definitions for the output DFSMSdss dump data set. You can restore tape device encrypted dump data sets through the RESTORE and COPYDUMP functions.

DFSMSdss allows a mixture of encrypting and non-encrypting tape devices for the output of DUMP and COPYDUMP commands.

In general, you can use tape device encryption or software encryption to encrypt a particular tape volume, but not both methods. If you request software encryption and one of the output devices is encrypting the data written to it, then DFSMSdss overrides software encryption. DFSMSdss does not write the data to any of the output devices that do not encrypt data and issues an ADR519E message indicating that some outputs are not processed. DFSMSdss issues the ADR519E message for each of the output data sets that are not backed up. DFSMSdss continues processing.

If you do not request software encryption, DFSMSdss writes to multiple outputs where some are encrypting data in the hardware and some are not. DFSMSdss

continues to notify an application through its Application Programming Interface (Exit 06 and Exit 26) that the particular output is encrypting the data written to it.

Observe the following considerations:

- · Use tape device encryption if your installation includes one or more encryption-capable tape drives. Here, you specify by data class which data is to be encrypted when stored on the tape drives.
- Use host-based encryption if you do not have an encryption-capable tape drive. You can encrypt tape backups through the host-based encryption method described in the sections that follow.

For a description of how DFSMSdss handles conflicting encryption requests, refer to "DFSMSdss processing of dump encryption requests" on page 69.

# Using host-based encryption to secure backups

When backing up your data, you can secure it through host-based encryption. You request host-based encryption on the DFSMSdss DUMP command. As with tape device encryption, host-based encryption through DFSMSdss provides a means of encrypting your installation's tape volumes.

Usually, DFSMSdss does not allow double encryption of data with the DUMP command. For a description of how DFSMSdss handles conflicting encryption requests, refer to "DFSMSdss processing of dump encryption requests" on page 69.

In the unlikely event that your installation requires double encryption for a dump data set, you can use the procedure described in "If double encryption is required" on page 70 to dump and restore a doubly-encrypted data set.

## Types of host-based encryption

DFSMSdss can use the following types of host-based encryption to secure your

- Triple-length Data Encryption Standard (TDES) clear keys
- Secure TDES keys
- 128-bit Advanced Encryption Standard (AES) clear keys.

What is DES and AES?: To manage cryptographic keys for encrypted data, DFSMSdss uses IBM Cryptographic Services Facility (ICSF), which supports the following cryptographic standards and architectures:

- IBM Common Cryptographic Architecture (CCA) that is based on the ANSI Data Encryption Standard (DES)
- Advanced Encryption Standard (AES).

With DES, two parties share secret keys that are used to protect data and keys that are exchanged on the network. The sharing of secret keys establishes a secure communications channel. The only way to protect the security of the data in a shared secret key cryptographic system is to protect the secrecy of the secret key. ICSF also supports triple DES encryption for data privacy. TDES triple-length keys use three, single-length keys to encipher and decipher the data. This results in a stronger form of cryptography than that available with single DES encipher.

With AES, data can be encrypted and decrypted using 128-bit, 192-bit, and 256-bit clear keys. CBC and ECB encryption are also supported. For public key cryptography, ICSF supports both the Rivest-Shamir-Adelman (RSA) algorithm 1, and the NIST Digital Signature Standard (DSS) algorithm. RSA and DSS are the most widely used public key encryption algorithms. In this system, each party

establishes a pair of cryptographic keys, which includes a public key and a private key. Both parties publish their public keys in a reliable information source, and maintain their private keys in secure storage.

Cryptographic keys and DFSMSdss: DFSMSdss uses TDES triple-length keys and 128-bit AES keys for host-based encryption. On a system with secure cryptographic hardware, you can use DFSMSdss to generate TDES and AES keys and encrypt them for protection through RSA public keys. On systems without secure cryptographic hardware, a password allows the generation of clear TDES and AES keys. The use of these cryptographic keys with DFSMSdss depends on the type of processor and the type of cryptographic hardware that you have installed.

RSA public and private keys for encryption can be stored in the ICSF Public Key Data Set (PKDS). These RSA keys are used by DFSMSdss to protect the symmetric keys that protect the data. You can use RACF commands to store public/private keys.

## Considerations for host-based encryption

The choice of which type of host-based encryption to use depends on several factors, including performance and level of security. On the DFSMSdss DUMP command, you can request the different types of host-based encryption:

- A clear TDES key; specify the CLRTDES subparameter of the ENCRYPT keyword
- A secure TDES key; specify the ENCTDES sub parameter of the ENCRYPT keyword
- A clear 128-bit AES key; specify the CLRAES128 subparameter of the ENCRYPT keyword.

The decision to use CLRTDES or ENCTDES key values depends on the kind of cryptographic hardware you have, the level of security you want, and the level of performance you require.

For DFSMSdss, a CLRTDES key is a triple-length TDES key that is generated dynamically. Unlike the ENCTDES key value the CLRTDES key value can appear in application storage. If DFSMSdss is running on a z890, z990, or System z9<sup>®</sup> 109, the data is encrypted using the clear TDES key on the CPACF, and this usually results in better performance than if you are using the ENCTDES key value.

The ENCTDES key is a triple-length TDES key that is generated within the secure boundary of the cryptographic hardware (CCF, PCICC, PCIXCC, or CEX2C), and it uses the ICSF symmetric master key to encrypt the data. The clear value of an ENCTDES key never leaves the boundary of the secure cryptographic hardware. Encryption and decryption of data using an ENCTDES key requires secure cryptographic hardware to be available.

Each type of key is equally secure in regards to the data that appears in the output data set.

The CLRAES128 option generates a 128-bit AES key. The key value can appear in application storage. If DFSMSdss is running on a z9 or z10 processor, the data is encrypted using CPACF. If DFSMSdss is running on any other type of processor, the data is encrypted by ICSF.

During DUMP processing, only user data may be encrypted. This means that VTOC and VVDS tracks that are processed are not encrypted. The data set names and other content from the VTOC will appear unencrypted in the output dump data set.

## **Key management considerations**

The RSA and KEYPASSWORD keywords are used for key management by DFSMSdss. The choice of one over the other depends on your environment and needs.

KEYPASSWORD Keyword: Generally, if you are encrypting low volumes of data or if you do not have secure cryptographic hardware installed, you can specify the KEYPASSWORD keyword. NOTE: Passwords are case sensitive.

The iteration count (ICOUNT) in Password Based Encryption (PBE) is intended to strengthen weak passwords. If the password is robust (that is, 32 random characters), the default of 16 provides reasonable security and performance. Most PBE schemes assume that weak password are chosen; thus, iteration counts of 1000 or higher are often normal.

#### Note:

You must take care when using the KEYPASSWORD keyword. The same password specified on the DUMP task must be specified on the RESTORE task. The password is not stored in the dump data set in any form. If the password is lost, the encrypted data in the dump data set cannot be decrypted.

The same password with the same iteration count (ICOUNT) generates the same data key. This means that if the same password is used for many DUMP tasks, all of the data from those DUMP jobs are protected by the same key. If the password is compromised, all of the dump data is vulnerable.

RSA Keyword: The RSA keyword makes use of public/private keys for encryption and the exchange of digital certificates. You specify the label of the public key that is stored in the ICSF PKDS on the RSA keyword when you dump and encrypt the data. The corresponding RSA private key must be present at the recovery site when you decipher the data. A recipient at another site can only decrypt the data through the private key that is specified on the RSA keyword during the RESTORE job. If the original RSA key and label exist in the system's ICSF PKDS, then the RSA keyword need not be specified. The original RSA label is stored on the dump data set for convenience.

If the same RSA label and key are used during multiple dumps, each dump has its data encrypted with a different symmetric key. Thus, if the symmetric key of one dump is discovered, the data in the other dumps is still secure.

#### Using compression with host-based encryption

When archiving large amounts of encrypted data, you can compress the data, for example, to reduce the number of tape volumes needed.

Some tape devices make use of their own compression when you store data. Encrypted data is not highly compressible, so you might want to compress your data prior to encryption using the HWCOMPRESS keyword.

During DUMP processing, only user data may be compressed. This means that VTOC and VVDS tracks that are processed are not compressed. The data set names and other content from the VTOC will appear uncompressed in the output dump data set.

## **Examples of host-based encryption**

In the following example, DFSMSdss is used to perform a full volume dump and to compress and encrypt the volume data using a clear TDES key. The clear TDES key is protected using an RSA private key.

```
DUMP FULL INDYNAM(VOL001) OUTDD(TAPE1) -
ENCRYPT(CLRTDES) RSA(SYSTEM.PRIVATE.S01024) -
HWCOMPRESS OPTIMIZE(4)
```

The following is an example of the RESTORE command you would use to restore the data on a system that has the same RSA private key with the same label:

RESTORE FULL INDD(TAPE1) OUTDYNAM(VOL001)

The following example shows the keywords needed to restore the data on a different system that has had the original RSA private key loaded into ICSF under a different label:

```
RESTORE FULL INDD(TAPE1) OUTDYNAM(VOL001) - RSA(NEWSYSTEM.PRIVKEY.S01024)
```

The following example shows the backup and recovery of data sets while using 128-bit AES encryption to secure the data. Note that a password is used for key management:

```
DUMP DATASET(INCLUDE(SOURCE.**)) -
OUTDDNAME(TAPE2) HWCOMPRESS -
KEYPASSWORD(mySecretPASSWORD) -
ENCRYPT(CLRAES128)

RESTORE DATASET(INCLUDE(SOURCE.**)) -
INDDNAME(TAPE2) -
REPLACE KEYPASSWORD(mySecretPASSWORD)
```

#### Hardware requirements for encryption and decryption

If you plan to use the RSA option with DFSMSdss to encrypt the data-encrypting key, you must consider the cryptographic hardware that exists at the site that will decrypt the data. Not all types of RSA private keys are supported by all types of cryptographic hardware.

Table 7 summarizes the RSA private tokens and required cryptographic hardware for decryption.

Table 7. RSA private tokens and required cryptographic hardware for decryption

RSA private key token (internal)	Required cryptographic hardware
RSA private key token 1024 — Modulus-Exponent Internal form	One of the following:
RSA private key token 1024 — Chinese Remainder Theorem Internal form	One of the following:  • PCI Cryptographic Coprocessor  • PCI X Cryptographic Coprocessor  • Crypto Express2 Coprocessor.

Table 7. RSA private tokens and required cryptographic hardware for decryption (continued)

RSA private key token (internal)	Required cryptographic hardware
RSA private key token 2048 — Chinese Remainder Theorem Internal form	One of the following:  • PCI Cryptographic Coprocessor with LIC January 2005 or later, and z/OS ICSF HCR770B or later  • PCI X Cryptographic Coprocessor  • Crypto Express2 Coprocessor.

For more information, refer to z/OS Cryptographic Services ICSF Application Programmer's Guide.

## Performance and processor types

The performance of host-based encryption can vary, depending on the type of processor and encryption being used. For example, DFSMSdss can use the Cipher Message with Chaining (KMC) System z instruction for some types of encryption if it is running on the appropriate processor. If the KMC instruction is not available or the type of encryption requires it, DFSMSdss uses the appropriate ICSF service to perform the encryption.

The table below describes the method of encryption that is used under various encryption types and processors.

Processor Encryption Type	Method of Encryption
z/800, z/900 o Clear TDES o Clear 128-bit AES o Secure TDES	ICSF Service ICSF Service ICSF Service
z/890, z990 o Clear TDES o Clear 128-bit AES o Secure TDES	KMC instruction ICSF Service ICSF Service
z8, z9 109 o Clear TDES o Clear 128-bit AES o Secure TDES	KMC instruction KMC instruction ICSF Service

## Software requirements for encryption and decryption

To perform encryption and decryption, DFSMSdss requires the following software to be installed and active on your system:

- Encryption Facility DFSMSdss Encryption Feature (HCF773D)
- IBM Cryptographic Services Facility (ICSF) (HCR770B or higher).

#### ICSF callable services for DFSMSdss

DFSMSdss invokes ICSF callable services for the DUMP command. If your installation uses RACF or a similar security product, ensure that the security administrator authorizes DFSMSdss to use the following services and any cryptographic keys that are specified as input:

- CSFCKM Multiple clear key Import
- CSFENC Encipher
- · CSFRNG Generate a random number
- CSFSYE Encipher using clear DES/AES key
- CSFPKE Public key encrypt
- CSFSYG Generate and wrap a symmetric key

- CSFSYX Export a symmetric key
- · CSFOWH One-way hash.

Similarly, ensure that the security administrator authorizes DFSMSdss to use the following ICSF callable services and cryptographic keys for the RESTORE command:

- · CSFCKM Multiple clear key import
- CSFDEC Decipher
- CSFSYD Decipher using clear DES/AES key
- CSFOWH One-way hash
- CSFPKD Public key decrypt
- CSFSYI Import a symmetric key.

For information about ICSF callable services, refer to *z/OS Cryptographic Services ICSF Application Programmer's Guide*.

# DFSMSdss processing of dump encryption requests

You can use tape device encryption or host-based encryption to encrypt a tape volume, but not both methods. Because DFSMSdss avoids performing double encryption of tape data, you must determine which type of encryption, if any, is to be used for your tape volumes. In general, DFSMSdss prevents you from combining both types of encryption to perform double encryption of tape volumes.

Table 8 shows how DFSMSdss processes potential double encryption requests, specified through the DFSMSdss DUMP command.

Table 8. DFSMSdss processing of dump encryption requests

Dump encryption request	DFSMSdss action
Your DUMP command specifies host-based encryption (through the RSA or KEYPASSWORD keywords), and all of the available tape drives are encryption-capable tape drives. Your request might also specify host-based compression (through the HWCOMPRESS keyword).	<ul> <li>DFSMSdss issues informational message ADR518I to indicate that tape device encryption was used instead of host-based encryption</li> <li>DFSMSdss ignores the compression request, if any.</li> </ul>
Your DUMP command specifies host-based encryption and one or more of the available tape drives are not encryption enabled. Your request might also specify host-based compression.	<ul> <li>DFSMSdss issues error message ADR519E to indicate that one or more of the available tape drives cannot perform encryption. To avoid performing double encryption of data, DFSMSdss uses only encryption-capable tape drives. DFSMSdss issues error message ADR324E to list the unused output devices.</li> <li>DFSMSdss ignores the compression request, if any.</li> <li>DFSMSdss continues processing the DUMP request as long as there are usable tape drives. On completion, DFSMSdss ends the task with return code 8.</li> </ul>
Your DUMP command does not specify host-based encryption and all of the available tape drives are encryption-capable tape drives. Your request might also specify host-based compression.	<ul> <li>Encryption-capable tape drives perform encryption</li> <li>DFSMSdss performs host-based compression, if requested.</li> </ul>

Table 8. DFSMSdss processing of dump encryption requests (continued)

Dump encryption request	DFSMSdss action
Your DUMP command does not specify host-based encryption and one or more of the available tape drives are not encryption enabled. Your request might also specify host-based compression.	<ul> <li>DUMP requests for encryption-capable tape drives are encrypted by the tape drives</li> <li>DUMP requests for non-encrypting tape drives are processed without encryption of any type</li> <li>DFSMSdss performs host-based compression, if requested.</li> </ul>

For tapes that require host-based encryption, ensure that your dump-requesting jobs use only tape drives that are not encryption capable. To do so, check the data classes of the output ddnames to ensure that the jobs do not specify a data class that requests encryption from the encryption-capable tape drives.

## If double encryption is required

In the unlikely event that your installation requires double encryption for a dump data set, you can use the following procedure:

- 1. Request host-based encryption for the data set (through the RSA or KEYPASSWORD keywords) and write the data set to a non-encrypting output
- 2. Use the DFSMSdss COPYDUMP command to copy the dump data set to an encrypting tape device.

To restore the double-encrypted dump data set, use the DFSMSdss RESTORE command. The encryption capable tape drive decrypts the dump data set and then DFSMSdss performs host-based decryption for the data set.

# Restoring data sets

With the RESTORE command, you can restore data to DASD volumes from DFSMSdss-produced dump volumes, which are identified with the INDDNAME keyword.

The restore function is logical or physical, depending upon the dump volume. If the dump volume was made physically, a physical restore is made. If it was made logically, a logical restore is made. If the data was compressed when it was dumped, it is automatically expanded to its original form during the restore operation.

Using the ALLDATA or ALLEXCP keyword during a dump affects target data set allocation during a restore. Only used space is dumped for both a physical and logical data set dump unless the ALLDATA or ALLEXCP keyword is specified as part of the DUMP command.

When ALLDATA or ALLEXCP is specified, the total allocated space is dumped. During a physical data set restore, the target data set is allocated with the same amount of space as the source data set. During a logical data set restore (without the ALLDATA or ALLEXCP keyword), the target data set is allocated according to the amount of space used in the data set, thereby releasing unused space. If logical data set processing is used and the target data set must preserve the total allocation of the source, the ALLDATA or ALLEXCP keyword should be specified during the dump.

When ALLDATA or ALLEXCP is specified for an extended-format sequential data set, data beyond the last-used-block pointer is not retained. The target data set is allocated with the same amount of space as the source data set during a logical restore or copy operation.

As with a data set DUMP command, you can use filtering to select data sets for restore processing. DFSMSdss reads the entire dump data set once during a restore regardless of how much data is actually being restored. This will result in multiple tape mounts if the dump data set is on multiple tapes.

Attention: You should restore a dumped data set that has extended attributes in an F9 DSCB to a volume that supports F8/F9 DSCBs. Otherwise, these extended attributes are lost. DFSMSdss propagates the vendor attributes if they exist in the F9 DSCB of the primary volume when DFSMSdss performs catalog processing or if they exist in the first volume that DFSMSdss processes when you specify input volumes. To prevent losing extended attributes, all volumes that contain data sets with vendor attributes in the F9 DSCB must be extended address volumes.

**Note:** Fully qualified names are required to restore the following data sets:

- VVDS
- VTOCIX
- SYS1.STGINDEX
- Integrated catalog facility catalogs
- OS catalog
- VSAM read-only data sets (temporarily exported with the INHIBITSOURCE parameter).

For more information about filtering, refer to Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259.

For information about using automatic class selection (ACS) routines during DFSMSdss restore operations, refer to Chapter 11, "ACS routine information," on page 179.

# Logical data set restore

A logical data set restore is performed if you are restoring from a volume created with a logical dump operation and if you specify the DATASET keyword. For instance, the following RESTORE command generates a logical data set restore if the volume was created with a logical dump operation.

```
RESTORE INDDNAME(TAPE) -
DATASET(INCLUDE(USER1.OLDDS)) -
REPLACE
```

**Note:** DFSMSdss logical restore processing cannot be used to process partitioned data sets containing location-dependent information that does not reside in note lists or the directory.

#### **Output volume selection**

In most cases, specifying output volumes is optional for a logical data set RESTORE command. Output volume specification is required only if the data set:

• Exists and is to be restored to a volume that is different from the current location

 Does not exist and is to be restored to a volume that is different from the source volume.

Specify output volumes with the OUTDDNAME or OUTDYNAM keywords. An example of a logical data set RESTORE command with OUTDDNAME is:

```
RESTORE
       INDDNAME(TAPE) OUTDDNAME(DASD1) -
       DATASET(INCLUDE(**))
```

When not specified, the volume on which the source data set currently resides is found from the catalog and is dynamically allocated. To do this, you must include the REPLACE keyword. This is particularly useful on a data set restore operation from a data-set-selection-by-catalog dump because you need not know where the data sets resided at dump time.

You can specify multiple output DASD volumes on a logical data set RESTORE command. This is required when all the data sets to be restored cannot fit on a single volume. An example of a logical data set restore operation with a spill volume specified is:

```
RESTORE
       INDDNAME(TAPE) OUTDYNAM((338001),(338002)) -
       DATASET(INCLUDE(PARTS.**))
       PCTU(80)
```

Note the use of the PERCENTUTILIZED (PCTU) keyword in the above example. With PERCENTUTILIZED, you can set a limit on the amount of space DFSMSdss can fill on the volume. When this limit is reached, subsequent data sets are allocated to other volumes. In the above example, PERCENTUTILIZED is used to specify that only 80% of the first target volume is to be filled. This leaves 20% free space for the data sets to extend, if necessary.

PERCENTUTILIZED is ignored for SMS-managed volumes.

Note: User data-set labels on DASD volumes are supported during a data set restore operation. However, either the data set on both the source and target volumes must have these labels, or neither must have them.

#### Restoring to preallocated target data sets

In some instances, you might want to control the placement of a data set on a volume when you restore it. Some data sets (such as data sets allocated by absolute track) have location-dependent data and must be preallocated. Others (such as catalogs) should be placed for performance reasons.

For information about restoring such data sets, refer to "Restoring indexed sequential, unmovable, direct, and absolute track data sets" on page 81 and "Restoring integrated catalog facility catalogs" on page 79.

To use a preallocated data set, you must specify the REPLACE or REPLACEUNCONDITIONAL keyword. If the REPLACE keyword is specified, the preallocated target data set name must be identical to the source data set name. If the REPLACEUNCONDITIONAL keyword is specified and the RENAME or

RENAMEUNCONDITIONAL keyword is also specified, the preallocated target data set name must match the new name filter criteria.

If a target data set is preallocated, it is scratched and reallocated if it is not large enough to contain the dumped data set. VSAM preallocated target data sets are also scratched and reallocated when:

- Any of the following source and target data set attributes do not match:
  - CI size
  - Record length
  - Key length (only KSDS and key range data sets)
  - SPANNED
- The preallocated target is multivolume and the space of the target data set on the first volume is not large enough to contain all of the dumped data.
- The data set was not defined as reusable and the high-used relative byte address (RBA) of a target VSAM KSDS is not 0.
- The target data set has the IMBED or REPLICATE attributes. It will be reallocated without those attributes.

You may use data set RESTORE to upgrade your standard format sequential data sets to large format data sets. To do this, simply preallocate a large format data set. In restoring a standard format sequential data set, if a preallocated large format data set is found, the preallocated large format data set will be the target of the restore. If the preallocated large format data set is not large enough to hold the data being restored, it is scratched and reallocated as a large sequential data set. In restoring a large format data set, if a preallocated standard format sequential data set is found, the standard format sequential data set is used and is upgraded to a large format data set. If the preallocated standard format sequential data set is not large enough to hold the data being restored, it is scratched and reallocated as a large format data set.

If a user wishes to downgrade a large format data set to a standard format sequential data set, restore the large format data set with no preallocated target, allocate a standard format sequential data set, and use a utility such as IEBCOPY to copy the data from the large format data set to the standard format sequential data set.

If a user wishes to upgrade or downgrade an extended format sequential data set you must preallocate the target data set to the extended format version number.

You may also use data set RESTORE to upgrade your data sets that are not enabled for CA reclaim to data sets that are enabled for CA reclaim. To do this, simply preallocate a data set that is enabled for CA reclaim to use as the target of the restore. In restoring a data set that is not enabled for CA reclaim, if a preallocated data set that is enabled for CA reclaim is found, the preallocated data set that is enabled for CA reclaim is not large enough to hold the data being restored, it is scratched and reallocated as a data set that is enabled for CA reclaim. In restoring a data set that is enabled for CA reclaim, if a preallocated data set that is not enabled for CA reclaim is found, the data set that is not enabled for CA reclaim is used for the target of the restore. If the preallocated data set that is not enabled for CA reclaim is not large enough to hold the data being restored, it is scratched and reallocated as a data set that is not enabled for CA reclaim. For more information, refer to the topic on CA reclaim in z/OS DFSMS Using Data Sets.

During logical restore processing, a compression is performed when partitioned data sets are restored to both like and unlike devices. If the partitioned data set is being restored to an unlike device, the device-dependent information (such as TTR pointers and note lists) is in a usable form after the restore. DFSMSdss is unable to resolve device-dependent information for all other data set types being restored to unlike devices.

The NOPACKING keyword is effective only for partitioned data sets. If NOPACKING is specified for preallocated partitioned data sets, the preallocated target must reside on the same or a like device. Processing is stopped for the data set if the target resides on an unlike device. The target is not deleted and reallocated.

The preallocated data set is usable if all of the following conditions that apply to the data set being processed are met:

- The user is authorized to update the target data set.
- If VSAM, the cluster types match
- The DSORG matches.
- If the data set being processed is multivolume or single volume and the non-SMS preallocated data set matches the multivolume or single volume.

## Cataloging data sets during logical restore processing

When you restore a data set, you might need to catalog it in the standard order of search or recatalog it in its original catalog. The CATALOG keyword catalogs the data set in the standard order of search. The RECATALOG(\*) keyword catalogs it in the same catalog that points to the source data set.

When a data set is restored as an SMS-managed data set, it is cataloged using the standard order of search. The RECATALOG keyword is ignored.

Examples of the CATALOG and RECATALOG keywords in a logical data set RESTORE command follow:

```
RESTORE -
       INDDNAME (TAPE)
       DATASET(INCLUDE(USER1.**)) -
       CATALOG
```

```
RESTORE -
       INDDNAME (TAPE) -
       DATASET(INCLUDE(USER1.**)) -
       RECATALOG(*)
```

When a VSAM KSDS or key range data set is being restored to an unlike device, the data set must be cataloged in the standard order of search.

## Renaming data sets during logical restore processing

In addition to cataloging data sets when they are restored, you can rename restored data sets by using the RENAME keyword. For instance, you can code the following to rename a data set you are restoring:

```
RESTORE -
INDDNAME(TAPE) -
DATASET(INCLUDE(USER2.OLDDS)) -
RENAME(*.OLDDS,*.NEWDS)
```

**Note:** The RENAME keyword works only if the data set exists on the output DASD with the old name. If you really want to unconditionally rename a data set, use RENAMEUNCONDITIONAL. Both VSAM and non-VSAM data sets can be renamed. The rules for renaming VSAM clusters are the same as for non-VSAM data sets. You can rename only clusters. DFSMSdss assigns a new name for the components of VSAM clusters. SMS considerations require DFSMSdss to ensure that VSAM component names resolve to the same catalog as the cluster name. DFSMSdss uses the cluster name as a guide to determine the component names. This applies equally to SMS and non-SMS data sets.

## Restoring data sets with the IMBED or REPLICATE attributes

During logical restore processing, DFSMSdss converts data sets with IMBED or REPLICATE attributes to indexed key-sequenced data sets (KSDS) without the IMBED and REPLICATE attributes. If the target data set already exists and has these attributes, it is deleted and reallocated without the IMBED and REPLICATE attributes.

### Restoring data sets with the KEYRANGES attribute

During logical restore processing, DFSMSdss restores data sets with the KEYRANGES attribute as they were dumped. DFSMSdss does not convert these data sets, but issues message ADR508I to bring attention to their existence.

# DFSMSdss handling of the expiration date during logical restore

For preallocated targets, the expiration date of the preallocated target is preserved. For non-preallocated targets, the expiration date depends on whether the data set is VSAM or non-VSAM, whether the source data set is SMS-managed, and whether the target data set is SMS-managed. SMS also ensures that the expiration date conforms with the target's management class retention period.

#### Allocating to SMS

For VSAM data sets, DFSMSdss uses the expiration date from the source catalog entry to set the target's expiration date in both the catalog and the VTOC. For an indexed VSAM data set, the expiration date in the VTOC for the index component is zero.

For non-VSAM data sets, DFSMSdss uses the expiration date from the source VTOC to set the target expiration date in both the catalog and VTOC. If the expiration date violates the target's management class retention period, SMS modifies the date to conform with the management class.

#### Allocating to non-SMS

For VSAM data sets, DFSMSdss uses the expiration date from the source catalog entry to set the target's expiration date in the catalog. The target expiration date in the VTOC is 99365. For an indexed VSAM data set, the expiration date in the VTOC for the index component is 99365.

For non-VSAM data sets, DFSMSdss uses the expiration date from the source VTOC to set the expiration date in the target VTOC. If the target is cataloged, the expiration date in the catalog is set to the date from the source VTOC if the source

data set is SMS-managed. If the target is cataloged, and the source data set is not SMS-managed, the expiration date in the catalog is not set.

# DFSMSdss handling of the data-set-changed indicator during restore

When restoring a data set, understand that the value of the data-set-changed indicator depends on several factors, such as whether you invoke DFSMSdss directly or through its Application Programming Interface (API), and whether you rename the data set during the restore operation.

Table 9 shows how DFSMSdss handles the data-set-changed indicator in each of these situations.

Table 9. DFSMSdss handling of the data-set-changed indicator during data set restore operations.

How is DFSMSdss invoked?	Is the data set renamed?	Result
Invoked directly to restore the data set.	No	DFSMSdss sets the data-set-changed indicator in the VTOC to the value the data set had when it was backed up.
Invoked directly to restore the data set.	Yes	DFSMSdss turns off the data-set-changed indicator for the data set because it is newly allocated.
Invoked by an application through the DFSMSdss API.	No	DFSMSdss leaves the data-set-changed indicator unmodified, so that other backup applications can continue to track the data set.
Invoked by an application through the DFSMSdss API.	Yes	DFSMSdss leaves the data-set-changed indicator unmodified, so that other backup applications can continue to track the data set.

# Physical data set restore

A physical data set restore is done if you are restoring from a dump volume created by physical dump processing and you specify the DATASET keyword. If the dump volumes resulted from a physical data set dump operation, you must do a physical data set restore or a tracks restore operation. A tracks restore operation can consist of a subset of the dump data.

#### Note:

- 1. When you perform a physical restore of many data sets, there is an initial delay while DFSMSdss allocates the target data sets.
- 2. To prevent index components from being restored inadvertently, you must specify the fully qualified name of the cluster.

On a physical data set restore operation, data sets from one or more logical volumes can be restored to a single DASD volume. If you want to restore data sets from specific source DASD volumes, use the LOGICALVOLUME keyword to specify the volume serial numbers of the source DASD volumes you want to restore. For example:

```
RESTORE -
INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**)) LOGICALVOLUME(111111) -
REPLACE
```

The following data sets cannot be processed by physical data set DUMP or RESTORE operations:

- VSAM data sets not cataloged in an integrated catalog facility catalog.
- Page, swap, and SYS1.STGINDEX data sets.

**Note:** Data from a specific volume can be restored only to a DASD volume of like device type.

## **Output volume selection**

For a physical data set RESTORE command, you must specify an output volume with the OUTDDNAME or OUTDYNAM keyword. A physical data set restore operation restores only to the first volume in a list passed in the OUTDDNAME or OUTDYNAM parameter.

## Cataloging data sets during physical restore processing

If you specify CATALOG on a physical data set restore operation, DFSMSdss creates catalog entries for single-volume, non-VSAM data sets that were allocated by DFSMSdss. The cataloging is done immediately after successful allocation of a data set. Failure in cataloging does not prevent the data set from being restored. A data set that was allocated and cataloged but encountered errors during the restore operation is neither uncataloged nor scratched by DFSMSdss. You must not specify the RECATALOG keyword for physical restore.

The catalog that DFSMSdss uses to catalog a data set is determined as follows:

- If the first qualifier of the data set name is an alias for a user catalog, the catalog pointed to is used for that data set.
- Otherwise, the master catalog is used.

DFSMSdss does not catalog VSAM data sets during physical restore processing. If the CATALOG keyword is specified, it is ignored when processing VSAM data sets. You should use the IDCAMS DEFINE RECATALOG command to catalog VSAM data sets that were allocated by DFSMSdss (not preallocated). To recatalog and later access the VSAM data set, the volume serial numbers for the target and source volumes must match and the data set must be cataloged in the same catalog from which it was dumped. The volume serial number and the catalog name are printed in message ADR4181 during restore.

**Note:** To catalog multivolume non-VSAM data sets, use the IDCAMS DEFINE NONVSAM command.

#### Coexistence considerations

For information about restoring dumps created with previous releases, refer to "Restoring backups using DFSMSdss" on page 649 in Appendix A, "Coexistence Considerations," on page 649.

# Restoring data sets with special requirements

Some data sets have special requirements for being restored. The sections that follow describe some of the special cases you might encounter when you restore data sets.

# Restoring multivolume data sets and restoring data sets using multiple target volumes (spill volumes)

Multivolume data sets from a logical data set dump tape can be restored either to a single volume or to multiple volumes. When multiple target volumes are specified, DFSMSdss selects target volumes as follows:

- If a target volume that has the same volume serial as the source volume is available and has adequate space, it is chosen.
- If a volume of the same device type is available, and if it has adequate space, it is selected.
- A volume of a *like* device type is selected if it has adequate space.
- A volume of an *unlike* device type is selected if it has adequate space.

If you are restoring a multivolume data set from a physical dump, be sure the segments from all volumes are restored with successive RESTORE commands. Restoring a portion of a multivolume non-VSAM data set to a preallocated data set is allowed only if the volume sequence numbers of the source and target data sets are the same.

A VSAM data set that has its index component defined on more than one volume (that is, a multivolume KSDS defined with the imbed attribute) should always be processed logically. If it must be processed physically, it should be treated as an absolute track allocation data set, and its extents restored to their original location. This can be accomplished by performing either a full-volume restore, or a tracks restore of the relevant tracks. If this procedure is not done, the index may become unusable.

During logical restores of VSAM data sets whose data and index components are on different source volumes, DFSMSdss preserves the volume spread if enough target volumes of like device types are specified.

Note: DFSMSdss preserves the volume spread by placing the data and index components on separate devices only if all of the following are true:

- The source data and index components reside on separate devices.
- The target data set is preallocated with the data and index components on separate devices.
- DFSMSdss does not need to scratch and reallocate the preallocated target data

For information about when DFSMSdss scratches and reallocates target data sets, refer to "Restoring to preallocated targets" on page 81.

Note: When you are copying or restoring multivolume data sets, be aware of the following considerations:

 DFSMSdss does not preserve candidate volumes. However, for SMS-managed data sets, if you copy and do not specify any output volumes, DFSMSdss

preserves the source volume count. If you copy and do specify the output volumes, DFSMSdss sets the volume count to the number of output volumes specified.

- DFSMSdss does not ensure that the copied or restored data set is on the same number of volumes as the original data set, nor does DFSMSdss ensure that the copied or restored data set extents are the same as the original data set. Instead, DFSMSdss tries to allocate the new data set on as few volumes as possible. This may result in the copied or restored data set becoming a single-volume data set.
- In addition, DFSMSdss tries to allocate each volume so that all data is contained in a single primary allocation of contiguous space with few, if any, of the secondary allocations being used.

# Restoring integrated catalog facility catalogs

Integrated catalog facility user catalogs can be restored only to the same volumes (the same volume serial and the same device type) from which they were dumped. The component names of the source and target user catalog must be the same. In addition, you must specify the fully qualified name to restore a catalog.

Restore from a logical dump is generally the best way to restore a catalog because it restores user catalog aliases if they are present in the logical dump data set. For logical restore operations, user catalog aliases are restored as follows:

- If DFSMSdss allocated the user catalog, aliases are restored if the catalog is successfully restored.
- If the target catalog was preallocated and is not empty, aliases are not restored.
- If the target catalog was preallocated and is empty, aliases are restored.

A physical restore operation does not restore aliases, and physically dumped catalogs cannot be restored if they are open. In addition, if the entries in the catalog during the dump operation do not match the entries during the physical restore operation, some of the data sets may become inaccessible.

An integrated catalog facility user catalog can be restored dynamically. Catalog recovery jobs must be modified to include any of the following options:

- Add the IDCAMS ALTER LOCK | SUSPEND command to lock or suspend the
  existing catalog before the DFSMSdss restore operation. After the recovery is
  complete, unlock or resume the catalog by using IDCAMS ALTER
  UNLOCK | RESUME. The LOCK or SUSPEND attribute on the dump tape is
  used if the catalog does not exist.
- Issue the F CATALOG, RECOVER, LOCK | SUSPEND(ucat) command before the DFSMSdss restore operation. After the recover is completed, unlock or resume the catalog by using IDCAMS ALTER UNLOCK | RESUME. The LOCK or SUSPEND attribute on the dump tape is used if the catalog does not exist.
- Specify the BCSRECOVER(LOCK | SUSPEND) keyword in the DFSMSdss RESTORE command. DFSMSdss will perform the necessary unlock and resume during internal processing. This option only applies to existing (pre-allocated) catalogs. If the catalog does not exist, DFSMSdss will define the catalog as locked to ensure the catalog is not accessible prior to DFSMSdss completing restore processing.

For more information, see the following:

 For more information about the BCSRECOVER parameter, see "BCSRECOVER" on page 460. • For more information about using the MODIFY CATALOG command, see *z/OS DFSMS Managing Catalogs*.

The following example shows the JCL used to restore an integrated catalog facility user catalog. If the master catalog is RACF-protected, RACF access to it is required, unless you have DASDVOL update access or the installation authorization exit routine bypasses authorization checking.

Figure 2 shows the printed output produced by the RESTORE command.

```
PAGE 0001
             5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                                 1999,211 14:54
  RESTORE
     DS(INCL(TEST.CAT.PUBSEXMP)) -
     OUTDYNAM (D9S060)
     REPLACE
      INDDNAME (TAPE)
ADR101I (R/I)-RI01 (01), TASKID 001 HAS BEEN ASSIGNED TO COMMAND 'RESTORE '
ADR1091 (R/I)-RI01 (01), 1999.211 14:54:46 INITIAL SCAN OF USER CONTROL STATEMENTS
                         COMPLETED.
ADR016I (001)-PRIME(01), RACF LOGGING OPTION IN EFFECT FOR THIS TASK
ADR006I (001)-STEND(01), 1999.211 14:54:46 EXECUTION BEGINS
ADR780I (001)-TDDS (01), THE INPUT DUMP DATA SET BEING PROCESSED IS IN LOGICAL
                         DATA SET FORMAT AND WAS CREATED BY DFSMSDSS VERSION 2
                         RELEASE 10 MODIFICATION LEVEL 0
ADR442I (001)-FRLBO(01), DATA SET TEST.CAT.PUBSEXMP PREALLOCATED, IN CATALOG
                         SYS1.MVSRES.MASTCAT, ON VOLUME(S): D9S060
ADR489I (001)-TDLOG(02), CLUSTER TEST.CAT.PUBSEXMP WAS RESTORED
                                         SYS1.MVSRES.MASTCAT
                          CATALOG
                          COMPONENT
                                         TEST, CAT, PUBSEXMP
                          COMPONENT
                                        TEST.CAT.PUBSEXMP.CATINDEX
ADR454I (001)-TDLOG(01), THE FOLLOWING DATA SETS WERE SUCCESSFULLY PROCESSED
                          TEST.CAT.PUBSEXMP
ADR006I (001)-STEND(02), 1999.211 14:54:47 EXECUTION ENDS
ADR013I (001)-CLTSK(01), 1999.211 14:54:47 TASK COMPLETED WITH RETURN CODE 0000
ADR012I (SCH)-DSSU (01), 1999.211 14:54:47 DFSMSDSS PROCESSING COMPLETE. HIGHEST
                         RETURN CODE IS 0000
```

Figure 2. Output from Restore of Integrated Catalog Facility User Catalog

For more information about the LOCK attribute and the access authority, refer to *z*/*OS DFSMS Managing Catalogs*.

For more information about the installation authorization exit routine, refer to *z/OS DFSMS Installation Exits*.

When you attempt to replace an existing integrated catalog facility (ICF) user catalog, it must not violate any of the following restrictions:

- The number of extents for the target must not exceed the number of extents of the data set being restored.
- If the ICF user catalog has been defined with the SHARE keyword, the target high index used CI must not exceed the high index used CI of the data set being restored.

- If the ICF user catalog has been defined with the SHARE keyword, the target high index allocated CI must not exceed the high index allocated CI of the data set being restored.
- The target ICF user catalog's high used relative byte address must not exceed the high used relative byte address of the data set being restored.
- The target ICF user catalog's high allocated relative byte address must not
  exceed the high allocated relative byte address of the data set being restored. A
  violation of these restrictions will result in a failure to restore the ICF user
  catalog.

# Restoring non-VSAM data sets that have aliases

DFSMSdss does not support INCLUDE filtering of non-VSAM data sets using an alias. To include a non-VSAM data set which has an alias for restore processing, you must use the data set's real name, as shown in the VTOC. DFSMSdss does not detect nor preserve aliases of non-VSAM data sets. You will need to redefine the aliases after the data set is restored.

# Restoring indexed sequential, unmovable, direct, and absolute track data sets

One important use of DFSMSdss is restoring data sets that contain device-dependent information. In some cases, such data sets can be restored without preallocating the target data sets. In other cases, however, you must preallocate the target to restore the data set.

DFSMSdss does not support restoring Indexed Sequential data sets.

## Restoring without preallocated targets

If an unmovable data set is not preallocated, DFSMSdss tries to allocate the data set on the same 'relative tracks from which it was dumped. If this allocation fails, the unmovable data sets are allocated to any available location if the FORCE keyword is specified.

When you specify the FORCE keyword and some of the data sets have truly location-dependent data, you should specify their names in the EXCLUDE parameter to prevent DFSMSdss from restoring them. Subsequently, you must either restore the data set onto a scratch volume or free up the area of the DASD where these data sets were located on the source volume and rerun the restore operation. When restoring a direct, undefined data set and the target data set is not preallocated, DFSMSdss allocates the data set. The allocation may result in a new data set with a different configuration from the data set that was dumped (for example, fewer volumes). This situation may cause problems when processing the restored data set.

# Restoring to preallocated targets

If you are restoring any of these types (unmovable, direct, or absolute track) of data sets by preallocating them, the size and location of the extents on the dump volume and on the restore volume should match. Restoring a data set to a larger preallocated data set can cause problems because of the extraneous data beyond the end of the original dumped data. If the preallocated data set is too small, DFSMSdss deletes it and reallocates a new data set. The allocation may fail, or it may result in a new data set with a different configuration (for example, fewer volumes). The latter situation can cause problems processing the data set.

For unmovable data sets (those allocated as ABSTR, PSU, POU, or DAU), a preallocated data set is restored if the extents match and the REPLACE or REPLACEUNCONDITIONAL keyword is specified. Even if the extents do not match, the data set is restored if you specify both the REPLACE and FORCE keywords or the REPLACEUNCONDITIONAL and FORCE keywords. When an unmovable data set cannot be restored, the extents of the data set on the source volume are listed so that you can take action to restore it.

Note: Indexed sequential data sets cannot be restored to unlike devices.

## Restoring direct access data sets

When DFSMSdss restores direct data sets, several processing options can be used. Direct data sets can be organized by relative block address or by track-track record

Relative block addressable direct access data sets can be processed block by block to like and unlike target devices if the block size fits on the target track. When the data sets are processed block by block, DFSMSdss updates the block reference count of dummy records contained in the relative block addressed direct access data sets. To process block by block, the direct access data sets must have neither a variable record format nor a standard user label.

TTR direct access data sets may become unusable if they are processed block by block. TTR and relative block addressable data sets can be processed track by track to like and unlike target devices whose track capacity is equal to or greater than the source. Block by block processing is more efficient because track by track processing to an unlike device of larger track capacity can leave some unused space on each track of the target data set.

Several DFSMSdss keywords implement the BDAM processing options:

#### **AUTORELBLOCKADDRESS**

If the data set is accessed with Optional Services Code (OPTCD) indicating relative block addressing, it is processed as if it were specified in the RELBLOCKADDRESS subkeyword list, and processing is block by block. If your installation has many relative block address direct access data sets, you can use the DFSMSdss installation options exit to turn on the AUTORELBLOCKADDRESS function.

#### RELBLOCKADDRESS

If the data set is specified in the subkeyword list, the data set is processed block by block.

#### **TTRADDRESS**

If the data set is specified in the subkeyword list, the data set is processed track by track.

#### **FORCE**

If the track capacity of the receiving volume is smaller than the source, FORCE may be required for variable or undefined length TTR-organized direct access data sets. These data sets may be unusable after restore and, if possible, should be restored to a like device. Use RELBLOCKADDRESS to restore relative block address direct access data sets to unlike devices.

**Note:** If you do not specify a keyword, data is moved to the target on a track by track basis.

For more information about using BDAM processing options with DFSMSdss keywords, refer to "RESTORE command for DFSMSdss" on page 452.

For more information about the installation options exit, refer to *z/OS DFSMS Installation Exits*.

For information about using DFSMS macros for non-VSAM data sets, refer to *z/OS DFSMS Macro Instructions for Data Sets*.

# Restoring an undefined DSORG data set

The PROCESS(UNDEFINEDSORG) keyword permits logical data set restore of an undefined DSORG data set to an unlike device of larger track capacity. The restore yields a usable data set; however, some unused space might remain on each track of the target data set. It may not always be possible to restore all undefined DSORG data sets to an unlike device type, even when the unlike device type has a track capacity greater than or equal to the source device. For example, if the source device is a 3380, the output device is a 3390, and the data set's block size is less than 277 bytes, a track on the target cannot contain as much data as a track on the source, and message ADR366W (invalid track format) is issued.

**Note:** A data set with an undefined DSORG or with a block size of 0 cannot be restored to a device of smaller track capacity than the source.

# Restoring an extended-format VSAM data set with stripe count of one

When performing a logical restore operation of an extended-format VSAM data set with a stripe count of one, the resulting target will remain a VSAM data set with a stripe count of one, even if the target storage class is multi-striped.

# Restoring a VSAM sphere

With DFSMSdss, you can restore an entire VSAM sphere (base cluster and all associated alternate index clusters and paths). The SPHERE keyword causes DFSMSdss to restore the entire VSAM sphere. If the dump was also taken with the SPHERE keyword specified, you need to specify the SPHERE keyword and the base cluster name to restore the base cluster and the other components.

When you restore a sphere to a preallocated target, all components (base clusters, alternate indexes, and paths) of the sphere must be preallocated. DFSMSdss does not restore a sphere if only some parts of the sphere are preallocated.

An example of the RESTORE command with the SPHERE keyword is:

```
RESTORE -
INDDNAME(TAPE) -
DATASET(INCLUDE(PARTS.VSAM1)) -
SPHERE -
REPLACE -
PSWD(PARTS.VSAM1/MASTUPW1)
```

# Restrictions for restore processing

 You can restore a sphere only if all parts of the sphere resolve to the same catalog.

- You may not need to rename all the parts in the VSAM sphere as you would with the copy function.
- Multiple path names to an alternate index are not supported. Only the last path name listed in the catalog is preserved.
- When restoring a sphere with one or more alternate indexes missing from the dump tape, DFSMSdss issues a message to indicate that the sphere was incompletely restored.

# Restoring a preallocated VSAM cluster

Restoring a VSAM cluster that has been preallocated is allowed if the following are the same on the source and the destination volumes:

- The number of components on the volume
- The beginning relative byte address (RBA)
- The component names
- Catalog names

The size of the cluster must be equal to or greater than that on the source volume. (Only the tracks that were dumped are restored.)

You should ensure that the control interval size, allocation unit, and secondary allocation quantity are the same as in the initial definition.

# Restoring the VVDS and the VTOCIX

To restore a VVDS or VTOCIX data set, you must specify the fully qualified data set name. The VVDS and the VTOCIX data set cannot be restored with other data sets in the same RESTORE command. VVDS and VTOCIX data sets should not be restored by data set as a normal recovery procedure. The VTOCIX data set is an extension of the VTOC and can be rebuilt using the Device Support Facilities program (ICKDSF) BUILDIX command.

The VVDS is an extension of the VTOC and of the catalogs for the VSAM data sets on the volume. If it is restored by a data set restore operation, it is possible that some of these data sets can become unusable because of a mismatch between the catalog, the VVDS, and the VTOC. If this occurs, run the diagnose function of access method services to determine the extent of the problem and to take appropriate corrective action.

DFSMSdss/VVDS Manager does not support dumping a multiple-extent VVDS and restoring the VVDS to a nonpreallocated VVDS. DFSMSdss can restore to a nonpreallocated VVDS only when the source VVDS resides on one extent.

The user can consolidate the VVDS extents by doing the following:

- DFSMSdss dump the multiple-extent VVDS
- IDCAMS delete the multiple-extent VVDS
- Preallocate a single-extent VVDS
- DFSMSdss restore the multiple-extent VVDS into the preallocated, single-extent target VVDS.

# Restoring a PDSE

DFSMSdss lets you restore a PDSE. The PDSE's original version level is preserved during restoration if restored on z/OS V2R1.0 or later. The version level that was

dumped stays the same when the PDSE is restored, if restored on the same release of z/OS that is was dumped from. PDSE member generations are also preserved if restored on z/OS V2R1.0 or later.

# Restoring a damaged PDS

During a logical restore, a PDS is monitored by DFSMSdss for conditions that are not normal. The following conditions are detected and reported:

- · Missing high-key entry in the PDS directory
- · Missing directory EOF
- Invalid member start TTR:
  - TTR points before directory EOF
  - TTR points after end of data set
- Missing member EOF. Each member of a partitioned data set is normally terminated by an EOF record.
- Invalid note or note list TTR:
  - Note pointing before the start of member data
  - Note pointing after the member EOF
  - Note pointing past the last valid record on a track
  - Note pointing to record 0 of a track

DFSMSdss notes all of these conditions with a message.

During compression, DFSMSdss repairs all missing high-key directory entries, missing directory EOFs, and missing member EOFs.

Invalid start TTRs prevent DFSMSdss from compressing data for that member. DFSMSdss translates all valid note and note list TTRs during compression.

Use the NOPACKING keyword to restore damaged partitioned data sets to same or like device target volumes. This results in an exact track-for-track image of the source data set. Obviously, no compression is performed in this case. During physical restore operations, DFSMSdss uses only track-level I/O. Therefore, no compression takes place against the PDS.

# Restoring data sets in an SMS-managed environment


Use the RESTORE command to recover data sets in an SMS-managed environment. If the data set was dumped logically, it is recovered logically. If it was dumped physically, it is recovered physically.

As discussed earlier, an SMS-managed environment can contain both SMS-managed and non-SMS-managed data. The following sections discuss how you can use the RESTORE command to recover these data sets.

Programming Interface Information
The following sections discuss variables available to automatic class selection (ACS) routines during DFSMSdss processing. This information is provided for guidance purposes only. It is not associated with any interface provided by DFSMSdss.
End Programming Interface Information

For information about writing ACS routines, refer to Chapter 17, "Syntax—DFSMSdss function commands," on page 269.

# Converting non-VSAM data sets to multivolume



The number of volumes allocated for certain VSAM and non-VSAM data sets can be changed with VOLCOUNT keyword options. The output data set must be SMS-managed. Single volume data sets can be converted to multivolume; multivolume data sets can be converted to single-volume; or the number of volumes allocated for multivolume data sets can be changed. Allocation depends on which VOLCOUNT keyword is selected, and on whether output volumes are specified.

Note: You cannot use the VOLCOUNT keyword to convert the following types of data sets to multivolume:

- TTR-BDAM or unmovable data sets. If DFSMSdss encounters an existing multivolume TTR-BDAM or unmovable data set, a DADSM error occurs.
- Partitioned data sets (PDS or PDSE). If an existing multivolume PDS or PDSE data set is encountered, it is converted to single-volume.
- You cannot restore a non-SMS-managed non-VSAM single volume data set that was dumped with DFSMSdss to multivolume.

End Programming Interface Information	
Life I logianining interface information ———————	_

# Restoring SMS-managed data sets

When you use the RESTORE command in an SMS-managed environment, automatic class selection (ACS) routines are invoked. ACS routines are written for each installation by the installation's own storage administrator.

When you use the RESTORE command, you are in the ACS RECOVER environment.

DFSMSdss passes a data set's classes at the time of the dump to ACS as input, and the ACS routines can assign or override these input classes.

VSAM alternate indexes do not have SMS constructs of their own; they use the same constructs as the base cluster. When restoring alternate indexes as independent clusters (because you did not specify the SPHERE keyword on the DUMP and RESTORE commands), DFSMSdss passes null classes to ACS. If you want DFSMSdss to pass the base cluster's classes to ACS, you must invoke sphere processing by specifying the SPHERE keyword on the DUMP and RESTORE commands.

If the source data set is not SMS-managed and has no class names, DFSMSdss passes null classes to ACS. If the source data set is SMS-managed and you do not specify otherwise, DFSMSdss passes ACS the source data set's classes. If you specify what you want passed to ACS with the STORCLAS, MGMTCLAS, NULLSTORCLAS, or NULLMGMTCLAS keywords, DFSMSdss passes ACS what you specify. In all cases, the ACS routines ultimately decide the classes assigned to the data set.

You can, however, force the storage class and management class you specify to be assigned to a data set by using the BYPASSACS keyword with the RESTORE command.

The following RESTORE command results in ACS routines determining the target classes, using the source classes as input:

```
RESTORE -
INDDNAME(TAPE) -
DATASET(INCLUDE(USER12.**))
```

If you preallocate a data set and specify the REPLACE or REPLACEUNCONDITIONAL keyword, the preallocated data set's classes are used.

For more information about the variables available to ACS routines during restore processing, refer to "ACS variables available during RESTORE and CONVERTV processing" on page 181.

For more information about using the RESTORE command to convert data to and from SMS management, refer to Chapter 8, "Converting data to and from SMS management," on page 141.

For more information about ACS routines, refer to Chapter 11, "ACS routine information," on page 179.

### Changing storage class with the RESTORE command

In some cases, you might want to pass ACS a storage class that is different from that of the source data set. You can specify the RESTORE command with the STORCLAS keyword to pass ACS a storage class name as follows:

```
RESTORE -
INDDNAME(TAPE) -
DATASET(INCLUDE(USER12.**)) -
STORCLAS(SCNAME1)
```

However, using STORCLAS does not guarantee that the data set is assigned the storage class you specify. It means only that the storage class you specified is passed to the ACS routines. Depending on how your installation's ACS routines are written, the storage class you specify can be ignored, assigned to the data set, or used in combination with other input variables to determine a new storage class for the data set.

RACF checks if the RESOWNER field of a given data set is authorized to define the data set with the given STORCLAS. Ensure that the RESOWNER field of the data set has the proper authority to use the indicated storage class.

To make certain that the storage class you specify is assigned to the data set, you can use the BYPASSACS keyword as follows:

```
RESTORE
       INDDNAME (TAPE)
       DATASET(INCLUDE(USER12.**)) -
       STORCLAS(SCNAME1)
       BYPASSACS(**)
```

In this case, ACS is not invoked, and therefore the data set is assigned whichever storage class that you have specified with STORCLAS. If you do not use STORCLAS, the data set is assigned the storage class of the source data set.

To limit the use of BYPASSACS, an installation can set up a RACF class profile.

You can use the NULLSTORCLAS keyword in conjunction with the BYPASSACS keyword to make a data set non-SMS-managed. For example, the following specification of the RESTORE command causes the specified data sets not to be SMS-managed:

```
RESTORE -
       INDDNAME (TAPE)
       DATASET(INCLUDE(USER12.**)) -
       NULLSTORCLAS
       BYPASSACS(**)
```

### Changing management class with restore processing

In addition to influencing a data set's storage class when you restore it, you can also give ACS input for assigning or overriding the data set's management class. By specifying MGMTCLAS, you can pass a management class name to ACS and, as with STORCLAS, ACS can ignore it, assign it to the data set, or use it in combination with other input variables to determine the data set's management class. By specifying NULLMGMTCLAS, you can pass a null management class to ACS, which may or may not assign a management class.

An example of the RESTORE command with the MGMTCLAS keyword is:

```
RESTORE -
       INDDNAME(TAPE) -
       DATASET(INCLUDE(USER12.**)) -
       MGMTCLAS (MCNAME1)
```

As with STORCLAS, RACF checks if the RESOWNER field of a given data set is authorized to define the data set with the given MGMTCLAS. Ensure that the RESOWNER field of the data set has the correct authority to use the indicated management class.

Just as you can with STORCLAS, you can use MGMTCLAS with BYPASSACS to ensure that the data set is assigned the management class you specify. For instance:

```
RESTORE -
       INDDNAME (TAPE)
       DATASET(INCLUDE(USER12.**)) -
       MGMTCLAS (MCNAME1) -
       BYPASSACS(**)
```

You should ensure that the management class you specify with MGMTCLAS is valid, or you will get an error. Remember that BYPASSACS skips both the STORCLAS and MGMTCLAS ACS routines.

To limit the use of BYPASSACS, an installation can set up a RACF class profile.

When you influence or assign the management class of a data set, you also need to be careful that the data set resides in a storage group capable of providing for the management class attributes associated with the management class you specify. For instance, if a data set has a management class that makes it eligible for migration, it needs to reside in a storage group on which DFSMShsm does migration. Otherwise, the data set will never migrate. For this reason, you might have to change the storage class along with the management class to ensure that the data set resides on volumes that can accommodate its management class.

However, if you are having to continually override your installation's ACS routines, you should refer to your storage administrator about changes to the ACS routines that would make it possible to let SMS do its job.

### Restoring SMS-managed data sets physically

In general, it is recommended that you use logical data set restore processing in an SMS-managed environment. If you use physical data set restore processing, you should be aware of the special rules for volume and SMS construct selection.

When restoring a non-SMS-managed user catalog on an SMS-managed volume or an SMS-managed user catalog on a non-SMS-managed volume, physical restore does *not* convert the catalog. Instead, DFSMSdss physical restore ensures that the user catalog looks exactly like the source catalog (SMS or non-SMS-managed) and then places the output volume in INITIAL status.

DFSMSdss physical data set restore processing is sensitive to the number of logical volumes in a dump data set. A DFSMSdss physical dump tape can contain multiple logical volumes. Because a physical dump operates at the track-image level, every volume from which data was dumped is on the tape in the form of a logical volume.

The following example shows how a dump tape can contain more than one logical volume:

```
DUMP -
DATASET(INCLUDE(**)) -
INDYNAM((338001),(338002)) -
OUTDD(TAPE) -
COMPRESS
```

If data sets are dumped from both volumes, two logical volumes are on the dump tape.

During physical data set restore processing, the SMS class selection is similar to logical data set restore processing. The source data set's SMS classes (if any) are used as input to the ACS routines. You can influence the classes selected for the target data set by using the STORCLAS, MGMTCLAS, NULLSTORCLAS, NULLMGMTCLAS, and BYPASSACS keywords.

The major difference in physical data set restore (as opposed to logical data set restore processing) is that all the data will be restored to the first volume you specify in the OUTDDNAME or OUTDYNAM keyword.

Note: If the specified target volume is SMS-managed, no non-SMS-managed data sets are restored; conversely, if the specified target volume is not SMS-managed, no SMS-managed data sets are restored.

### Restoring GDG data sets

For generation data group (GDG) data sets, filtering on generations is supported. Generation names in relative generation number, dsn(n), can be specified in the INCLUDE and EXCLUDE parameters. The GDG base must be defined (cataloged) before restoring GDG data sets. Otherwise, messages indicating that catalog errors have occurred may be issued during the restore.

### Restoring SMS-managed GDG data sets

SMS-managed GDG data sets can be in any one of the following states:

- ACTIVE
- DEFERRED
- ROLLED-OFF

When restoring a GDG data set to SMS-managed storage, DFSMSdss does one of the following:

- Preallocated restore retains the status of the preallocated generation data set (GDS).
- Restore function places the GDS in DEFERRED status, if the TGTGDS keyword is not specified. DFSMSdss leaves the GDS in DEFERRED status to enable you to (1) roll it back as an ACTIVE generation or (2) leave it as DEFERRED.
- If the TGTGDS keyword is specified, the appropriate status is assigned to the data set as long as the requested target status does not violate rules of the generation data group. The default status of logical and physical data set restore operation is DEFERRED.

# Restoring non-SMS-managed data sets

To restore a data set to a non-SMS-managed target volume, you can use the NULLSTORCLAS and BYPASSACS keywords on the RESTORE command. If you use these keywords, the data set is placed on a non-SMS-managed volume, regardless of whether the source data set was SMS-managed.

Extended-format data sets cannot be restored to non-SMS-managed target volumes during a physical or logical data set restore.

Data sets with DFM attributes (created by Distributed FileManager) can be restored to non-SMS-managed target volumes but the DFM attributes will be lost and a warning message will be issued.

For information about DFM, see *z/OS DFSMS DFM Guide and Reference*.

# Logical restore of data sets with phantom catalog entries

During a disaster recovery, the logical restore of data sets may be unsuccessful because of phantom catalog entries; that is, the target data set names are cataloged but the target data sets do not exist. This condition can occur if you have:

- Scratched the target volumes and have not deleted the catalog entries for the corresponding data sets
- · Restored the catalogs before restoring the data sets
- Restored the target data sets to different volumes from the offline source volumes, and the target data sets have not been renamed

DFSMSdss provides two parameters to support disaster recovery operations: DELETECATALOGENTRY and IMPORT.

### Using the DELETECATALOGENTRY keyword

You can use the DELETECATALOGENTRY keyword to cause DFSMSdss to perform a DELETE NOSCRATCH operation for any phantom catalog entry for a target data set being restored.

**Attention:** DELETECATALOGENTRY should be used with extreme care. **Do not** use it if:

- Any volumes on the restoring system are varied offline. If you do, DFSMSdss
  does a DELETE NOSCRATCH for any data set being restored that exists on the
  varied offline volume. Then, when the volume is varied online, you will have
  two data sets: a cataloged, restored data set and an uncataloged original data set
  on the volume that was varied offline.
  - Also note that if the volumes are varied offline, catalog messages will be issued for each cataloged data set informing you that the volume is offline and requesting that you reply with 'CANCEL' or a device name.
- The restoring system is sharing catalogs with another system but not sharing the data set volumes. If you do, DFSMSdss does a DELETE NOSCRATCH for any data set that is cataloged in the shared catalog on the other system but that is on a volume not available to the restoring system. After the restore, you may have two data sets: a cataloged, restored data set and an uncataloged original data set on a volume in the other system.

#### IMPORT keyword

IMPORT specifies that you are restoring data sets that were dumped from a system other than the one into which the restore is being done. Because the data sets to be restored are new to the system, the usual source data set authorization checks are not done. If you are authorized to read the input dump data set containing the data sets being restored, you have the authority to read any data set being restored. DFSMSdss continues to ensure that you are authorized to create a new target data set or replace an existing one.

# Logical restore of preformatted empty VSAM data sets

During a Logical Restore of preformatted empty VSAM data sets, DFSMSdss opens the target data set to preformat it. Open processing requires the data set to be cataloged in the standard catalog search order. Thus, to restore a preformatted empty VSAM data set, the target data set must be cataloged in the standard catalog search order.

## Restoring volumes

You can recover a volume or ranges of tracks from a full-volume dump operation. If the dump volumes resulted from a full dump operation, you can do a full or a tracks restore (that is, ranges of tracks) or a data set restore operation. If the dump volumes resulted from a tracks dump operation (that is, ranges of tracks), you must do a tracks RESTORE command, which can consist of a subset of the dump data

An example of a full-volume restore operation is:

```
INDDNAME(TAPE) -
OUTDDNAME(DASD1) -
PURGE
```

With the restore operation, you can copy the volume serial number to the output DASD with the COPYVOLID keyword. For example:

```
RESTORE -
       INDDNAME(TAPE) -
       OUTDDNAME (DASD1) -
       COPYVOLID -
```

#### Note:

- 1. COPYVOLID is required if you are restoring an SMS-managed volume, unless the source and target volume serial numbers match.
- 2. Data set restore of VSAM extended-addressable data sets from a physical volume dump is not supported.

For information about using DFSMSdss to restore Linux for System z partitions and volumes, see Chapter 12, "Dumping and restoring Linux for System z partitions and volumes," on page 185.

You must consider several factors when restoring volumes in an SMS environment. Before you start to restore a full volume, you must ensure that the status of the target volume is synchronized with its environment. For example, if the target volume is a non-SMS-managed volume, the volume must not be defined in a storage group. Conversely, if the target volume is an SMS-managed volume, the volume must be defined in a storage group. Finally, if the target volume is SMS-managed, then SMS must be active for the full-volume restore operation.

If you are using Record Level Sharing (RLS), be careful when restoring volumes with the FULL or TRACKS keywords. If the target volume has data sets associated with retained locks or data in the coupling facility, a full-volume or tracks restore can result in data integrity problems.

When restoring data in a full volume or tracks operation, DFSMSdss resets the data-set-changed indicator in the VTOC for each restored data set. This action indicates that the data set has not changed since the previous backup.

## Specifying output volumes

For a full or tracks restore, you must specify an output volume by using the OUTDDNAME or OUTDYNAM keywords.

The device type of the source volume used in the dump operation and the device type of the target volume used in the restore operation must be the same. However, the following exceptions are possible:

- Data from a smaller-capacity IBM 3380 model can be restored to a larger-capacity IBM 3380 model.
- Data from a smaller-capacity IBM 3390 model can be restored to a larger-capacity IBM 3390 model.
- Data from a minivolume or a virtual volume can be restored to a real volume of like device type, and vice versa, device capacity permitting.
- Data can be restored from a from a larger-capacity IBM 3380, 3390, or 9345
  model to a smaller-capacity IBM 3380, 3390, or 9345 model, if you are restoring
  specific track ranges using the TRACKS keyword and if the range of data to be
  processed falls within the capacity of the output device.
- Data from a smaller-capacity IBM 9345 can be restored to a larger-capacity IBM 9345.

**Note:** If you perform a full-volume restore to DASD that is shared between multiple systems, you must ensure that the DASD is offline to all systems except the system that is performing the restore.

When performing a full-volume restore operation to DASD, DFSMSdss automatically corrects the free-space information on the volume and might invoke ICKDSF to rebuild the VTOC index. DFSMSdss takes this action when it copies data to a larger-capacity DASD from a tape dumped from a smaller-capacity DASD or when both of the volumes, including volumes of equal capacity, contain a VTOC index. DFSMSdss allocates a large (more than 65 535 tracks) dummy data set to recalculate the free-space information. You can ignore any IEC614I messages that DFSMSdss generates during this process.

During a full-volume restore operation, other jobs may be enqueued on the output volume. If so, DFSMSdss cannot enqueue on the output volume to perform the full-volume restore operation. To determine if the output volume is allocated before performing the full-volume restore operation, issue the following operator command:

D U,DASD,ALLOC,cuu,1

This command displays the specified volume and the names of the jobs enqueued on it.

If, for example, the catalog has enqueued on the output volume, you can take the following steps:

1. Use the following catalog modify command to display a list of all open catalogs:

MODIFY CATALOG, LIST

2. Use the following catalog modify command to make CAS unallocate the

F CATALOG, UNALLOCATE (catname)

If no other allocated catalogs are on the volume and the volume is not allocated by any other users, you can proceed with your full-volume restore.

For more information about CAS allocation, see *z/OS DFSMS Managing Catalogs*.

### Processing RACF-protected data sets

On a physical restore operation, DFSMSdss does not delete the profiles of RACF-protected data sets on the volume before a full restore operation. After a full restore, RACF profiles are not built for RACF-indicated data sets on the restored volume. If RACF data set profiles do not exist for these data sets, these data sets are inaccessible until RACF profiles are built for them.

If you use the COPYVOLID keyword to change the volume serial number or if the volume serial for the dump volume and the restored volume are different, DFSMSdss does not build profiles for the RACF-protected data sets on the restored volume or for the RACF DASDVOL for the RACF-protected DASD volume.

The protection status of data sets that are restored through a full restore is unpredictable if:

- RACF profiles (generic or discrete) of the data sets were changed between dump and restore functions.
- The dump was produced on a system (that supports RACF generic profiles) other than the one used for the restore.

### Recovering system volumes

You can use the DFSMSdss stand-alone restore program to perform either a full or a tracks restore from the first data set of DFSMSdss-produced dump tapes, without the use of a host system environment. The stand-alone restore program allows you to recover system volumes so that you can start the host environment.

You can also use the DFSMSdss stand-alone restore program in a VM environment. The stand-alone restore program operates in ESA/390 mode, ESA/370 mode, or System/370 XA mode.

You cannot use the stand-alone restore program with an encrypted tape. If you attempt to do so, DFSMSdss issues message ADRY0513I to indicate that the dump data set resides on an encrypted tape and thus, cannot be read with the stand-alone restore program. DFSMSdss also issues message ADRY509D to prompt the operator to continue or end the function.

For more information about how to perform a restore using DFSMSdss stand-alone services, see Chapter 19, "DFSMSdss stand-alone services," on page 511.

# Recovering VM-format volumes

You can use DFSMSdss to recover VM-format volumes that are accessible to your z/OS system. The volumes must have OS-compatible VTOCs starting on track zero, record five. DFSMSdss can only retrieve device information from the OS-compatible VTOC, and cannot interpret any VM-specific information on the volume.

Use the CPVOLUME keyword and specify the range of tracks to be restored with the TRACKS keyword. Because DFSMSdss cannot check access authorization for VM data, CPVOLUME is only allowed with the ADMINISTRATOR keyword.

Exercise caution when using DFSMSdss to recover VM-format volumes, because DFSMSdss does not serialize any VM data in any way. If you restore OS-format volumes to VM-format volumes or VM-format volumes to OS-format volumes, you must restore all of the volume's tracks. Failure to restore all of the tracks may render the volume unusable.

### **Coexistence considerations**

For information about restoring dumps created with previous releases, refer to "Restoring backups using DFSMSdss" on page 649 in Appendix A, "Coexistence Considerations," on page 649.

# Chapter 7. Managing data movement with DFSMSdss

Data movement is necessary when you are doing the following tasks:

### Replacing devices

When you remove devices to be replaced with other ones, you must move the data off the devices you are removing.

#### Adding devices

If you add new devices at your site, you must move data onto them to take advantage of the added capacity.

### Maintaining devices

When you are servicing a volume, you might need to move data off the volume so users can continue to access the data.

#### Tuning performance

If a volume is performing poorly, it might be because data sets on the volume are being frequently accessed and causing an I/O bottleneck. In this case, you might move the data sets to another volume that is better able to handle it (either because it is less full or because it is cached).

You can use the DFSMSdss COPY command to move data between volumes.

## Preparing for data movement

Before moving your data, determine the amount of space the data requires. You can determine this by building a data set or volume list with ISMF. A data set list indicates how much space is allocated for each data set and how much space it actually uses. A volume list indicates how much free space is on each volume in the list. You can use this information to calculate how much space the data to be moved requires and to ensure that enough free space exists on the target volumes. This calculation is especially important when combining multiple devices onto one larger-capacity device.

**Note:** In an SMS-managed environment, this calculation is unnecessary if enough DASD space is provided because the system finds the necessary free space and places the data for you.

Ensure that enough free space exists to contain the data, and back up the data before moving it to guard against its loss during the movement. You can use the DFSMSdss DUMP command to back up volumes or data sets.

For more information about using the DUMP command to back up data, see Chapter 6, "Managing availability with DFSMSdss," on page 33.

# Evaluating the use of logical and physical copy

As previously stated, you can use the COPY command to perform the actual data movement. However, you must determine whether to use logical or physical copy function to move the data. The physical copy function gives you better performance, but the logical copy function allows you to move data to unlike devices.

Initiate a copy operation, logical or physical, at a time of low activity. Logical processing involves copying data sets. Physical processing involves volumes, tracks and the parts of data sets that reside on a particular volume. Logical processing generally takes more time than physical processing.

Note: It is best not to specify the TOLERATE(ENQFAILURE) option when you move data with the COPY command. If you move data while updating it, you may lose the updates. Also, the TOLERATE(ENQFAILURE) option is not honored for a source HFS data set or a source zFS data set.

After DFSMSdss has finished processing, you can verify that the data has moved by looking at the ISMF data set or volume list.

## Controlling what DFSMSdss copies

DFSMSdss copies only used space for sequential or partitioned data sets and data sets with null DSORG fields (X'0000'), unless overridden by ALLDATA or ALLEXCP. Use the ALLDATA(\*) and ALLEXCP keywords to process allocated space when the following conditions exist:

- You are not sure of the data set organization (DSORG) of a data set on a volume when doing a full-volume copy operation.
- There are sequential, partitioned, or individual data sets with a null DSORG field (X'0000') that is not accessed using SAM or PAM.

Note: The COPY command requires temporary work space. Ensure that public or storage volumes are available. Some temporary data sets are allocated to nonspecific devices by referring to SYSDA or SYSALLDA generic groups. If DFSMSdss is to function, these allocations must be allowed by the installation. Allocation validation exits must not restrict DFSMSdss allocations.

For temporary data sets allocated to nonspecific devices, DFSMSdss provides no unit type. SYSDA, SYSALLDA, or whatever is specified in the default allocation table is used. In an SMS-managed environment the default unit specified in the SMS base configuration table is taken even for non-SMS-managed temporary data

See Chapter 11, "ACS routine information," on page 179 for information on automatic class selection (ACS) routines during DFSMSdss copy operations.

# Moving data sets

Using the COPY command with the DATASET keyword, you can copy one or more data sets from one DASD volume to another of like or unlike device types. If you specify the DELETE keyword with the COPY command, the data set on the source volume is deleted after it has been successfully copied to the target volume. In this way, you can perform a data set move.

Attention: You should restore a dumped data set that has extended attributes in an F9 DSCB to a volume that supports F8/F9 DSCBs. Otherwise, these extended attributes are lost. DFSMSdss propagates the vendor attributes if they exist in the F9 DSCB of the primary volume when DFSMSdss performs catalog processing or if they exist in the first volume that DFSMSdss processes when you specify input volumes. To prevent losing extended attributes, all volumes that contain data sets with vendor attributes in the F9 DSCB must be extended address volumes.

**Note:** Concurrent copy operation fails and a message is issued if the DELETE keyword is specified.

### **Moving volumes**

You can move volumes logically or physically with DFSMSdss.

As with moving data sets, if the output volume has unexpired data sets, you can stop the copy operation or write over the unexpired data sets.

# Logical data set copy

If you specify the DATASET keyword with the COPY command and do not specify input volumes, DFSMSdss performs a logical data set copy using information in the catalogs to select data sets. For example, the following COPY command results in a logical data set copy.

```
COPY -
DATASET( INCLUDE( USER.**)) -
RENAMEUNCONDITIONAL( USER2 )
```

When you specify input volumes using the LOGINDDNAME or LOGINDYNAM volume list, a data set is selected based on the following criteria:

 When you either specify SELECTMULTI(ALL) or specify input volumes without specifying the SELECTMULTI keyword, all of the volumes that contain a part of a non-VSAM or VSAM cluster must be in the volume list.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you must list all parts of the base cluster in the volume list.
- Do not specify SPHERE and you must list all parts of the base cluster and the associated alternate indexes in the volume list.
- When you specify SELECTMULTI(ANY), any part of the non-VSAM data set or VSAM base cluster can be on a volume in the volume list.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you must list any part of the base cluster in the volume list.
- Do not specify SPHERE and you must list any part of the base cluster and the associated alternate indexes in the volume list.
- When you specify SELECTMULTI(FIRST), the volume list must include the volume that contains the first part of either the non-VSAM data set or the primary data component of the base cluster for a VSAM sphere.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you must list the volume that contains the first extent of the data component for the base cluster in the volume list.
- Do not specify SPHERE and you must specify the following information in the volume list:
  - The volume that contains the first extent of the data component for the base cluster.
  - The volume that contains the first extent of the data component for the associated alternate indexes.

Note: When processing input volumes, DFSMSdss filters first based on the VTOC, and second, based on catalog filters, if specified.

If a data set is found on more than one specified input volume and the volume sequence numbers match, DFSMSdss cannot determine which data set is to be selected for processing. You do not need to specify a SELECTMULTI option when you build a list of input volumes with STORGRP. The volume list will contain all of the volumes in a storage group.

## Physical data set copy

If you specify DATASET and the PHYSINDDNAME or PHYSINDYNAM keywords, DFSMSdss performs a physical data set copy. This method of moving data sets on a per volume basis only allows data movement between like devices. Single volume data sets will be copied from the source volume to the target volume. Single volume non-VSAM SMS managed data sets will be cataloged when they are either renamed or the DELETE keyword was specified. Multivolume data sets must be copied a volume at a time, and then recataloged by the user.

A conditioned volume created through the DFSMSdss COPY FULL DUMPCONDITIONING command can be specified as a source volume. A non-conditioned volume can also be specified as the source volume. However, the target volume cannot be a conditioned volume.

The following is an example of the syntax to specify a COPY command that results in a physical data set copy operation. You can specify only one volume on the PHYSINDD or PHYSINDYNAM keyword.

```
COPY DATASET(INCLUDE(**)) -
                PHYSINDDNAME(DASD1) OUTDYNAM(VOLS02) -
```

# Specifying input volumes

The COPY DATASET command does not require that you specify input volumes. If you do not specify input volumes, data sets are selected from all the data sets cataloged in the standard order of search.

When you specify input volumes using the LOGINDDNAME or LOGINDYNAM volume list, a data set is selected based on the following criteria:

• When you either specify SELECTMULTI(ALL) or specify input volumes without specifying the SELECTMULTI keyword, all of the volumes that contain a part of a non-VSAM or VSAM cluster must be in the volume list.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you must list all parts of the base cluster in the volume
- Do not specify SPHERE and you must list all parts of the base cluster and the associated alternate indexes in the volume list.
- When you specify SELECTMULTI(ANY), any part of the non-VSAM data set or VSAM base cluster can be on a volume in the volume list.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you must list any part of the base cluster in the volume
- Do not specify SPHERE and you must list any part of the base cluster and the associated alternate indexes in the volume list.
- When you specify SELECTMULTI(FIRST), the volume list must include the volume that contains the first part of either the non-VSAM data set or the primary data component of the base cluster for a VSAM sphere.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you must list the volume that contains the first extent of the data component for the base cluster in the volume list.
- Do not specify SPHERE and you must specify the following information in the volume list:
  - The volume that contains the first extent of the data component for the base cluster.
  - The volume that contains the first extent of the data component for the associated alternate indexes.

Note: DFSMSdss, when processing input volumes, filters first based on the VTOC, and second, based on catalog filters, if specified.

If a data set is found on more than one specified input volume and the volume sequence numbers match, DFSMSdss cannot determine which data set is to be selected for processing. You do not need to specify a SELECTMULTI option when you build a list of input volumes with STORGRP. The volume list will contain all of the volumes in a storage group.

## **Selecting output volumes**

Specifying output volumes is required for the COPY DATASET command in a non-SMS-managed environment. (For a discussion of SMS considerations for moving data, see "Moving SMS-managed data sets" on page 123.)

You can specify multiple target volumes with the OUTDDNAME or OUTDYNAM keywords. This allows you to specify spill volumes. These spill volumes are used if the data sets you are moving require more space than is available on your first choice of volume.

If the output volume has unexpired data sets, you can either not process the data sets or write over them.

DFSMSdss now distinguishes between non-SMS and SMS volumes specified in the OUTDDNAME or OUTDYNAM keywords. For non-SMS allocations, only the volumes that are non-SMS are considered for allocation. Similarly, only SMS volumes are considered for SMS allocations.

The distinction between SMS and non-SMS is also used when determining the volume count for a multivolume allocation. Where volume count is determined from the number of specified volumes, only those volumes eligible for the type of allocation (SMS volume for SMS allocation or non-SMS volume for non-SMS allocation), processing proceeds with a null volume list.

There are several reasons for distinguishing between SMS and non-SMS volumes:

- Non-SMS volumes cannot be used for SMS allocations
- Specifying non-SMS volumes interferes with SMS guaranteed-space allocation

- Reducing volume count problems
- Improving the ability of DFSMSdss to process both non-SMS and SMS allocations in a single operation

For non-SMS output volume selection, DFSMSdss selects volumes based on size of the allocation necessary. The first volume that has enough space will be used for the allocation. When moving data sets with the extended attributes variable DS1EATTR set in the VTOC, the system selects non-SMS output volumes as follows:

- 1. EATTR=NO: All volumes will be considered for allocation.
- 2. EATTR = OPT: For both VSAM and non-VSAM data sets, DFSMSdss prefers EAVs when the data set organization and type is supported in the EAS and the data set's size is greater than the BPV. EATTR = OPT is the default. If EATTR is not specified, it is the same as EATTR = OPT.

Preferring EAVs means that all volumes that are EAVs will be evaluated before any non-EAVs are even considered. If the EAVs in the list of output volumes cannot satisfy the allocation request, all of the output volumes will then be evaluated to accommodate the allocation request.

**Note:** The BPV is derived, in the following order, from the Storage Group attribute, the IGDSMSxx parmlib member, and the system default of 10 cylinders. The BPV can be changed dynamically in the storage group definition or changed with the SETSMS BPV operator command to override the IGDSMSxx parmlib member. However, for non-SMS volume selection, there will be no Storage Group attribute to evaluate.

# Renaming data sets

You can rename data sets with the RENAMEUNCONDITIONAL (RENAMEU) keyword for the COPY command. For VSAM data sets, you can only rename clusters. DFSMSdss derives the new names for the components of VSAM clusters

 If the data set is a linear data set and the new cluster name matches the following convention:

```
HLQ1.DSNDBC.HLQ3.HLQ4.%nnnn.%nnn
```

and the old component matches the following convention:

```
HLQ1.DSNDBD.HLQ3.HLQ4.%nnnn.%nnn
```

where % is any single letter, nnnn is a 4-digit number, and nnn is a 3-digit number, then DFSMSdss generates the target component as follows:

- If a qualifier from the source cluster name is identical to the corresponding qualifier of the source component name, the corresponding qualifier from the target cluster name is used in the target component name. Otherwise, DFSMSdss uses the qualifier from the source component name in the target component name.
- DFSMSdss sets the sixth qualifier of the new component name to AD for a data component, or to AI for an index component whenever any of the following conditions are true:
  - The new target component name exceeds 44 characters.
  - The new cluster name and new component name are identical.
  - The old component name and new component name are identical.

- If the standard order of search directs the new target component name to a different catalog with the new cluster name, the following occurs:
  - DFSMSdss regenerates the target component name using the first five qualifiers of the new cluster name.
  - DFSMSdss appends a sixth qualifier of either AD for the data component or AI for the index component.
- If the following conditions are true:
  - The data set is a linear data set
  - DFSMSdss was invoked using the application interface
  - The UIM set the EI22DB2 bit ON
  - The new cluster matches the following convention: HLQ1.DSNDBC.HLQ3.HLQ4.%nnnn.%nnn

where % is any single character, nnnn is a 4-digit number, and nnn is a 3-digit number.

then DFSMSdss generates the target component name by using all of the qualifiers of the new cluster name as the corresponding qualifiers of the target component name, with the exception of the second qualifier. The second qualifier of the target component will be "DSNDBD."

If the old component's name is equal to the old cluster name (plus any suffix), then the new component name will equal the new cluster name, plus the same suffix of the old component.

**Example:** When RENAMEU(NEW) is specified, the following configuration occurs:

Instance	Cluster Name	Data Component Name	Index Component Name
Old	IBM.DFSMS.DSS	IBM.DFSMS.DSS.DAT1	IBM.DFSMS.DSS.INDX1
New	NEW.DFSMS.DSS	NEW.DFSMS.DSS.DAT1	NEW.DFSMS.DSS.INDX1

• If the old and new cluster names have "cluster" as their last qualifier, and the old component names match the cluster name up to the last qualifier, then the new component names will adhere to the old component naming convention. **Example:** When RENAMEU(SYS2) is specified, the following configuration occurs:

Instance	Cluster Name	Data Component Name
Old	SYS1.IODF00.CLUSTER	SYS1.IODF00
New	SYS2.IODF00.CLUSTER	SYS2.IODF00

If the last qualifier of the new cluster name is "cluster," and the old component names do not match the cluster name up to the last qualifier, then new component names will be generated using the new cluster name and replacing the last "cluster" qualifier with "data" or "index."

**Example:** When RENAMEU(SYS2) is specified, the following configuration occurs:

Instance	Cluster Name	Data Component Name
Old	SYS1.IODF00.CLUSTER	SYS1.DFSMS
New	SYS2.IODF00.CLUSTER	SYS2.IODF00.DATA

• If the new cluster name is less than or equal to 42 characters and the last qualifier is not "cluster", DFSMSdss creates component names by adding a single character to the new cluster name: "D" for the data component, "I" for the index component.

**Example:** When RENAMEU(SYS2) is specified, the following configuration occurs:

Instance	Cluster Name	Data Component Name
Old	SYS1.IODF00.DATASET	SYS1.DFSMS
New	SYS2.IODF00.DATASET	SYS2.IODF00.DATASET.D

• If renaming the data set results in a component name that exceeds 44 characters in length, DSS replaces any DATA or INDEX specific qualifier with "D" or "I" respectively.

**Example:** When RENAMEU (NEWNAM) is specified, the following configuration occurs:

Instance	Cluster Name	Data Component Name
Old	IBM.DFSMS.DSS.LARGE.VSAM.DSNAME.TEST	IBM.DFSMS.DSS.LARGE.VSAM.DSNAME.TEST.DATA
New	NEWNAM.DFSMS.DSS.LARGE.VSAM.DSNAME.TEST	NEWNAM.DFSMS.DSS.LARGE.VSAM.DSNAME.TEST.DATA

- If the new cluster name is more than 42 characters and the last qualifier is not "cluster," DFSMSdss derives the component names by doing the following:
  - Using up to the first four qualifiers of the new cluster name
  - Appending eight-character qualifiers, generated by using the time clock and system date, until the component names are five qualifiers

Using up to the first four qualifiers of the new cluster name ensures that the component names will orient to the same catalog as the cluster.

**Note:** These examples represent common renaming scenarios. A combination of renaming rules might apply, depending on the source and target names of any given cluster or component.

# **Expiration date handling**

When you copy a data set, the expiration date of the target data set is dependent upon whether:

- The data set is VSAM or non-VSAM.
- The source data set is SMS or non-SMS-managed.
- The target data set is SMS or non-SMS-managed.
- The source data set is cataloged or not cataloged.
- The SMS target's expiration date matches the target's management class.

#### SMS to SMS

The catalog expiration date and the expiration date in the Volume Table of Contents (VTOC) will have the same value as that of the source data set. For an indexed VSAM data set, the expiration date in the VTOC for the index component will be zero. If the expiration date is different than the target's management class, SMS will modify the expiration date to match the target's management class.

#### SMS to non-SMS

The expiration date handling is dependent upon whether the data set is VSAM or non-VSAM:

- VSAM data set: The catalog expiration date will be the same as that of the source data set. In the VTOC, the expiration date is set to 99365. For an indexed VSAM data set, the expiration date in the VTOC for the index component will also be 99365.
- Non-VSAM data set: The catalog expiration date and the expiration date in the VTOC will have the same value as that of the source data set.

### Non-SMS to SMS

The expiration date handling is dependent upon whether the data set is VSAM or non-VSAM:

- VSAM data set: The catalog expiration date and the expiration date in the VTOC will have the same value as the catalog expiration date of the source data set. For an indexed VSAM data set, the expiration date in the VTOC for the index component will be zero. If the expiration date violates the target's management class, SMS will change the date to conform with the management class.
- Non-VSAM data set: If there is a catalog expiration date for the source data set, then the catalog expiration date is used for both the VTOC and the catalog expiration date of the target data set. If the source data set does not have a catalog expiration date or is uncataloged, then the VTOC expiration date for the source data set is used for both the catalog and the VTOC of the target data set. If the expiration date violates the target's management class, SMS will modify the date to conform with the management class.

### Non-SMS to non-SMS

The expiration date handling is dependent upon whether the data set is VSAM or non-VSAM and whether the source data set is cataloged or not cataloged:

- VSAM data set: The catalog expiration date is the same as that of the source data set. In the VTOC, the expiration date is set to 99365. For an indexed VSAM data set, the expiration date in the VTOC for the index component will also be 99365.
- Non-VSAM data set: The catalog expiration date of the source data set is used for the catalog expiration date of the target data set. The expiration date in the VTOC of the source data set is used for the VTOC expiration date of the target data set.

# **Defining RACF profiles**

For information about defining RACF profiles, see Chapter 20, "Data security and authorization checking," on page 531.

# Moving data sets with utilities

In some cases, DFSMSdss invokes a utility to move a data set. Table 10 on page 106 shows when DFSMSdss invokes a utility for a data set copy operation.

When you move a data set and a utility is used, the data set must be cataloged in the standard order of search.

DFSMSdss cannot use fast replication methods to move data if a utility must be used. When FASTREPLICATION(REQUIRED) is specified in such a case, DFSMSdss will not use traditional I/O movement methods and therefore will not call the utility.

When DFSMSdss invokes IEBCOPY to copy a LOADMOD, message IEC507D is issued requesting operator authorization to overwrite an unexpired area when the source data set has an incorrect RLD count and an unexpired date.

When DFSMSdss invokes IEHMOVE to copy data sets, IEHMOVE has DD statement requirements that DFSMSdss cannot always satisfy. To avoid potential abnormal ends, do one or both of the following:

- Specify the source and target volumes as PRIVATE.
- Ensure that the source and target volumes are not in the list of default volumes for dynamic allocation.

When DFSMSdss invokes IDCAMS to copy a KSDS, the data set is automatically reorganized to optimize it for VSAM processing. A large KSDS may require extensive reorganization that could result in greater processing time for the copy operation. If IDCAMS was selected because multiple output volumes were specified, performance may be improved by specifying a single output volume for the data set.

Table 10. Data Mover Selection Matrix for Data Set Copy

Data Set Type	Like Devices	Unlike Devices
Sequential	DFSMSdss	DFSMSdss
Partitioned (not PDSE)	DFSMSdss (1, 2)	DFSMSdss (1, 2)
Partitioned (not PDSE) load modules	DFSMSdss (3)	IEBCOPY
Partitioned data set extended (PDSE)	DFSMSdss (4)	DFSMSdss (4)
Direct nonrelative block address mode	DFSMSdss	DFSMSdss (5)
Direct relative block address mode (6)	DFSMSdss	DFSMSdss
ESDS	DFSMSdss (7)	DFSMSdss (7, 8)
RRDS	DFSMSdss (7)	IDCAMS (REPRO)
LDS	DFSMSdss (7)	IDCAMS (REPRO)
KSDS or VRRDS	DFSMSdss (9)	IDCAMS (REPRO)
Key range data set	DFSMSdss (10)	IDCAMS (REPRO)
Extended-format VSAM	DFSMSdss (7)	IDCAMS (REPRO)
Integrated catalog facility user catalogs	IDCAMS (EXPORT/IMPORT)	IDCAMS (EXPORT/IMPORT)
Undefined DSORG	DFSMSdss	DFSMSdss

Table 10. Data Mover Selection Matrix for Data Set Copy (continued)

Data Set Type	Like Devices	Unlike Devices

#### Note:

- 1. All partitioned data sets that are not load modules are compressed during a copy to a like or unlike device.
- 2. DFSMSdss calls the IGWFAMS utility when you are converting a PDS to a PDSE.
- 3. If copying partitioned load modules with REBLOCK, DFSMSdss calls IEBCOPY to copy the data set to a like device.
- 4. DFSMSdss calls the IGWFAMS utility when you are converting a PDSE to a PDS. DFSMSdss also calls IGWFAMS when all of the following conditions are met:
  - Fast replication methods cannot be used and FASTREPLICATION(REQUIRED) is not specified.
  - · Concurrent copy cannot be used.
- 5. The source data set is not copied if the target data set is preallocated or if the target device has a smaller track capacity than the source.
- 6. Specify the DFSMSdss RELBLOCKADDRESS parameter.
- 7. DFSMSdss calls IDCAMS if the target CISIZE, CASIZE, physical record size, or physical block size of the target is different from that of the source.
- **8**. DFSMSdss calls IDCAMS if the calculated number of blocks per control area is different from the calculated number of usable blocks per control area.
- 9. DFSMSdss calls IDCAMS if any of the following is true:
  - The CISIZE, CASIZE, physical record size, physical block size, imbed, or span attributes of the target are different from that of the source.
  - The target data set is SMS and has an imbedded index or has key ranges, and the target volume count is greater than one. For help in determining the volume count, "VOLCOUNT" on page 359.
  - The target data set is non-SMS, the source component or components span multiple volumes, and there is not enough space on one target volume to contain the entire data set.
- 10. DFSMSdss calls IDCAMS if the source and target CASIZE, physical record size, or physical block size are different; if the components span multiple volumes; for a KSDS with IMBED and either the source HURBA=HARBA or it has extended indexes.

# Moving data sets with concurrent copy

#### **Programming Interface Information**

The DFSMSdss concurrent copy function lets you move data but minimizes the time that the data is unavailable. The user determines an appropriate time to move the data (for example, when the data is in a known state and update activity is stopped). DFSMSdss is invoked directly or via the DFSMSdss application program interface (API) to do a concurrent copy of the data. After initialization is complete, DFSMSdss releases any serialization it held on the data sets and prints a message both to SYSPRINT and the console that the CC operation is logically complete. If DFSMSdss was invoked via the API, DFSMSdss informs the caller through the UIM exit option, Eioption 24 (for more information, see "CONCURRENT" on page 316). The application can resume normal operation at this time.

End	<b>Programming</b>	Interface	Information	
	110514111111111111111111111111111111111	miteriace	minormation	

If for any reason data cannot be processed with concurrent copy (for example, the hardware being used does not support concurrent copy), DFSMSdss optionally uses another method of data movement and does not release the serialization until the copy is completed.

If the source device supportsdata set FlashCopy or SnapShot, DFSMSdss can use FlashCopy or SnapShot function to provide a concurrent copy-like function called virtual concurrent copy.

## Specifying concurrent copy for COPY requests

On the DFSMSdss COPY command, you can specify that DFSMSdss is to use the concurrent copy function to process data. To do so, you specify the CONCURRENT keyword, and, optionally, one of several available sub-keywords to indicate the type of concurrent copy to be used and whether DFSMSdss can use other methods of data movement. If you do not specify the CONCURRENT keyword, your COPY request does not use concurrent copy.

The CONCURRENT keyword applies to all of the data being copied. You cannot apply this function to a subset of the data being processed.

If you specify the CONCURRENT keyword, DFSMSdss might use a function equivalent to cache-based concurrent copy, called virtual concurrent copy. During virtual concurrent copy, data is "flashed" or "snapped" from the source location to an intermediate location, and then copied to the target location through standard I/O. The operation is logically complete after the source data is "flashed" or "snapped" to the intermediate location and physically complete after the data is moved to the target media.

If the source volume supports data set FlashCopy, DFSMSdss uses FlashCopy to provide virtual concurrent copy. If the source volume is a RAMAC Virtual Array (RVA), DFSMSdss uses SnapShot. For more information about virtual concurrent copy, see "Using concurrent copy" on page 7.

**Attention:** Use concurrent copy only during periods of light update activity for the data sets or volumes involved. Performing cache-based concurrent copy operations against many large data sets when there is also heavy update activity (such as reorganizing data sets or initializing the volume the data sets reside on) might result in a shortage of storage, because data is transferred to z/OS data space storage faster than DFSMSdss can process it. When you use multiple simultaneous concurrent copy tasks to process large, heavily updated data sets, you might also experience long run times and contention for SYS.DATA.SPACE.LATCH.SET. You must ensure that during the concurrent copy operation another system does not reserve volumes that are to be processed. You must also ensure that jobs and address spaces that are to use the concurrent copy are assigned a WLM service class with a high execution velocity. Do not assign a discretionary goal to concurrent copy work. You should spread multiple concurrent copy jobs across as many LPARs as possible and avoid the use of PARALLEL mode in DFSMSdss.

#### Note:

- 1. To help ensure data integrity, do not update the data during concurrent copy initialization.
- 2. If a concurrent copy operation fails after signaling that concurrent copy initialization is complete (and update activity on the data has resumed), you

- cannot recover the data to the point-in-time at which the concurrent copy operation was started. The data might have been updated while the copy operation was progressing.
- 3. Performing cache-based concurrent copy operations against many large data sets when there is also heavy update activity (such as reorganizing data sets or initializing the volume the data sets reside on) might result in a shortage of storage. The shortage occurs because data is transferred to z/OS data space storage faster than DFSMSdss can process it.
- 4. If DFSMSdss invokes a utility such as IDCAMS REPRO or IEBCOPY for a data set copy operation, DFSMSdss does not perform concurrent copy.
- 5. VM mini-volumes are supported if you are using RVA devices to the extent that they are supported by IBM Extended Facilities Product (IXFP) device reporting.
- 6. The use of concurrent copy and virtual concurrent copy with the DFSMSdss COPY command is controlled by the RACF FACILITY class profile, STGADMIN.ADR.COPY.CNCURRNT.

For information about specifying CONCURRENT and the other COPY command keywords, refer to "COPY Command for DFSMSdss" on page 299.

# Moving data sets with FlashCopy

DFSMSdss can use FlashCopy to quickly move data from a source location to a target location when the following requirements exist:

- The source and target device types must be the same.
- The source devices and the target devices must be in the same ESS.
- The ESS must support data set FlashCopy (data set FlashCopy).
- The FASTREPLICATION(NONE) keyword is not specified.
- The data must not need manipulation. The following types of processing require data manipulation:
  - Reblocking Reblocking occurs when you specify the REBLOCK keyword or when the VTOC indicates that the data set can be reblocked.
  - PDS compression DFSMSdss compresses a PDS data set during copy processing, by default. You can specify the NOPACKING keyword to prevent DFSMSdss from compressing the PDS, thereby allowing the use of FlashCopy.
  - Changing stripe counts The source stripe count must be the same as the target stripe count for a striped extended format data set.
  - An individual stripe extending to more than one volume A single-striped sequential-extended format data set cannot use FlashCopy if either the source data set or the target data set is multivolume.
  - PDS or PDSE conversion Conversion occurs when you specify the CONVERT keyword with these data sets.
  - Block-by-block processing of direct access data sets Block-by-block processing occurs when you specify the RELBLOCKADDRESS or the AUTORELOCKADDRESS keyword.
  - Utilities FlashCopy cannot be used if your data must be moved with the use of a utility.

DFSMSdss attempts to allocate the target data set on the same device type in the same ESS if the source data is in an ESS. This increases the probability that FlashCopy can be used to copy the data. However, FlashCopy cannot be used if the source data set is multivolume and is not contained entirely in one ESS subsystem. The reason that FlashCopy cannot be used is because all source and

target devices must be in one ESS subsystem in order to establish a FlashCopy relationship. These data sets will not be processed with FlashCopy and will be allocated to whatever volumes are available, irrespective of their FlashCopy capability.

DFSMSdss FlashCopy Batch Protection allows DFSMSdss to direct a fast replication request to the storage group ACS routine. The ACS routine then assigns a storage group to allocate the data set during a logical data set COPY to SMS operation. This enables users, without modifying existing batch jobs, to have a set of volumes dedicated for FlashCopy usage, limiting situations in which a volume is selected that does not allow FlashCopy to be used (such as when a volume is a Global Mirror volume or a z/OS Global Mirror (XRC) primary).

For FlashCopy Batch Protection, add the following statement to the storage group ACS routines:

IF &ACSENVR2 = 'FLASHCPY' THEN SET &STORGRP = 'fcstrgrp'

where fcstrgrp is a new or existing storage group containing volume serials that DFSMSdss is to select for allocation.

For more information, refer to Chapter 11, "ACS routine information," on page 179.

### Designating FlashCopy usage

The FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword tells DFSMSdss how you want FlashCopy to be used. The default is FASTREPLICATION(PREFERRED).

FASTREPLICATION(REQUIRED) specifies that DFSMSdss must use FlashCopy to move data. If FlashCopy cannot be used, DFSMSdss issues error message ADR938E which indicates the processing of the current data set or that the entire COPY task failed. If the processing of the current data set failed, DFSMSdss does not try any other methods of data movement for the current data set and attempts to use FlashCopy for the subsequent data sets. If the entire copy task failed, DFSMSdss terminates the copy operation.

Restriction: You cannot use the FASTREPLICATION(REQUIRED) and CONCURRENT keywords together.

FASTREPLICATION(PREFERRED) specifies that you want DFSMSdss to use FlashCopy before any other method to move data (even when you specify the CONCURRENT keyword). If FlashCopy cannot be used and you have specified the CONCURRENT keyword, DFSMSdss attempts to use concurrent copy. If you have not specified the CONCURRENT keyword or if concurrent copy has failed, DFSMSdss uses traditional data movement methods to copy the data.

FASTREPLICATION(NONE) specifies that DFSMSdss not attempt to use FlashCopy to copy data.

For more information about the FASTREPLICATION keyword, refer to "FASTREPLICATION" on page 327.

### Preserve Mirror FlashCopy

You can choose to allow the target volume of a FlashCopy operation to be a Peer-to-Peer Remote Copy (PPRC) primary device. When the tracks associated with the FlashCopy relationship are copied to the PPRC secondary device, the PPRC

(Metro Mirror) pair goes into a duplex pending state, to ensure the integrity of the mirror between the local site and the remote site. When the FlashCopy operation completes, the PPRC\_SYNC volume pair returns to full duplex state.

IBM Remote Pair FlashCopy (also known as Preserve Mirror) mirrors the FlashCopy command that is issued at the local site, to the remote site. This allows FlashCopy operations to occur to PPRC primary volumes without affecting the PPRC duplex state.

When you specify the FCTOPPRCPrimary keyword on the COPY command, you are requesting that DFSMSdss allows a PPPRC primary volume to become the target volume of the FlashCopy operation. You can specify the following sub-keywords to indicate whether the PPRCP mirror is allowed to go to duplex pending state if the target volume of the FlashCopy operation is a metro mirror primary device:

#### **PRESMIRREQ**

specifies that if the target volume is a Metro Mirror Primary device, the pair must not go into a duplex pending state as the result of a FlashCopy operations.

#### **PRESMIRPREF**

specifies that if the target volume is a Metro Mirror primary device, it would be preferable that the pair does not go into a duplex pending state as the result of a FlashCopy operation. However, if a Preserve Mirror operation cannot be accomplished, the FlashCopy operation is still to be performed.

#### **PRESMIRNONE**

specifies that Preserve Mirror operation is not to be done, even if all of the configuration requirements for a Preserve Mirror operation are met. If the target specified is a Metro Mirror primary device, the pair is to go into a duplex pending state while the secondary device is updated with the tracks to be copied. PRESMIRONONE is the default if you specify FCTTOPPRCPrimary without a subkeyword.

**Note:** If the target volume of FlashCopy operation is not a metro mirror primary volume, then the FCTOPPRCPrimary keyword has no effect on the FlashCopy operation.

For more information about Peer-to-Peer Remote Copy (PPRC) and metro mirror operation, refer to *z/OS DFSMS Advanced Copy Services*.

For more information about the FCTOPPRCPrimary keyword on the COPY command, refer to "COPY Command for DFSMSdss" on page 299.

#### Determining why FlashCopy cannot be used

There may be times when you expect DFSMSdss to use FlashCopy to move the data but FlashCopy was not used. As far as you can tell, your data sets meet the criteria for FlashCopy use. Use the DEBUG(FRMSG (MINIMAL | SUMMARIZED | DETAILED)) keyword to help you resolve this situation. Include this keyword to indicate the applicable fast replication message level (MIN, SUM, or DTL) in your COPY command. The message level controls the type and amount of information that DFSMSdss provides.

DEBUG(FRMSG(MIN | SUM | DTL)) dircts DFSMSdss to issue an informational message that indicates why FlashCopy or Preserve Mirror was not used. When you specify FASTREPLICATION(REQUIRED), DFSMSdss issues an informational

message in addition to the ADR938E message, whether you have specified the DEBUG(FRMSG(MIN | SUM | DTL)) keyword or not.

#### Note:

- 1. The DEBUG(FRMSG) keyword might not have an effect if the target of the FlashCopy operation is not a PPRC primary device
- 2. If you specify FASTREPLICATION(REQUIRED) without specifying the DEBUG keyword, DFSMSdss still issues an informational message whenever a fast replication method cannot be used.
- 3. The DEBUG(FRMSG) keyword overrides the DEBUG=FRMSG parameter specified on the JCL EXEC statement.

For more information about the DEBUG keyword, refer to z/OS DFSMSdfp Storage Administration.

### Freeing subsystem resources

Performing a physical copy of the data uses subsystem resources and can impact the performance of other I/O operations that are issued to the ESS. Using the FCNOCOPY keyword on a DFSMSdss COPY command prevents the ESS subsystem from performing a physical copy of the data. However, when you designate the FCNOCOPY keyword, you must either withdraw the FlashCopy relationship when you no longer need the copy or convert the existing FlashCopy relationship from FCNOCOPY to COPY mode. Withdrawing the FlashCopy relationship frees the subsystem resources that are used to maintain the FlashCopy relationship.

You can withdraw the FlashCopy relationship by doing one of the following:

- Performing a logical data set dump of the target data sets (of the data set copy) and specify the FCWITHDRAW keyword on the DUMP command.
- Entering the TSO FCWITHDR command.

When an existing FlashCopy relationship is converted from no-background copy (FCNOCOPY) to background copy mode, the relationship ends (unless the relationship is persistent) when the background copy has completed. When the relationship ends, it frees the subsystem resources that are used to maintain the FlashCopy relationship. You can change the existing FlashCopy copy mode by performing a logical data set copy specifying the FCNOCOPYTOCOPY keyword along with the source data sets for which you want background copy to be started. The FCNOCOPYTOCOPY function will initiate background copy of any NOCOPY FlashCopy relationships in which the specified source data sets are participating.

In general, if you want a temporary copy of the data, specify FCNOCOPY, and then withdraw the FlashCopy relationship when you no longer need the copy. If you want a permanent copy, but want to delay background copy until a convenient time, specify FCNOCOPY to get a point-in-time copy and then perform FCNOCOPYTOCOPY later to start background copy. If you want a permanent copy and do not want to delay background copy, do not specify FCNOCOPY. Allow the ESS subsystem to perform the physical copy and release the subsystem resources that are used to maintain the FlashCopy relationship.

Note: A Persistent FlashCopy relationship does not end when physical background copy has completed. The relationship can be removed by performing a Withdraw FlashCopy operation (e.g., TSO FCWITHDR command). An Incremental FlashCopy relationship is an example of a Persistent FlashCopy relationship supported by

DFSMSdss. If you want to establish a Persistent FlashCopy relationship independent of Incremental FlashCopy, you can use the ESS Copy Services Web User Interface.

For an overview of FlashCopy and more information about the FCWITHDR command, refer toz/OS DFSMS Advanced Copy Services.

For more information, refer to "FCNOCOPY" on page 333, "FCNOCOPYTOCOPY" on page 333, and "FCWITHDRAW" on page 406 keywords.

## Moving data sets with SnapShot

When the source and target devices are in the same RAMAC Virtual Array (RVA) and the data does not need to be manipulated (such as, reblocked, track packed to unlike), DFSMSdss may be able to use SnapShot to quickly move the data from the source location to the target location. SnapShot is much faster than traditional methods, especially when large amounts of data are moved.

To use SnapShot, the following requirements must be met:

- The source and target device types must be the same.
- The source and target devices must be in the same RAMAC Virtual Array (RVA).
- The FASTREPLICATION(NONE) keyword must not be specified.
- There must *not* be any required data manipulation. The following types of processing require data manipulation:
  - Reblocking Reblocking occurs when the REBLOCK keyword is specified or when the VTOC indicates that the data set is capable of being reblocked.
  - PDS compression DFSMSdss compresses a PDS data set during copy, by default. You can specify the NOPACKING keyword to prevent DFSMSdss from compressing the PDS, thereby allowing the use of SnapShot.
  - Changing stripe counts The source stripe count must be the same as the target stripe count for a striped sequential-extended format data set.
  - An individual stripe extending to more than one volume A single-striped extended format data set cannot use SnapShot if either the source data set or the target data set is multivolume.
  - PDS or PDSE conversion Conversion occurs when you specify the CONVERT keyword with these data sets.
  - Block-by-block processing of direct access data sets Block-by-block processing occurs when you specify the RELBLOCKADDRESS OR the AUTORELOCKADDRESS keyword.
  - Utilities SnapShot cannot be used if your data must be moved with a utility.

If the source data is in an RVA, DFSMSdss attempts to allocate the target data set on the same device type in the same RVA, thus increasing the probability that SnapShot can copy the data. If the source data set is multivolume and not contained entirely in one partition of one RVA subsystem, it is not possible to allocate the target so that SnapShot can be used. These data sets are allocated to whatever volumes are available, irrespective of their SnapShot capability.

### Designating SnapShot usage

The FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword tells DFSMSdss how you want fast replication such as SnapShot to be used. The default is FASTREPLICATION(PREFERRED).

FASTREPLICATION(REQUIRED) specifies that DFSMSdss must use fast replication such as SnapShot to move data. If SnapShot cannot be used, DFSMSdss issues error message ADR938E which indicates that the processing of the current data set or the entire COPY task failed. If the processing of the current data set failed, DFSMSdss does not try any other methods of data movement for the current data set. However, DFSMSdss attempts to use fast replication such as SnapShot for the subsequent data sets. If the entire copy task failed, DFSMSdss terminates the copy operation.

Restriction: You cannot use the FASTREPLICATION(REQUIRED) and CONCURRENT keywords together.

FASTREPLICATION(PREFERRED) specifies that DFSMSdss attempt to use SnapShot before any other method to move data (even when you specify the CONCURRENT keyword). If SnapShot cannot be used and you have specified the CONCURRENT keyword, DFSMSdss attempts to use virtual concurrent copy. If you do not specify the CONCURRENT keyword or if virtual concurrent copy fails, DFSMSdss uses traditional data movement methods to copy the data.

FASTREPLICATION(NONE) specifies that you do not want DFSMSdss to use SnapShot to copy data. Instead, DFSMSdss attempts to use virtual concurrent copy if the CONCURRENT keyword is specified. If virtual concurrent copy cannot be used, DFSMSdss uses traditional data movement methods to move the data.

For more information about the FASTREPLICATION keyword, see "FASTREPLICATION" on page 327.

### Determining why SnapShot cannot be used

There may be times when you expect DFSMSdss to use SnapShot to move the data but SnapShot was not used. As far as you can tell, your data sets meet all the criteria for SnapShot use. Use the DEBUG(FRMSG (MINIMAL | SUMMARIZED | DETAILED)) keyword to help you resolve this situation. Include this keyword to indicate the applicable fast replication message level (MIN, SUM, or DTL) in your COPY command. The message level controls the type and amount of information that DFSMSdss provides.

DEBUG(FRMSG(MIN | SUM | DTL)) directs DFSMSdss to issue an informational message that indicates why SnapShot was not used. When you specify FASTREPLICATION(REQUIRED), the informational message is issued in addition to the ADR938E message whether you have specified the DEBUG(FRMSG(MIN | SUM | DTL)) keyword or not.

For more information about the DEBUG keyword, see "DEBUG" on page 320.

# Moving data sets with special requirements

Some data sets require special treatment when they are moved. The following sections discuss some considerations for moving these special data sets.

# Moving undefined DSORG and empty non-VSAM data sets

To copy a data set with an undefined DSORG, ensure that the following conditions

- The PROCESS(UNDEFINEDSORG) keyword is specified.
- The selected target volume is either of the same device type as the source volume, or a device type with equal or greater track capacity.

To copy an empty non-VSAM data set, ensure that the following conditions are

- An EOF record exists in the first track of the source data set.
- If the target data set is to be SMS-managed, the selected target SMS volume must either be of the same device type as the source data set, or a device type with equal or greater track capacity.

Note: It may not be possible to move all undefined DSORG data sets to an unlike device type, even when the unlike device type has a track capacity greater than or equal to the source device. For example, if the source device is a 3380, the output device is a 3390, and the data set's block size is less than 277 bytes, a track on the target cannot contain as much data as a track on the source, and message ADR366W (invalid track format) is issued.

### Moving system data sets

Some system data sets do not require movement, either because they are allocated during system generation or because they are built at IPL time. Other system data sets, however, can be moved by DFSMSdss for various reasons.

Unless excluded, system data sets are copied. However, they generally remain open while the system is running and cannot be scratched or uncataloged because the DELETE and UNCATALOG options apply only to data sets not in use.

Frequently, system data sets are prefixed with a high-level qualifier of SYS1. The PROCESS(SYS1) keyword can be used for a data set copy operation of a SYS1 data set to move it to a preallocated target or to copy it with the DELETE option. PROCESS(SYS1) does not apply to VTOCIX or VVDS.

To limit the use of the PROCESS keyword, you need to set up a RACF FACILITY class profile. For more information about RACF FACILITY class profiles, see *z/OS* Security Server RACF Security Administrator's Guide.

**Note:** The PROCESS(SYS1) option does not lift the restrictions on the processing of volume VVDSs or VTOC indexes.

When the PROCESS(SYS1) keyword is not specified, you cannot move system data sets the way you normally move data sets with DFSMSdss. In order for DFSMSdss to move system data sets, you must do one of the following:

- Dump the data sets, and then restore them to a different volume.
- Copy the data sets to a different volume and then catalog them in a different catalog.

When a data set copy operation is used to copy the following data sets, space is defined for the target data set but no data is copied:

- Model DSCBs
- Page and swap data sets
- SYS1.STGINDEX.

# Moving catalogs

When you copy an integrated catalog facility user catalog, the DELETE keyword must be specified, but an input volume and the RENAMEUNCONDITIONAL keyword must not be specified. You must specify the fully qualified name of the user catalog in the INCLUDE parameter. In any processor in the complex, there

should be no other jobs executing that access the user catalog being moved; otherwise, the copy operation might fail or the copied catalog might contain errors.

You need RACF access if the catalog is RACF-protected.

User catalog aliases are automatically redefined after the copy. The LOCK attribute of an integrated catalog facility user catalog is preserved during the copy operation. For a description of the LOCK attribute and the correct access authority, see z/OS DFSMS Managing Catalogs.

**Note:** DFSMSdss cannot be used to move an active VSAM master catalog, integrated catalog facility tape volume catalogs (VOLCATALOG), the VVDS, or the VTOCIX.

## Moving non-VSAM data sets that have aliases

DFSMSdss does not support INCLUDE filtering of non-VSAM data sets using an alias. To include a non-VSAM data set which has an alias for copy processing, you must use the data set's real name, as shown in the VTOC. In most cases DFSMSdss does not detect or preserve aliases of non-VSAM data sets. However, during logical data set copy with the DELETE keyword specified and the RENAMEUNCONDITIONAL keyword not specified, if the data set is SMS-managed and remains SMS-managed during the copy, any aliases associated with the data set are preserved. In all other cases, you must redefine the aliases after the data set is moved.

## Moving multivolume data sets

If you are specifying input volumes with the LOGINDDNAME or LOGINDYNAM keywords and you are moving multivolume data sets, use the SELECTMULTI keyword on the COPY command. SELECTMULTI allows you to move multivolume data sets in their entirety, even if you do not specify all the volumes on which the data set resides.

When you specify input volumes using the LOGINDDNAME or LOGINDYNAM volume list, a data set is selected based on the following criteria:

- When you either specify SELECTMULTI(ALL) or specify input volumes without specifying the SELECTMULTI keyword, all of the volumes that contain a part of a non-VSAM or VSAM cluster must be in the volume list.
  - For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:
  - Specify SPHERE and you must list all parts of the base cluster in the volume list.
  - Do not specify SPHERE and you must list all parts of the base cluster and the associated alternate indexes in the volume list.
- When you specify SELECTMULTI(ANY), any part of the non-VSAM data set or VSAM base cluster can be on a volume in the volume list.
  - For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:
  - Specify SPHERE and you must list any part of the base cluster in the volume list.
  - Do not specify SPHERE and you must list any part of the base cluster and the associated alternate indexes in the volume list.

- When you specify SELECTMULTI(FIRST), the volume list must include the volume that contains the *first part* of either the non-VSAM data set or the primary data component of the base cluster for a VSAM sphere.
  - For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:
  - Specify SPHERE and you must list the volume that contains the first extent of the data component for the base cluster in the volume list.
  - Do not specify SPHERE and you must specify the following information in the volume list:
    - The volume that contains the first extent of the data component for the base cluster.
    - The volume that contains the first extent of the data component for the associated alternate indexes.

If a data set is found on more than one specified input volume and the volume sequence numbers match, DFSMSdss cannot determine which data set to select for processing.

You do not need to specify a SELECTMULTI option when you build a list of input volumes with STORGRP. The volume list contains all of the volumes in a storage group.

A multivolume data set can be copied to a single volume or to multiple volumes. For a multivolume data set with a standard user label, only the standard user label on the first volume is copied to the target volumes.

If you do not specify any input volumes, you can move multivolume data sets without any special keywords.

A DFSMSdss logical data set copy operation attempts to ensure that all parts of a multivolume non-VSAM data set exist. In cases where a part of the data set is missing, such as an inadvertent scratching of the VTOC entry on a volume, DFSMSdss issues an error message and discontinues processing the data set.

DFSMSdss cannot process the following non-VSAM data sets because they are missing one or more parts:

- Multivolume data sets whose catalog volume order differs from the VTOC volume order
- Single-volume data sets with the same name that are cataloged as one multivolume data set
- Multivolume data sets whose last volume indicator in the VTOC is not set

**Note:** When you are copying or restoring multivolume data sets, be aware of the following considerations:

- DFSMSdss does not preserve candidate volumes. However, for SMS-managed data sets, if you copy and do not specify any output volumes, DFSMSdss preserves the source volume count. If you copy and do specify the output volumes, DFSMSdss sets the volume count to the number of output volumes specified.
- DFSMSdss does not ensure that the copied or restored data set is on the same number of volumes as the original data set, nor does DFSMSdss ensure that the copied or restored data set extents are the same as the original data set. Instead,

DFSMSdss tries to allocate the new data set on as few volumes as possible. This may result in the copied or restored data set becoming a single-volume data set.

In addition, DFSMSdss tries to allocate each volume so that all data is contained in a single primary allocation of contiguous space with few, if any, of the secondary allocations being used.

### Converting VSAM and non-VSAM data sets to multivolume

The number of volumes allocated for certain VSAM and non-VSAM data sets can be changed with VOLCOUNT keyword options. The output data set must be SMS-managed. Single-volume data sets can be converted to multivolume, multivolume data sets can be converted to single-volume, or the number of volumes allocated for multivolume data sets can be changed. Allocation depends on which VOLCOUNT keyword is selected, and on whether output volumes are specified.

Note: TTR-BDAM and unmovable data sets cannot be converted to multivolume with the VOLCOUNT keyword. If an existing multivolume TTR-BDAM or unmovable data set is encountered, a DADSM error occurs. Partitioned data sets (PDS and PDSE) cannot be made multivolume with the VOLCOUNT keyword. If DFSMSdss encounters an existing multivolume PDS or PDSE data set, it converts the data set to single-volume.

## Moving VSAM data sets

When you move a VSAM data set and the REPLACE or REPLACEUNCONDITIONAL keywords are not specified, you must specify DELETE, RENAMEUNCONDITIONAL, or RECATALOG (to a catalog different from the source catalog). If the REPLACE or REPLACEUNCONDITIONAL keyword is specified and a preallocated target is not found, DELETE, RENAMEUNCONDITIONAL, or RECATALOG must be specified for the data set to be processed.

For VSAM data sets cataloged in an integrated catalog facility catalog that will be copied using the IDCAMS utility, a preallocated target data set will be renamed using a DFSMSdss-generated temporary name. This allows dynamic allocation and IDCAMS REPRO to work, because both are currently undirected in catalog usage.

VSAM data sets cataloged in an integrated catalog facility catalog with alternate index and path associations do not use a preallocated target if the DELETE keyword is specified. No search is made for existing data sets in this case. An integrated catalog facility alternate index cannot use a preallocated target. No search is made for existing data sets when copying an alternate index.

For VSAM components that are larger than one cylinder, DFSMSdss will recognize only an integral number of cylinders of free space on a target volume. Also, the required space for a VSAM data set must be contiguous.

You can move the base cluster, all associated alternate index clusters, and paths by using the SPHERE keyword with the COPY command.

#### Restrictions for the COPY command

The following information covers restrictions when using the COPY command:

DFSMSdss must be able to invoke IDCAMS to copy an extended-format VSAM data set.

- When performing a logical copy operation of an extended-format data set, the target data set allocation must be consistent with the source data set allocation as follows:
  - If the source is extended-format VSAM, then the target must be extended-format VSAM.
  - If the source is extended-addressable VSAM, then the target must be extended-addressable VSAM.
  - If the source is a compressed-format VSAM KSDS, then the target must be a compressed-format VSAM KSDS.
  - If the source is an alternate index for an extended-format KSDS, then the target must be an alternate index for an extended-format KSDS.
  - If the source is an alternate index for a compressed-format KSDS, then the target must be an alternate index for a compressed-format KSDS.
  - The target control interval size must be equal to the source.
- When performing a logical copy operation of an extended-format VSAM data set with a stripe count of one, the resulting target will remain a VSAM data set with a stripe count of one, even if the target storage class is multi-striped.
- You can copy a sphere only if all the parts of the sphere resolve to the same catalog.
- Multiple path names to an alternate index are not supported. Only the last path name listed in the catalog is preserved.
- To copy a sphere logically without the DELETE or RECAT keywords, you must rename every data set in the sphere. This includes all paths, all alternate indexes, and the base cluster. If the target sphere is to be SMS-managed, the data sets must be renamed even if the RECATALOG keyword is specified because the RECATALOG keyword is ignored for SMS-managed data sets.

If you do not use the SPHERE keyword and the base cluster has associated alternate index clusters, only the base cluster is moved as follows:

- If you specify DELETE, only the base cluster is moved, but the alternate index cluster continues to be related to the base cluster.
- If you do not specify DELETE, a second copy of the base cluster is created, and the alternate index cluster continues to be related to the original base cluster.

To move an alternate index cluster, specify DELETE on the COPY command. Only the alternate index cluster is moved, and it continues to relate to its base cluster. An alternate index cannot be moved by itself outside the environment of the base cluster. If the base cluster is not SMS-managed, the alternate index cannot be moved to an SMS-managed volume. If the base cluster is SMS-managed, the alternate index cannot be moved to a volume residing in another storage group.

For an empty VSAM data set (zero data relative block address or zero record count), the data set is defined on the target volume but is not copied. Message ADR474W is issued for the data set.

Note: DFSMSdss does not preserve candidate volumes during copy processing.

# Moving a PDSE

The COPY command can be used to move a PDSE. The CONVERT keyword, along with the PDSE and PDS subkeywords, can be used with the COPY command to convert a PDS to a PDSE and vice versa.

The version level of a PDSE remains the same after a move if restored on z/OS V2R1.0 or later – the resulting data set keeps the same version level of the original data set if copied on z/OS V2R1.0. PDSE member generations are also preserved if copied on z/OS V2R1.0 or later.

# Moving a damaged PDS

DFSMSdss monitors PDSs during compression for conditions that are not normal. The following conditions are detected and reported:

- Missing high key entry in the PDS directory
- Missing directory EOF
- · Invalid member start TTR
  - TTR points before directory EOF
  - TTR points after end of data set
- Missing member EOF (each member of a partitioned data set is normally ended by an EOF record)
- Invalid note or note list TTR
  - Note pointing before the start of member data
  - Note pointing after the member EOF
  - Note pointing past the last valid record on a track
  - Note pointing to record 0 of a track

DFSMSdss notes all these conditions with a message.

During compression, DFSMSdss repairs:

- · Missing high key directory entry
- Missing directory EOF
- Missing member EOFs

Invalid start TTRs prevent DFSMSdss from compressing data for that member. DFSMSdss translates all valid note and note list TTRs during compression.

You can move damaged partitioned data sets to same or like device target volumes by using the NOPACKING keyword. This results in an exact track-for-track image of the source data set. Obviously, no compression is performed in this case.

# Moving unmovable data sets

When copying unmovable data sets to like devices, DFSMSdss places them at the same track locations on the target volume under the following conditions:

- The target volume has an indexed VTOC.
- The space where the unmovable data would be placed is available.

If any of these conditions do not exist, you must specify the FORCE keyword to move the data set. FORCE enables DFSMSdss to treat the unmovable data set as movable and to move it to an unlike device. Because DFSMSdss places the data set in any available location when FORCE is specified, use FORCE with caution.

If some data sets have CCHHR (cylinder, cylinder, head, head, record) location-dependent data and you are using FORCE, exclude these data sets with the EXCLUDE keyword to prevent DFSMSdss from moving location-dependent data sets.

Another way to position data sets in a specific location on a volume is to allocate all space on the target volume except where you plan to place the unmovable data sets. Then move the unmovable data sets with FORCE and afterwards scratch the dummy space allocation.

### Moving data sets to unlike devices

DFSMSdss sets the secondary space to zero when processing data sets defined with the contiguous space attribute and zero secondary allocation. This action, which prevents DFSMSdss from creating an unusable data set, may result in ABEND D37-04 due to underallocation of the data set. Should this occur, the user must preallocate the target with adequate space to allow successful copy processing.

### Moving indexed sequential data sets

DFSMSdss does not support the copy of Indexed Sequential data sets.

### Moving direct access data sets

When DFSMSdss restores direct data sets, several processing options can be used. Direct data sets can be organized by relative block address or by track-track record (TTR).

Relative block addressable direct access data sets can be processed block by block to like and unlike target devices if the block size fits on the target track. When the data sets are processed block by block, DFSMSdss updates the block reference count of dummy records contained in the relative block addressed direct access data sets. To process block by block, the direct access data sets must have neither a variable record format nor a standard user label.

TTR direct access data sets may become unusable if they are processed block by block. TTR and relative block addressable data sets can be processed track by track to like and unlike target devices whose track capacity is equal to or greater than the source. Block by block processing is more efficient because track by track processing to an unlike device of larger track capacity can leave some unused space on each track of the target data set.

The following DFSMSdss keywords implement the processing options (for details on their use, see "Explanation of RESTORE command keywords" on page 459):

#### **AUTORELBLOCKADDRESS**

If the data set is accessed with OPTCD indicating relative block addressing, it is processed as if it were specified in the RELBLOCKADDRESS subkeyword list, and processing is block by block. For more information, see z/OS DFSMS Macro Instructions for Data Sets for macro instructions on non-VSAM data sets. If your installation has many relative block address direct access data sets, you may wish to consider the DFSMSdss installation options exit to turn on AUTORELBLOCKADDRESS (see "AUTORELBLOCKADDRESS" on page 460).

#### RELBLOCKADDRESS

If the data set is specified in the subkeyword list, the data set is processed block by block.

#### **TTRADDRESS**

If the data set is specified in the subkeyword list, the data set is processed track by track.

#### **FORCE**

If the track capacity of the receiving volume is smaller than the source, FORCE may be required for variable or undefined length TTR-organized direct access data sets. These data sets may be unusable after restore and, if possible, should be restored to a like device. Use RELBLOCKADDRESS to restore relative block address direct access data sets to unlike devices.

**Note:** If you do not specify a keyword, data is moved to the target track by track.

### Moving GDG data sets

For generation data group (GDG) data sets, filtering on generations is supported. You can specify generation names in relative generation number, dsn(n), with the INCLUDE and EXCLUDE keywords. During a copy operation, if you catalog the GDGs in a different catalog or you rename them, you must predefine the target GDG base name because the source GDG base name is unusable.

### Moving generation data sets to SMS-managed volumes

An SMS-managed generation data set (GDS) can be in one of three states:

- ACTIVE
- DEFERRED
- ROLLED-OFF

When copying a GDS to an SMS-managed volume and the data set is not preallocated, DFSMSdss allocates the target GDS as follows:

- If DELETE is specified and RENAMEUNCONDITIONAL is not specified, the target GDS is allocated with the same state as the source GDS.
- If the TGTGDS keyword is specified, the appropriate status is assigned to the data set. The requested target status must not violate rules of the generation data group.
- When the source is an SMS-managed GDS and the target has the same name (that is, DELETE without RENAME), the target status is the same as the source status.
- When the source is a non-SMS-managed GDS and the target has the same name (that is, DELETE without RENAMEUNCONDITIONAL), the default target status is ACTIVE when the source is cataloged. When the source is not cataloged, the default target status is DEFERRED.
- In all other cases, the default target status is DEFERRED.
- You can use the TGTGDS keyword to alter the target status except when the source is an SMS-managed GDS and the target has the same name.

Table 11 on page 123 describes the default situation for DFSMSdss to allocate the SMS-managed GDG data set (MOVE refers to COPY command with the DELETE keyword specified):

Table 11. Default Situation for DFSMSdss to Allocate the SMS-Managed GDG Data Set

Target Environment	Source Environment	Source Status	DFSMSdss Function	TGTGDS Default
SMS	Non-SMS	Cataloged	COPY	DEFERRED
			MOVE	ACTIVE
		Not Cataloged	COPY	DEFERRED
			MOVE	DEFERRED
	SMS	ACTIVE	COPY	DEFERRED
			MOVE	ACTIVE
		DEFERRED	COPY	DEFERRED
			MOVE	DEFERRED
		ROLLED-OFF	COPY	DEFERRED
			MOVE	ROLLED-OFF

If the data set is preallocated, the state of the target GDS is not altered.


### Moving generation data sets to non-SMS-managed volumes

A non-SMS-managed generation data set (GDS) can be in one of two states:

- Cataloged
- Not cataloged

When you copy a GDS to a non-SMS-managed volume, the state of the GDS is determined only by the CATALOG or RECATALOG keywords.

# Moving SMS-managed data sets



As with the RESTORE command, COPY invokes the Automatic Class Selection (ACS) routines, which in turn assign or override a data set's classes.

When you use the COPY command, you are in the ACS ALLOC environment. The storage class ACS routine is executed first. If the storage class assigned is not null, the management class ACS routine and then the storage group ACS routine are executed. (See "ACS variables available during Copy function" on page 179 for a list of variables available to ACS routines during copy processing.)

If you do not specify otherwise, DFSMSdss passes the source data set's class names as input to ACS. If you want to specify storage and management class names to be passed to ACS, you can use the STORCLAS and MGMTCLAS keywords. You can use the NULLSTORCLAS and NULLMGMTCLAS keywords to pass null storage and management classes to the ACS routines.

VSAM alternate indexes do not have SMS constructs of their own; they use the same constructs as the base cluster. When copying or moving alternate indexes as independent clusters (because you did not specify the SPHERE keyword on the COPY command), DFSMSdss passes null classes to ACS. If you want DFSMSdss to pass the base cluster's classes to ACS, you must invoke sphere processing by specifying the SPHERE keyword on the COPY command.

If you do not want a data set to be SMS-managed, specify the BYPASSACS and NULLSTORCLAS keywords.

All of these keywords work the same for the COPY command as they do for the RESTORE command (see "Changing storage class with the RESTORE command" on page 87 and "Changing management class with restore processing" on page 88).

End Programming Interface Information

### Selecting target volumes

### **Programming Interface Information**

In an SMS-managed environment, you generally allow the system to place data sets for you. If for some reason you want to control the placement of the data sets (for example, because of performance problems or because you want to put data sets on some new, empty volumes you have just added to a storage group), you must take special steps.

If you use OUTDDNAME or OUTDYNAM to specify a volume list, the volume serial numbers are passed as input to the ACS routines. Depending on how your ACS routines are written, this input might or might not be used in determining where to place the data set.

One way to guarantee that data sets go to particular volumes is to write your storage group ACS routine such that data sets are moved to the volumes you select.

Alternatively, if a data set's storage class has the guaranteed-space attribute, the data set is placed on the user-specified volumes if the volumes reside in the same storage group and ACS selects that storage group for the data set. By using BYPASSACS and STORCLAS keywords, you can ensure that the storage group selected contains the volumes you specify with OUTDDNAME or OUTDYNAM. However, for this procedure to work, your storage group ACS routine must use storage class to determine the storage group for a data set. This allows you to determine which storage class to specify with the STORCLAS keyword to ensure that the storage group containing the volumes specified with OUTDDNAME or OUTDYNAM is selected.

 $_{-}$  End Programming Interface Information  $_{-}$ 

### Changing storage class with Copy

**Programming Interface Information** 

You can use the STORCLAS keyword to specify a storage class name for DFSMSdss to pass to ACS. You can specify the NULLSTORCLAS keyword if you want DFSMSdss to pass a null storage class to ACS.

Note: RACF checks if the RESOWNER of a given data set is authorized to define the data set with the specified STORCLAS. Ensure that the RESOWNER of the data set has the correct authority to use the indicated storage class.

Using STORCLAS does not guarantee that the data set is assigned the storage class you specify. To ensure that the storage class you specify is assigned to the data set, you must specify BYPASSACS. In this case, using BYPASSACS causes the storage

class and management class ACS routines to be bypassed, so the data set is assigned whatever you have specified with STORCLAS or, if you do not use STORCLAS, whatever the source data set's storage class is. Ensure that the storage class you specify with STORCLAS is valid, or you will get an error.

You can also use STORCLAS and BYPASSACS to move data sets into a newly defined storage class. For example, suppose you want to combine all your storage classes except two into one new, large storage class. You can code the following:

```
COPY -
DATASET(INCLUDE(**) -
BY(STORCLAS,NE,(SCNAME1,SCNAME2))) -
STORCLAS(SCNAME3) -
BYPASSACS(**) -
DELETE
```

If you specify NULLSTORCLAS and BYPASSACS together, the target data set becomes non-SMS-managed.

End Programming Interface Information —

### Changing management class with Copy

#### **Programming Interface Information**

In addition to influencing a data set's storage class with the copy command, you can also give ACS input for assigning or overriding the data set's management class. By specifying MGMTCLAS, you can pass a management class name to ACS and, as with STORCLAS, ACS ignores it, assigns it to the data set, or uses it in combination with other things to determine the data set's management class. By specifying NULLMGMTCLAS, you can pass null management class to ACS, which might or might not assign a management class to the data set.

**Note:** RACF checks if the RESOWNER of a given data set is authorized to define the data set with the specified MGMTCLAS. Ensure that the RESOWNER of the data set has the correct authority to use the indicated management class.

Also, just as with STORCLAS, you can use MGMTCLAS with BYPASSACS to ensure that the data set is assigned the management class you specify. Ensure that the management class you specify with MGMTCLAS is valid, or you will get an error. You must be authorized to use BYPASSACS and the management class you specify with MGMTCLAS.

\_\_\_\_\_ End Programming Interface Information \_\_\_\_\_

# Moving non-SMS-managed data sets

If the data set being moved is to be non-SMS-managed, use the NULLSTORCLAS and BYPASSACS keywords on the COPY command. By using these keywords, you can copy an SMS-managed data set into a non-SMS-managed data set. Using NULLSTORCLAS and BYPASSACS also prevents a non-SMS-managed data set from becoming SMS-managed. When copying a VSAM data set to a non-SMS-managed volume, ensure that a VVDS exists on the volume prior to running the job, to prevent potential allocation errors because of insufficient space. DFSMSdss assumes a VVDS exists on the volume when doing size calculations on non-SMS-managed volumes.

### Moving to preallocated data sets

In some cases, you might want to copy data sets to preallocated targets. However, integrated catalog facility catalogs, and system data sets that are named SYS1.\* cannot be copied to preallocated data sets unless the PROCESS(SYS1) keyword is specified.

If a user wishes to upgrade or downgrade an extended format nonVSAM sequential data set you must preallocate the target data set to the extended format version number.

### Rules for moving to preallocated target data sets

To use a preallocated data set, you must specify the REPLACE or REPLACEUNCONDITIONAL keyword. If the REPLACE keyword is specified, the preallocated data set name must be identical to the source data set name. If the RENAMEUNCONDITIONAL (newname) and REPLACEUNCONDITIONAL keywords are specified, the preallocated data set name must match the new name filter criteria. You cannot, however, copy a data set to a preallocated target data set with the same name within an SMS environment because SMS does not support duplicate data set names.

The rules for moving VSAM and non-VSAM data sets to preallocated data sets follow.

**VSAM preallocation:** An existing data set qualifies as a preallocated target for a data set copy operation if the cluster name matches and the complete cluster is available on target volumes.

The preallocated data set is usable if all of the following conditions that apply to the data set being processed are met:

- The user is authorized to update the target data set.
- The cluster types match.
- The number of components match.
- The key length and offset match.
- · The KEYRANGES match.
- None of the components are multivolume.
- Sufficient space is available for each component.
- Key sequential data sets (KSDS) are reusable or empty.
- Key range data sets are empty.
- The data set is cataloged in the standard order of search, if required for the copy operation.
- The data set has no alternate indexes or paths defined over it (except for a single path defined directly over the base cluster).

If a target data set is preallocated, it is scratched and reallocated when it is being renamed and:

- Any of the following source and target data set attributes do not match:
  - CI size
  - Record length
  - IMBED (only KSDS and key range data sets)
  - Key length (only KSDS and key range data sets)
  - REPLICATE (only KSDS and key range data sets)
  - SPANNED

- The data set was not defined as reusable and the high-used relative byte address (RBA) of a target VSAM KSDS is not 0.
- The target data set is not large enough to contain the source data set.

Non-VSAM preallocation: An existing data set qualifies as a preallocated target for a data set copy operation if the data set names match, the complete data set is available on target volumes, and:

- For single-volume target qualification, the data set organization is partitioned or the data set's volume sequence number in the VTOC is 1 and the last volume flag is on.
- · For multivolume target or single-volume target with the last volume flag off, the data set is cataloged in the standard order of search. All volume serial numbers returned by a locate operation on the data set are in the output volume list. (Candidate volumes are acceptable.)

Note: If a target data set is preallocated, but is not large enough to contain the source data set, it will be scratched and reallocated if it is being renamed.

You may use data set COPY to upgrade your standard format sequential data sets to large format data sets. When copying a data set and a usable preallocated target is found, it will be used as the target of the copy operation. When copying a standard format sequential data set and a preallocated large format data set is found, it will be used. If the preallocated large format data set does not have enough space for the source data, it will be scratched and reallocated as a large format data set. When copying a large format data set and a standard format sequential data set is found, it will be used and upgraded to a large format data set. If the preallocated standard format sequential data set does not have a large enough allocation to hold the source data, it will be scratched and reallocated as a large format data set.

If a user wishes to downgrade a large format data set to a standard format sequential data set, allocate a standard format sequential data set and use a utility such as IEBCOPY to copy the data from the large format data set to the standard format sequential data set.

You may also use data set COPY to upgrade your data sets that are not enabled for CA reclaim to data sets that are enabled for CA reclaim. To do this, simply preallocate a data set that is enabled for CA reclaim to use as a target of the copy. In copying a data set that is not enabled for CA reclaim, if a preallocated data set that is enabled for CA reclaim is found, the preallocated data set that is enabled for CA reclaim is used for the target of the copy. If the preallocated data set that is enabled for CA reclaim is not large enough to hold the data being copied, it is scratched and reallocated as a data set that is enabled for CA reclaim. In copying a data set that is enabled for CA reclaim, if a preallocated data set that is not enabled for CA reclaim is found, the data set that is not enabled for CA reclaim is used for the target of the copy. If the preallocated data set that is not enabled for CA reclaim is not large enough to hold the data being copied, it is scratched and reallocated as a data set that is not enabled for CA reclaim.

For PDSEs, the source data set's original version level is preserved after the copy or move, regardless of the version level of the pre-allocated target data set. For example, if the pre-allocated target data set is a PDSE with version level 2, and the source data set is a PDSE with version level 1, after a copy or move the target would be a PDSE with level 1.

The preallocated data set is usable if all of the following conditions that apply to the data set being processed are met:

- The user is authorized to update the target data set.
- The DSORG matches.
- For direct access data sets, the target does not exist if the copy operation is done using the IEHMOVE utility. If the RELBLOCKADDRESS keyword is specified for the data set, preallocated targets are allowed.
- For unmovable data sets, extents match exactly when you copy to a like device without specifying the FORCE keyword.
- For movable data sets or unmovable data sets with the FORCE keyword, the amount of allocated space in the target data set is greater than or equal to the amount of allocated space in the source data set.
- For partitioned data sets, the target directory can contain all source members and aliases.
- For preallocated standard user label data sets, the target has more than one extent when the source data set has more than one extent.

If a VSAM or non-VSAM preallocated data set is determined to be unusable, message ADR439E is issued, and the copy operation is stopped only for that data set. No attempt is made to clear or alter the target data set if:

- The source data set is empty.
- The DSORG is not supported.
- The target is preallocated but not empty.

Message ADR363E is issued to inform the user.

### Specifying multiple target volumes

When multiple target volumes and the REPLACE or REPLACEUNCONDITIONAL keyword are specified, more than one existing data set may qualify as a preallocated target. The first existing data set that qualifies as a preallocated target when you use the OUTDDNAME/OUTDYNAM list order is used as the target data set. For non-VSAM data sets that require catalog verification, the catalog standard order of search determines the data set used as the preallocated target.

The device-selection criteria used for the data set copy operation (same, like, then unlike device preference) is not observed if a preallocated data set target is used.

### How keywords work with preallocated targets

When you use preallocated data sets with the COPY command, some keywords have a different effect and others have no effect at all.

**ALLEXCP and ALLDATA:** If ALLEXCP or ALLDATA is specified and the target is a like device, the data in the source data set is moved to the target. When ALLDATA or ALLEXCP is specified for an extended-format sequential data set, data beyond the last-used-block pointer is not retained.

**CATALOG** and **RECATALOG**: Data set copy operation cannot change the catalog or the catalog status (cataloged or uncataloged) of the preallocated target data set. As a result, the CATALOG and RECATALOG keywords have no effect on preallocated target data sets. (Similarly, passwords and expiration dates of preallocated data sets cannot be changed.)

**NOPACKING:** The NOPACKING keyword is effective only for partitioned data sets. If NOPACKING is specified for preallocated partitioned data sets, the

preallocated target must reside on the same or a like device. Processing is stopped for the data set if the target resides on an unlike device. The target is not deleted and reallocated.

PERCENTUTILIZED: The PERCENTUTILIZED keyword has no effect when the target data set is preallocated.

**PROCESS(SYS1):** Data set copy operation permits moving SYS1 data sets to a preallocated target.

**REBLOCK:** If a data set qualifies for reblocking when REBLOCK is specified (sequential and partitioned only) and a preallocated target is used, the target block size is overwritten with one of the following values:

- The source data set block size
- A DFSMSdss-selected block size
- A user-selected block size passed by the installation reblock exit
- A system-determined block size

The block size used is determined by the installation reblock exit return code and the reblockable indicator for the data set VTOC entry.

If REBLOCK is not specified, the target BLKSIZE of a non-VSAM data set is overwritten with the source BLKSIZE.

If a partitioned data set is specified with both NOPACKING and REBLOCK keywords, the data set is not reblocked.

**RENAMEUNCONDITIONAL:** RENAMEUNCONDITIONAL has no effect on preallocated target data sets unless you have specified REPLACEUNCONDITIONAL.

# Moving data sets being accessed with record level sharing

During logical data set copy operations of SMS-managed VSAM data sets, DFSMSdss communicates with VSAM RLS to perform quiesce processing of data sets that are being accessed by another job using Record Level Sharing (RLS).

By default, DFSMSdss does not use timeout protection during RLS quiesce processing. You can control whether or not DFSMSdss uses timeout protection during RLS quiesce processing and what the timeout value should be using the DSSTIMEOUT parameter of the IGDSMSxx PARMLIB member.

You can also change the timeout value without IPLing the system using the SETSMS DSSTIMEOUT(nnnnn) command.

For more information about using IGDSMSxx to control the RLS timeout value used during DFSMSdss operations, refer toz/OS DFSMSdfp Storage Administration.

For more information about using the SETSMS command, refer toz/OS MVS System Commands.

# Moving preformatted empty VSAM data sets

When moving a preformatted empty VSAM data set, DFSMSdss opens the target data set in order to preformat it. Open processing requires the data set to be

cataloged in the standard order of search. Therefore, to copy a preformatted empty VSAM data set, the target data set must be cataloged in the standard order of search.

# VTOC considerations for moving volumes

When moving volumes, ensure that the VTOC on the target device is large enough to hold entries for all the data sets to be placed on the target device. If you do not expand the VTOC when moving to a larger volume, DFSMSdss logical data set processing might fail. The following two sections describe how the size of the target VTOC is affected by DFSMSdss processing.

You can also use the REFORMAT EXTVTOC or REFORMAT NEWVTOC functions of ICKDSF to extend or reallocate the VTOC on a volume if it is not large enough.

When performing a full-volume restore operation to DASD, DFSMSdss automatically corrects the free-space information on the volume and can invoke ICKDSF to rebuild the VTOC index. DFSMSdss takes this action when it copies data to a larger-capacity DASD from a smaller-capacity DASD or when both of the volumes, including volumes of equal capacity, contain a VTOC index. DFSMSdss allocates a large (more than 65 535 tracks) dummy data set to recalculate the free-space information. You can ignore any IEC614I messages that DFSMSdss generates during this process.

Following a COPY or RESTORE operation, the VTOC location or the volume serial on the target volume may change. Before this volume can be accessed on any remote system, the UCBs on the remote systems must be refreshed. The refresh occurs automatically if the volume is online and the device manager REFUCB function is enabled. You enable the REFUCB function through PARMLIB member DEVSUPxx or the MODIFY DEVMAN command. For more information, refer to the description of the REFUCB keyword in z/OS MVS Initialization and Tuning Reference or z/OS MVS System Commands.

# Logical volume copy operation

To move a volume logically, use the DATASET keyword, specify input volumes with LOGINDDNAME, LOGINDYNAM, INDDNAME, INDYNAM, or STORGRP, and use INCLUDE(\*\*). This method of moving volumes allows you to move data between unlike devices.

Some data sets require special processing when you move them (see "Moving data sets with special requirements" on page 114). For example:

- · Unmovable data sets
- Multivolume data sets
- Integrated catalog facility catalogs
- Data sets beginning with SYS1
- Data sets used by device-dependent application programs

If you use the COPY DATASET command to move a volume and the volume contains such data sets, you must move them in the correct sequence to achieve the expected results.

You may want to process unmovable data sets first, so you can place them at the same track location on the target device. Move user catalogs only when acquiesced. In addition, do not move catalogs together with the data sets cataloged in them.

See Chapter 11, "ACS routine information," on page 179 for information on automatic class selection (ACS) routines during DFSMSdss copy operations.

**Note:** Some data sets are not eligible for movement by DFSMSdss (for example, VSAM data sets not cataloged in integrated catalog facility catalogs). Others might require special parameters (for example, unmovable data sets).

## Physical volume copy operation

If you do not specify DATASET or TRACKS on the COPY command, the COPY command defaults to FULL and moves the volume physically. You must also specify INDDNAME or INDYNAM to indicate the source volume and OUTDDNAME or OUTDYNAM to indicate the target volume. Full-volume copy can move data only between like devices of equal or greater capacity (for example, from a double capacity 3380 model) to a double or triple capacity 3380 model).

**With full-volume copy**, you can physically move volumes only between like devices. However, you can move data:

- From a smaller-capacity IBM 3380 to a larger-capacity IBM 3380
- From a smaller-capacity IBM 3390 to a larger-capacity IBM 3390
- From a smaller-capacity IBM 9345 to a larger-capacity IBM 9345
- From a minivolume or virtual volume to a real volume of like device type, and vice versa, device capacity permitting

#### With tracks copy, you can move data:

- From a larger-capacity IBM 3380 to a smaller-capacity IBM 3380, if the range of data to be processed falls within the capacity of the output device
- From a larger-capacity IBM 3390 to a smaller-capacity IBM 3390, if the range of data to be processed falls within the capacity of the output device
- From a larger-capacity IBM 9345 to a smaller-capacity IBM 9345, if the range of data to be processed falls within the capacity of the output device

**Note:** If you perform a full-volume copy operation to a DASD that is shared between multiple systems, ensure that the DASD is offline to all systems except the one performing the copy.

When you use the physical volume COPY command, you can specify the COPYVOLID keyword. If you specify the COPYVOLID keyword, the volume serial number of the source volume is copied to the target volume. This ensures that RACF profiles and catalog entries for the data sets on the volume have the correct volume serial number.

**Note:** Changing the volume serial number of a volume causes the operating system to demount the target volume at the end of the copy operation. To use the target volume, you must demount the source volume and mount the target volume.

If you are using record level sharing (RLS), be careful when copying volumes with the FULL or TRACKS keywords. If the target volume has data sets on it that have retained locks or data in the coupling facility associated with them, a full-volume or tracks copy can result in data integrity problems.

For information about automatic class selection (ACS) routines during DFSMSdss copy operations, see Chapter 11, "ACS routine information," on page 179.

# Moving volumes with FlashCopy

FlashCopy is much faster than traditional data movement methods, especially when large amounts of data are moved. DFSMSdss can use FlashCopy during a full volume copy if the following requirements are met:

- The source devices and the target devices both support compatible levels of FlashCopy.
- The volumes must be in the same logical subsystem (LSS) of an ESS if the ESS supports only FlashCopy Version 1.
- The volumes must be in the same ESS.
- The FASTREPLICATION(NONE) keyword must not be specified.

For the best performance during full volume copy operations, specify the following keywords:

- ADMINISTRATOR
- ALLDATA(\*)
- ALLEXCP
- PURGE

The performance improvement that is provided by these keywords is most significant when DFSMSdss uses FlashCopy or SnapShot to perform the copy.

For more information about using the ADMINISTRATOR, ALLDATA, ALLEXCP, and PURGE keywords, see "Explanation of COPY Command Keywords" on page 310.

### Designating FlashCopy usage

The FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword tells DFSMSdss how you want FlashCopy to be used. The default is FASTREPLICATION(PREFERRED).

FASTREPLICATION(REQUIRED) specifies that DFSMSdss must use fast replication such as FlashCopy to move data. If FlashCopy cannot be used, DFSMSdss issues error message ADR938E and the copy operation fails. DFSMSdss does not try any other methods of data movement.

Restriction: You cannot use the FASTREPLICATION(REQUIRED) and CONCURRENT keywords together.

FASTREPLICATION(PREFERRED) specifies that DFSMSdss attempt to use FlashCopy before any other method to move data (even when you specify the CONCURRENT keyword). If FlashCopy cannot be used and you have specified the CONCURRENT keyword, DFSMSdss attempts to use concurrent copy. If you have not specified the CONCURRENT keyword or if concurrent copy has failed, DFSMSdss uses traditional data movement methods to copy the data.

FASTREPLICATION(NONE) specifies that DFSMSdss not attempt to use FlashCopy to copy data.

For more information about the FASTREPLICATION keyword, see "FASTREPLICATION" on page 327.

### Determining why FlashCopy cannot be used

There might be times whey you expect DFSMSdss to use FlashCopy to move the data but FlashCopy was not used. As far as you can tell, your volumes meet all the criteria for FlashCopy use. Use the DEBUG(FRMSG(MINIMAL | SUMMARIZED | DETAILED)) keyword to help you resolve this situation. Include this keyword to indicate the applicable fast replication message level (MIN, SUM, or DTL) in your COPY command. The message level controls the type and amount of information DFSMSdss provides.

DEBUG(FRMSG(MIN | SUM | DTL)) directs DFSMSdss to issue an informational message that indicates why FlashCopy was not used. When you specify FASTREPLICATION(REQUIRED), the informational message is issued in addition to the ADR938E message whether you have specified the DEBUG(FRMSG(MIN | SUM | DTL)) keyword or not.

For more information about the DEBUG keyword, see "DEBUG" on page 320.

## Freeing subsystem resources

Performing a physical copy of the data uses subsystem resources and can impact the performance of other I/O operations that are issued to the ESS. Using the FCNOCOPY keyword on a DFSMSdss copy command prevents the ESS subsystem from performing a physical copy of the data. However, when you designate the FCNOCOPY keyword, you must either withdraw the FlashCopy relationship when you no longer need the copy or convert the existing FlashCopy relationship from FCNOCOPY to COPY mode.

Withdrawing the FlashCopy relationship frees the subsystem resources that are used to maintain the FlashCopy relationship. You can withdraw the FlashCopy relationship by:

- · Performing a full volume dump of the target volume, specifying the FCWITHDRAW keyword on the DUMP command.
- Entering the TSO FCWITHDR command.

DFSMSdss also issues an FCWITHDRAW with the Delete Data Space Withdraw (DDSW) option to the target volume during COPY and RESTORE commands using FULL and TRACKS operations.

When an existing FlashCopy relationship is converted from no-background copy (FCNOCOPY) to background copy mode, the relationship ends (unless the relationship is persistent) when the background copy has completed. When the relationship ends, it frees the subsystem resources that are used to maintain the FlashCopy relationship. You can change the existing FlashCopy copy mode by performing a physical full volume or tracks copy specifying the FCNOCOPYTOCOPY keyword along with the source volume or extents for which you want background copy to be started. The FCNOCOPYTOCOPY function will initiate background copy of any NOCOPY FlashCopy relationships in which the specified source volume or extents are participating.

In general, if you want a temporary copy of the data, specify FCNOCOPY and then withdraw the FlashCopy relationship when you no longer need the copy. If you want a permanent copy, but want to delay background copy until a convenient time, specify FCNOCOPY to get a point-in-time copy and then perform FCNOCOPYTOCOPY later to start background copy. If you want a permanent copy and do not want to delay background copy, do not specify FCNOCOPY.

Allow the ESS subsystem to perform the physical copy and release the subsystem resources that are used to maintain the FlashCopy relationship.

Note: A Persistent FlashCopy relationship does not end when physical background copy has completed. The relationship can be removed by performing a Withdraw FlashCopy operation (e.g., TSO FCWITHDR command). An Incremental FlashCopy relationship is an example of a Persistent FlashCopy relationship supported by DFSMSdss. If you want to establish a Persistent FlashCopy relationship independent of Incremental FlashCopy, you can use the ESS Copy Services Web User Interface.

For more information about using the SETSMS command, refer toz/OS MVS System Commands.

For more information about using the SETSMS command, refer toz/OS MVS System Commands.

For more information, refer to "FCNOCOPY" on page 333, "FCNOCOPYTOCOPY" on page 333, and "FCWITHDRAW" on page 406.

# Choosing space efficient FlashCopy with the FCSETGTOK keyword

A space efficient volume does not have all of its physical space allocated when it is created. Instead, its physical space is allocated on a track basis. When data is written to a space efficient volume, a track of physical space is taken from the segments assigned to a repository volume, and is used to hold the data for the space efficient volume. A repository volume can provide the physical space for multiple space efficient volumes.

During full volume copy operations, DFSMSdss can use a space efficient volume as the target of a FlashCopy relationship, when you specify the FCSETGTOK keyword on your COPY command. This type of FlashCopy relationship is called a space efficient FlashCopy.

You can use space efficient FlashCopy for a full-volume copy operation only; that is, a COPY FULL operation or a COPY TRACKS command that specifies a full volume. Observe the following considerations:

- If you specify FCSETGTOK with COPY FULL, and the target is a space efficient volume, DFSMSdss attempts to establish a full-volume FlashCopy relationship without excluding free space, which results in one FlashCopy relationship for the entire volume. If FlashCopy cannot be used, DFSMSdss issues an error message and the copy operation fails. DFSMSdss does not try any other methods of data movement.
- To use FCSETGTOK with COPY TRACKS, your command must specify one track range (an extent) that includes the entire volume (tracks 0 through n). Otherwise, the FCSETGTOK keyword has no effect on the copy operation.

DFSMSdss ignores the FCSETGTOK keyword for COPY operations in which:

- FlashCopy is not used to perform the copy operation
- The target volume is not a space efficient volume
- Less than a full volume is to be copied, for example, a COPY DATASET operation.

Along with the FCSETGTOK keyword, you must also specify the FAILRELATION sub-keyword to indicate the action that the storage facility is to take if the space on the repository volume is exhausted while the space efficient FlashCopy relationship still exists.

Using FCSETGTOK might require RACF authorization. If your installation has defined the RACF FACILITY class profile, STGADMIN.ADR.COPY.FCSETGT, your user ID requires READ access to the profile. For more information, see "Protecting DFSMSdss functions with RACF FACILITY class profiles" on page 29.

**Attention:** Space efficient FlashCopy is intended for full volume copies that are short term in nature, such as those that are to be backed up to tape. Space efficient FlashCopy might also be appropriate for longer term copies, if the source and target volumes are not frequently updated. The physical background copy option is not permitted for space efficient FlashCopy. That is, you must also specify FCNOCOPY with the FCSETGTOK keyword.

For an overview of FlashCopy, refer toz/OS DFSMS Advanced Copy Services.

For more information about the FCSETGTOK keyword and the FAILRELATION sub-keyword, refer to "FCSETGTOK" on page 334.

### Initializing the volume with the FCWITHDRAW keyword

During DUMP FULL and DUMP TRACKS operations, DFSMSdss invokes ICKDSF to initialize the source volume of the DUMP operation at the end of the dump processing, when all of the following conditions are true:

- FCWITHDRAW is specified
- The VTOC tracks on the source volume of the DUMP operation are the target of a FlashCopy relationship
- TRACKS, if specified, designates one extent range that represents the entire volume
- The volume is not a VM-format volume (CP volume)
- The volume supports data set FlashCopy or space efficient FlashCopy.

If these conditions are not met, DFSMSdss performs a FlashCopy withdraw operation only.

For information about how to disable the volume initialization function, refer to "Changing the default initialization processing during DUMP with FCWITHDRAW (OA18929)" on page 236.

For information about the FCWITHDRAW keyword, refer to "FCWITHDRAW" on page 406.

# Backing up volumes with FlashCopy consistency group

The sections that follow describe the use of a FlashCopy consistency group.

### Creating consistent copies with FlashCopy consistency group

You can use the FlashCopy Consistency Group function to minimize application impact when making consistent copies of data spanning multiple volumes. The procedure consists of freezing the source volume during each volume copy operation, and thawing all the frozen volumes using the CGCREATED command after a FlashCopy Consistency Group has been formed. During the time period

between the first and the last volumes are frozen, no dependent write updates will occur which allows a consistent copy of logically related data that spans multiple volumes.

**Note:** Because I/O activity is held on source volumes that are frozen, it is recommended not to include system volumes that are required to run the current COPY command (or subsequent COPY commands) needed to form a FlashCopy Consistency Group. Examples of such system volumes include spool, page, and volumes containing checkpoint data sets, catalogs, and RACF databases.

### Freezing the source volumes in copy operations

You can use the FCCGFREEZE keyword on the COPY FULL or COPY TRACKS CPVOLUME command to specify that the FlashCopy source volume is to be part of a FlashCopy Consistency Group. Subsequent I/O activity to the source volumes will be held (frozen) as each volume is copied. A frozen volume remains in long busy state until the "Consistency Group Created" (thaw) command is processed on the logical subsystem (LSS) where the volume resides or when the FlashCopy Consistency Group timer expires.

### Thawing the frozen volumes in CGCREATED operation

When all volume copy operations have completed, you can use the DFSMSdss CGCREATED command to allow I/O activity to resume on the frozen volumes (thaw the volumes) residing in the logical subsystems. The required ACCESSVOL keyword specifies one or more volumes residing in the LSS to which the "thaw" command will be directed. Only one volume needs to be specified for each LSS containing frozen volumes in the FlashCopy Consistency Group.

### Verifying the consistency group

You can use the FCCGVERIFY keyword on the CGCREATED command to validate the state of the FlashCopy Consistency Group before thawing all the volumes. This will help you determine if the copies of the group of volumes are consistent. An error message is issued if the frozen state cannot be verified. Regardless of the verification result, DFSMSdss will proceed to thaw all the volumes in the designated logical subsystems.

For the verification volume, IBM recommends that you select the first source volume that was copied with FCCGFREEZE in the group. When the logical subsystems have different Consistency Group timer values, select the volume residing in the LSS with the smallest Consistency Group timer value, or select one volume from each LSS.

#### **Example**

**Example** In the following example, volume SRC101 and SRC102 reside on LSS 01. Volume SRC203 resides on LSS 02. LSS01 and LSS02 can be in the same or different storage control units. SRC101 is selected as the verification volume.

- The first COPY command -- by default, in SERIAL mode -- will copy the verification volume, SRC101.
- When the first COPY command completes, the PARALLEL command instructs DFSMSdss to switch to parallel mode. DFSMSdss will execute all subsequent commands in parallel until it reaches the SERIAL command which tells DFSMSdss to wait for all previous commands to finish before proceeding.
- The user instructs DFSMSdss to verify the state of the FlashCopy Consistency Group using the specified verification volume during the "thaw" operation. The CGCREATED command should always be issued to thaw the volumes whether

the copy commands completed successfully or not. In other words, the control statements do not need to check condition code prior to the CGCREATED command.

```
//SYSIN
  COPY FULL INDYNAM(SRC101) OUTDYNAM(TGT101) ADMIN DUMPCOND FCFREEZE
   PARALLEL
   COPY FULL INDYNAM(SRC102) OUTDYNAM(TGT102) ADMIN DUMPCOND FCFREEZE
   COPY FULL INDYNAM(SRC203) OUTDYNAM(TGT203) ADMIN DUMPCOND FCFREEZE
   CGCREATED FCCGVFY(SRC101) ACCVOL(SRC101, SRC203)
```

#### Note:

- 1. The freeze and thaw operations require the specified devices support the FlashCopy Consistency Group function.
- 2. There is one Consistency Group timer per logical subsystem (LSS) for FlashCopy.
- 3. The Consistency Group timer has a default of 120 seconds. The timer value can be set via the ESS Web User Interface.
- 4. The CGCREATED operation is processed at LSS level. It thaws all the volumes currently in "frozen for consistency grouping" state in the LSS that received the command. When a "thaw" command is received by an LSS that does not have any frozen volumes in a FlashCopy Consistency Group, the command is accepted, but no actual processing takes place.
- 5. Multiple FlashCopy Consistency Groups with volumes in the same LSS must not be formed at the same time.
- 6. When a FlashCopy Consistency Group timer expires before the "thaw" command is received on the LSS, I/O activity will be allowed to resume on all currently frozen volumes in the LSS. As a result, the copies of the volumes are likely inconsistent.
- 7. When FCCGFREEZE is specified, if the FlashCopy pair failed to be established, DFSMSdss will withdraw all FlashCopy relations previously established with FCNOCOPY FCCGFREEZE option by the same DFSMSdss invocation. DFSMSdss will also stop processing the rest of the COPY FCCGFREEZE commands issued by the same invocation (e.g., in the same job step).
- 8. During a CGCREATED operation, or a FCFREEZE operation that ends in error, DFSMSdss might issue a FlashCopy withdraw request for the source and target volume. If either volume is attached at device address X'0000', the system fails the FlashCopy withdraw operation with warning message ADR815W. Processing continues.

For more information, about using the FCCGFREEZE keyword on the COPY command, refer to "FCCGFREEZE" on page 328.

For more information about the ACCESSVOLUME and FCCGVERIFY keywords on the CGCREATED command, refer to "ACCESSVOLUME" on page 277 and "FCCGVERIFY" on page 278.

For more information about FlashCopy Consistency Groups, refer toz/OS DFSMS Advanced Copy Services.

## Moving volumes with SnapShot

DFSMSdss can use SnapShot during a physical full volume copy operation when the source and the target devices are in the same RAMAC Virtual Array (RVA). SnapShot is much faster than traditional methods of data movement, especially when you are moving large amounts of data.

For the best performance during full volume copy operations, specify the following keywords:

- ADMINISTRATOR
- ALLDATA(\*)
- ALLEXCP
- PURGE

The performance improvement that is provided by these keywords is most significant when DFSMSdss uses FlashCopy or SnapShot to perform the copy.

For more information about how to use the ADMINISTRATOR, ALLDATA, ALLEXCP, and PURGE keywords, see "Explanation of COPY Command Keywords" on page 310.

### Designating SnapShot usage

The FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword tells DFSMSdss how you want SnapShot to be used. The default is FASTREPLICATION(PREFERRED).

FASTREPLICATION(REQUIRED) specifies that DFSMSdss use fast replication such as SnapShot to move data. If SnapShot cannot be used, DFSMSdss issues error message ADR938E and the copy operation fails. DFSMSdss does not try any other methods of data movement.

Restriction: You cannot use the FASTREPLICATION(REQUIRED) and CONCURRENT keywords together.

FASTREPLICATION(PREFERRED) specifies that DFSMSdss attempt to use SnapShot before any other method to move data (even when you specify the CONCURRENT keyword). If SnapShot cannot be used and you have specified the CONCURRENT keyword, DFSMSdss attempts to use virtual concurrent copy. If you have not specified the CONCURRENT keyword or if virtual concurrent copy has failed, DFSMSdss uses traditional data movement methods to copy the data.

FASTREPLICATION(NONE) specifies that DFSMSdss not attempt to use SnapShot to copy data. Instead, DFSMSdss attempts to use virtual concurrent copy if the CONCURRENT keyword is specified. If virtual concurrent copy cannot be used, DFSMSdss uses traditional data movement methods to move the volume.

For more information about the FASTREPLICATION keyword, see "FASTREPLICATION" on page 327.

# Determining why SnapShot cannot be used

There may be times when you expect DFSMSdss to use native SnapShot to move the data but SnapShot was not used. As far as you can tell, your volume meets all the criteria for SnapShot use. Use the DEBUG(FRMSG(MINIMAL | SUMMARIZED | DETAILED)) keyword to help you resolve this situation. Include this keyword to indicate the applicable fast replication message level (MIN, SUM, or DTL) in your COPY command. The message level controls the type and amount of information that DFSMSdss provides.

DEBUG(FRMSG(MIN | SUM | DTL)) directs DFSMSdss to issue an informational message that indicates why SnapShot was not used. When FASTREPLICATION(REQUIRED) is specified, the informational message is issued in addition to the ADR938E message whether you have specified the DEBUG(FRMSG(MIN | SUM | DTL)) keyword or not.

For more information about using the DEBUG keyword, see "DEBUG" on page 320.

## Moving volumes to like devices of equal capacity

When the source and target devices are of equal capacity, you can use logical or physical copy processing. If you use logical processing, the source VTOC is not copied to the target device. In this case, use ICKDSF to initialize the target device with an appropriately sized VTOC, then perform the logical data set copy operation.

If you use physical processing, the source VTOC is copied to the target device and DFSMSdss might invoke ICKDSF to rebuild the VTOC index (if present on the source and target devices). If you determine that the source VTOC is not large enough for the target device, use ICKDSF to initialize the target device with an appropriately sized VTOC, use logical data set copy to move the volume.

# Moving volumes to like devices of greater capacity

When the target device is of greater capacity than the source (for example, if you are moving from a 3390 Model 2 to a 3390 Model 3), you can use logical or physical copy processing. If you use logical processing, the source VTOC is not copied to the target device. In this case, use ICKDSF to initialize the target device with an appropriately sized VTOC, then perform the logical data set copy operation. If you do not expand the VTOC when moving to a larger volume, DFSMSdss logical data set processing might fail.

If you use physical processing, the source VTOC is copied to the target device if the target VTOC is within the range of the source device (for example, if you are copying a 3390 Model 2 to a 3390 Model 3 and the VTOC on the 3390 Model 3 starts at or before cylinder 2226). In this case, DFSMSdss automatically rebuilds the free-space information in the target VTOC or the indexed VTOC (if present) on the target device to account for the larger size. If you determine that the source VTOC is not large enough, do *one* of the following two things:

- Use ICKDSF to initialize the target device with an appropriately sized VTOC, then use logical data set copy to move the volume.
- Use ICKDSF to initialize the target device with an appropriately sized VTOC that is outside the range of the source device (for example, if you are copying a 3390 Model 2 to a 3390 Model 3, put the VTOC on the 3390 Model 3 at or after cylinder 2227), and then use full volume copy to move the volume. In this case, the size and location of the target VTOC are preserved and DFSMSdss automatically rebuilds the free-space information in the target VTOC or the indexed VTOC (if present).

## Moving volumes to unlike devices

When moving data between unlike devices, you must use logical processing. If you specify DATASET with the COPY command, DFSMSdss does a logical copy operation. To copy all the data on a volume logically, you also need to specify input volumes with LOGINDDNAME, LOGINDYNAM, INDDNAME, or INDYNAM. LOGINDDNAME or LOGINDYNAM is required if you specify SELECTMULTI.

## Moving VM-format volumes

You can use DFSMSdss to move VM-format volumes that are accessible to your z/OS system. The volumes must have OS-compatible VTOCs starting on track zero, record five. DFSMSdss can only retrieve device information from the OS-compatible VTOC, and cannot interpret any VM-specific information on the volume.

Use the CPVOLUME keyword and specify the range of tracks to be copied with the TRACKS keyword. You can use concurrent copy to move the volume by specifying the CONCURRENT keyword. Because DFSMSdss cannot check access authorization for VM data, CPVOLUME is only allowed with the ADMINISTRATOR keyword.

Exercise caution when using DFSMSdss to copy VM-format volumes because DFSMSdss does not serialize any VM data in any way. You cannot copy VM-format volumes to OS-format volumes, nor can you copy OS-format volumes to OS-format volumes.

# Chapter 8. Converting data to and from SMS management

DFSMSdss is the primary tool for converting data to and from SMS management. Conversion can be done with or without data movement.

This topic is organized as follows:

- "Evaluating conversion to SMS management" discusses the advantages and disadvantages of the two types of conversion.
- "Conversion by data movement" on page 142 describes how to use the COPY and DUMP/RESTORE commands to convert data sets *to* SMS management.
- "Conversion without data movement" on page 143 describes how to use the CONVERTV command to convert volumes *to* SMS management.
- "Special data set requirements for conversion to SMS" on page 146 describes some of the data sets that have special requirements for conversion to SMS management.
- "Converting from SMS management without data movement" on page 148 describes how to use the CONVERTV command to convert volumes from SMS management.
- "Special data set requirements for conversion from SMS" on page 148 describes some of the data sets that have special requirements for conversion from SMS management.

## **Evaluating conversion to SMS management**

When you convert data to SMS management, the first thing to consider is whether to convert data sets with or without data movement. If you have SMS-managed volumes with sufficient free space, you can convert data sets by simply moving them from non-SMS-managed volumes to SMS-managed volumes. The same is also true if you are converting data from SMS-management. Converting data sets to SMS management by data movement is often preferable because it allows the system to place the data sets for you. This ensures that the data sets are placed on volumes in storage groups that can meet the availability and performance requirements of the data set.

If, however, you do not have sufficient free space on your SMS-managed volumes to convert by data movement, you might have to convert data sets without data movement. The drawback to this method of conversion is that it does not allow the system to place data sets for you. You must ensure that the storage group in which you place the volume can meet the availability and performance requirements of the data sets.

Regardless of how you convert to SMS management, you must determine the eligibility for conversion of your data sets and volumes prior to conversion.

# Data sets ineligible for conversion to SMS

The following data sets cannot be converted to SMS management:

- Absolute track allocation data sets
- Direct with OPTCD=A
- · GDS with candidate volumes
- · Indexed sequential data sets

- Model DSCBs
- SYS1 storage index data sets (SYS1.STGINDEX)
- · Indirectly cataloged data sets
- · Uncataloged, multivolume data sets
- VSAM data sets not cataloged in an integrated catalog facility catalog
- VVDS/VTOCIX
- · Unmovable data sets

#### Note:

- 1. Using the CONVERTV command with the SMS and TEST keywords identifies ineligible data sets without actually converting any data.
- 2. VVDS/VTOCIX data sets can be SMS-managed, but DFSMSdss cannot be used to convert them, except when using the CONVERTV command to convert the volume that they are on.

## Data sets ineligible for conversion from SMS

The following data sets cannot be converted from SMS management:

- Extended-format sequential data sets
- · Extended-format VSAM data sets
- · Indirectly cataloged data sets
- VSAM data sets that have record level sharing (RLS) information associated with
- VSAM base cluster or alternate index with a component with greater than 255 extents.

#### Note:

- 1. Using the CONVERTV command with the NONSMS and TEST keywords identifies ineligible data sets without actually converting them.
- 2. VVDS/VTOCIX data sets can be non-SMS-managed, but DFSMSdss cannot be used to convert them, except when using the CONVERTV command to convert the volume that they are on.

# Volumes eligible for conversion to SMS

A volume is eligible for conversion if it:

- · Is a DASD volume
- · Is permanently mounted and accessible online
- · Has an indexed VTOC
- Is defined in an SMS storage group in an active configuration

# Conversion by data movement

By using the logical data set COPY or DUMP/RESTORE command, you can move data sets between non-SMS-managed and SMS-managed volumes. When moving data sets to SMS-managed volumes, COPY and RESTORE commands invoke ACS to assign classes to the data sets. This type of conversion to SMS allows the data sets to be placed on the most appropriate SMS-managed volume.

# Converting to SMS management by data movement

When moving data sets to SMS-managed volumes, you can use the COPY or RESTORE command. You can specify storage and management class names with the STORCLAS and MGMTCLAS keywords. You can also specify output volumes with OUTDDNAME and OUTDYNAM. DFSMSdss passes the class names and volume serial numbers to ACS, which might use them in determining the classes and placement of the data set.

This method of converting data sets to SMS management is similar to moving data sets in an SMS-managed environment as described in "Moving SMS-managed data sets" on page 123.

If you use the COPY or RESTORE command on a data set that is ineligible for SMS management and if a non-SMS-managed volume has been specified in the output volume list, DFSMSdss puts it on a non-SMS-managed volume. However, if you specify STORCLAS and BYPASSACS with the COPY or RESTORE command for a data set that is ineligible for SMS management, the copy or restore operation fails.

For data sets cataloged outside the standard order of search, use the INCAT keyword on the COPY or DUMP command to identify what catalog to search. Use the SELECTMULTI keyword on the COPY or DUMP command to convert multivolume data sets. This allows you to specify only the volume with the primary component on the LOGINDD or LOGINDY parameter. You can use the SPHERE keyword on the COPY DUMP/RESTORE command to convert entire VSAM spheres (if you use SPHERE on the RESTORE command, you must specify it on the corresponding dump as well).

Note that neither the COPY nor the RESTORE command invokes the data class ACS routine, so no data class is assigned. To cause the data class ACS routine to be invoked, create a new dataset either with the IDCAMS DEFINE command or a JCL DD statement with DISP=(NEW,CATLG).

# Conversion from SMS management by data movement

To take a data set out of SMS management with the COPY or DUMP/RESTORE command, you should specify the BYPASSACS and NULLSTORCLAS keywords. This forces DFSMSdss to make the data set non-SMS-managed.

### Conversion without data movement

Conversion without data movement is divided into two phases: conversion of data sets and conversion of volumes. Convert data sets and the volumes they reside on without moving data by using the DFSMSdss CONVERTV command. You should set up RACF FACILITY class authorization to limit the people who can use the CONVERTV command. When you use the CONVERTV command to perform conversion, it attempts to convert all the data sets on the volume. After all the data sets are processed, the volume is placed in one of the following three states:

- CONVERTED—the volume and its data sets are converted to SMS management. A volume can be placed in this state with the CONVERTV command and the SMS keyword.
- INITIAL—new allocations cannot be made to the volume and, although users can access their data sets, the data sets cannot be extended to other volumes. A volume may be placed in this state because you have used the CONVERTV command with the PREPARE keyword to reduce activity to the volume prior to conversion. A volume may also be placed in this state if you are attempting to convert it but it contains data sets that are not eligible for conversion.

 NONSMS—the volume and its data sets were taken out of the CONVERTED or the INITIAL state and are non-SMS-managed. A volume can be placed in this state with the CONVERTV command and the NONSMS keyword.

### Simulating conversion

Before you convert a volume to SMS management, you should simulate the conversion to ensure that all the data sets on the volume are eligible for conversion to SMS. In addition, simulating conversion shows you the classes ACS would assign to the data sets eligible for conversion.

You can simulate conversion by using the CONVERTV command with the SMS and TEST keywords. If the volume is ineligible for conversion, the data sets on the volume are still examined to determine their eligibility for conversion (provided the volume is permanently mounted and online).

When you use CONVERTV SMS TEST, you are in the ACS CONVERT environment. Only the storage class and management class ACS routines are executed. For a list of variables available to ACS routines during CONVERTV processing, see "ACS variables available during RESTORE and CONVERTV processing" on page 181.

Simulated conversion creates a report that identifies data sets ineligible for conversion. For a sample of this report, see "SMS report" on page 146. Note that this report indicates the management class and storage class that would be assigned to each data set. Careful analysis of this report allows you to determine if your ACS routines will assign appropriate classes to the data sets before doing the actual conversion.

Move data sets unsupported by SMS off the volume prior to actual conversion. Other data sets (for example, uncataloged data sets) can be made eligible for conversion by taking some action (for example, using the CATALOG keyword to catalog uncataloged data sets).

If you have ineligible data sets on a volume and you run the CONVERTV function with SMS, DFSMSdss still converts the eligible data sets on the volume. It then puts the volume in the INITIAL state. You must then take action to make the ineligible data sets eligible for conversion or move them off the volume. Once all the ineligible data sets are dealt with, you can run CONVERTV processing again to complete the conversion.

# Preparing a volume for conversion

Before you convert a volume to SMS management, you should reduce the amount of activity to the volume being converted. The CONVERTV command with the SMS keyword automatically places the volume in a state of reduced activity before doing the actual conversion. You might, however, want to reduce activity without doing the actual conversion (for example, if you want to simulate conversion). Do this by specifying the PREPARE keyword on the CONVERTV command.

Specifying PREPARE prevents data sets from extending and new allocations from being made on the volume. However, users can still access the data on the volume from either the SMS system or a system sharing the volume.

When you use PREPARE, a report is generated that tells you the volumes that have been placed in the INITIAL state. If any of the volumes are ineligible to be placed in the INITIAL state, the report also lists them and the reason they were ineligible (for example, they did not have an indexed VTOC or were offline).

If you use the TEST keyword with PREPARE, you still get the report indicating which volumes would and would not be placed in the INITIAL state, but the PREPARE is not actually performed. You can then take some action to make those volumes eligible or simply not run PREPARE against those volumes.

The CONVERTV command with the NONSMS keyword reverses the effect of PREPARE and takes a volume out of the INITIAL state.

## Converting to SMS management without data movement

To convert data to SMS management, use the CONVERTV command with the SMS keyword. (Because SMS is the default for the CONVERTV command, you can simply specify CONVERTV.) Of course, the volume and all its data sets must be eligible for conversion to successfully run CONVERTV with SMS.

If the volume is eligible for conversion, the INITIAL indicator on the volume is set. This means the volume is in the same state as when you specify the CONVERTV command with the PREPARE keyword. When a volume has its INITIAL indicator set on, DFSMSdss begins processing the data sets on the volume.

If a data set is eligible for conversion, ACS is called to assign SMS classes to the data set. When you use the CONVERTV command with SMS, you are in the ACS CONVERT environment. The storage class ACS routine is executed first. If the storage class assigned is not null, the management class ACS routine is executed. For a list of variables available to ACS routines during CONVERTV processing, see "ACS variables available during RESTORE and CONVERTV processing" on page 181.

RACF checks if the RESOWNER of a given data set is authorized to define the data set with the given STORCLAS, MGMTCLAS, or both. Ensure that the RESOWNER has the correct authority.

If no errors occur, the catalog entry for the data set is updated to include the classes. For VSAM data sets, the catalog entry is updated to indicate that it is SMS-managed. For non-VSAM data sets, a catalog entry is added that indicates the data set is SMS-managed. After the catalog updates and additions are successfully made, the data set's VTOC entry is updated to indicate it is SMS-managed.

If a VSAM data set has the guaranteed-space attribute, a check is done to verify the eligibility of its candidate volumes. If this check fails, the data set is not converted to SMS management. Non-VSAM data sets have candidate volumes in their catalog entries made nonspecific.

When DFSMSdss encounters a data set that is not eligible for conversion, it does not process the data set, but it continues to process other data sets on the volume. The only time conversion of data sets stops is when an error prevents ACS from returning class information for any data set.

DFSMSdss does not mark a volume as SMS-managed until all the data sets on the volume are SMS-managed. If a volume contains data sets that are ineligible for conversion, you must take some action to make them eligible or move them off the volume. You can then resubmit the CONVERTV command to convert any data sets not already converted and mark the volume as an SMS-managed volume.

On subsequent invocations of CONVERTV processing, DFSMSdss processes only those data sets not yet converted unless you specify the REDETERMINE keyword. If REDETERMINE is specified, DFSMSdss processes data sets already converted if their SMS management class or SMS storage class do not match those returned by the current ACS routines and data sets not yet converted. You may want to do this if your ACS routines changed since the last time you ran the CONVERTV operation on the volume.

## **SMS** report

Figure 3 shows a sample report generated by DFSMSdss during CONVERTV SMS processing.

```
PAGE 0001
                 5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                                              1999,211 14:55
  CONVERTV
      SMS
      DYNAM(D9S060)
ADR101I (R/I)-RI01 (01), TASKID 001 HAS BEEN ASSIGNED TO COMMAND 'CONVERTV'
ADRI09I (R/I)-RI01 (01), 1999.211 14:55:22 INITIAL SCAN OF USER CONTROL STATEMENTS COMPLETED. ADR016I (001)-PRIME(01), RACF LOGGING OPTION IN EFFECT FOR THIS TASK
ADROBGI (001)-TRIBL(01), AND LOUGHING OF THE INTECT FOR THIS TASK
ADROBGI (001)-EVSMS(01), PROCESSING BEGINS ON VOLUME D9S060
ADR873I (001)-KVSMS(01), VOLUME D9S060 IN STORAGE GROUP XFMT9SSG IS ELIGIBLE FOR CONVERSION TO SMS MANAGEMENT
ADR877I (001)-KVSMS(01), THE FOLLOWING DATA SETS ON VOLUME D9S060 WERE SUCCESSFULLY PROCESSED
                               PUBSEXMP.ESDS.S01
                                                                                          CATALOG: TEST.CAT.PUBSEXMP
                                                                                         MGMTCLAS: NONE
CATALOG: TEST.CAT.PUBSEXMP
                                    STORCLAS: XFMT9SSC
                               PUBSEXMP.KSDS.S01
                                    STORCLAS: XFMT9SSC
                                                                                          MGMTCLAS: NONE
                               TEST, CAT, PUBSEXMP
                                                                                          CATALOG: TEST.CAT.PUBSEXMF
                                    STORCLAS: XFMT9SSC
                                                                                          MGMTCLAS: NONE
                               PUBSEXMP.SAM.S01
                                                                                          CATALOG: TEST.CAT.PUBSEXMP
                                    STORCLAS: XFMT9SSC
                                                                                         MGMTCLAS: NONE
                               PUBSEXMP.PDS.S01
                                                                                         CATALOG: TEST.CAT.PUBSEXMF
                                    STORCLAS: XFMT9SSC
                                                                                          MGMTCLAS: NONE
ADR885I (001)-KVSMS(01), VOLUME D9S060 HAS BEEN SUCCESSFULLY CONVERTED TO SMS MANAGEMENT
                 5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
PAGE 0002
ADR892I (001)-KVRPT(01), THE STATUS OF EACH VOLUME IS AS FOLLOWS
                                      VOLUME
                                                                                       REASON FOR FAILURE
                                                             FINAL STATUS
                               D9S060 - CONVERTED
                                                             SMS
ADRO06I (001)-STEND(02), 1999.211 14:55:23 EXECUTION ENDS
ADR013I (001)-CLTSK(01), 1999.211 14:55:23 TASK COMPLETED WITH RETURN CODE 0000
ADR012I (SCH)-DSSU (01), 1999.211 14:55:23 DFSMSDSS PROCESSING COMPLETE. HIGHEST RETURN CODE IS 0000
```

Figure 3. SMS Report

For details on the messages, refer to z/OS MVS System Messages, Vol 1 (ABA-AOM).

# Special data set requirements for conversion to SMS

Some data sets have special requirements for conversion to SMS management. The sections below describe the special considerations for converting these data sets to SMS management.

# **VSAM** sphere eligibility

A VSAM sphere is considered to be a single data set by the CONVERTV command. As a result, either all the data sets of the sphere are converted or none of them are.

If any of the following parts are ineligible for conversion, then all the clusters that compose the sphere are ineligible for conversion:

- Components of a base cluster
- Alternate indexes related to the base cluster
- Alternate index components
- Paths relating alternate indexes to the base cluster

You must direct all parts of a VSAM sphere (the base cluster, base cluster components, alternate indexes, alternate index components, and paths) to the same catalog by using an alias. If they are not directed to the same catalog, the sphere cannot be converted to SMS management. To correct this problem you can either rename the data sets in the sphere, or add or delete catalog aliases, and rerun the CONVERTV command.

### Multivolume data sets

If you do not specify SELECTMULTI, all volumes must be included in DDNAME or DYNAM volume lists.

If you specify input volumes (with either the DDNAME or DYNAM volume list), a data set is selected based on the following criteria:

- When you either specify SELECTMULTI(ALL) or specify input volumes without specifying the SELECTMULTI keyword, all of the volumes that contain a part of the non-VSAM data set or VSAM base cluster must be in the volume list.
- When you specify SELECTMULTI(ANY), any part of the non-VSAM data set or VSAM base cluster can be on a volume in the volume list.
- When you specify SELECTMULTI(FIRST), the volume list must include the volume that contains either the first part of the non-VSAM data set or the primary data component of the base cluster for a VSAM sphere.

Multivolume data sets are not eligible for conversion if any part of the data set resides on volumes that:

- · Do not have indexed VTOCs
- · Are not defined in an SMS storage group
- Are defined to a different storage group
- Are not permanently mounted and online

If the previous requirements are satisfied, DFSMSdss verifies that all the volumes on which the data set resides:

- Are permanently mounted and online
- · Have indexed VTOCs
- Are defined to the same storage group

If all these criteria are met, the data set is converted to SMS management.

#### Note:

- 1. If SELECTMULTI(FIRST) or SELECTMULTI(ANY) is specified, volumes not specified in the DDNAME or DYNAM volume lists are put in the INITIAL state following a successful conversion of the data set to SMS (unless the volume is already in the INITIAL or SMS state.)
- 2. If SELECTMULTI is not specified or if SELECTMULTI(ALL) is specified, volumes not specified in the DDNAME or DYNAM volume lists are not put in the INITIAL state.

DFSMSdss cannot determine whether or not a volume being converted is a candidate volume for one or more data sets in the system. If such a volume is converted, DFSMSdss cannot ensure consistent conversion for all of the volumes of the data set (or sets) for which the volume is a candidate. This can result in a data set having both SMS-managed and non-SMS-managed volumes in its volume list, which can cause the data set to become unusable.

To avoid this situation when performing CONVERTV operations, if you specify any volume of a multivolume data set in the list of volumes to be converted, ensure that you also include at least one of the primary volumes of the data set. This allows DFSMSdss to ensure that all of the volumes of the data set are converted consistently.

#### GDG data sets

Generation data groups (GDGs) require special consideration while being cataloged or uncataloged during SMS conversion. Uncataloged GDGs are converted to SMS management, but are left uncataloged. Messages ADR877I and ADR879I indicate NOT CATALOGED for the catalog name in the data set name lists for SMS processing.

### Temporary data sets

Data set VTOC entries of temporary data sets are updated to indicate uncataloged SMS status.

### VTOC and VVDS

Data set VTOC entries for the VTOC, VTOC index, and VVDS are updated to SMS management.

## Converting from SMS management without data movement

If you want to take volumes out of SMS management, you can use the CONVERTV command with the NONSMS keyword. All volumes and most data sets are eligible for NONSMS processing. After you execute this command, the volume indicators that designate the volume as an SMS-managed volume are turned off. The active SMS configuration should be updated to remove the volume from its storage group, otherwise data set allocations to the volume will fail. Thereafter, only non-SMS-managed data sets can be allocated to the volume.

As with the SMS keyword, you can specify the TEST keyword with NONSMS. No conversion is actually done, but a report is generated that identifies the data sets that are and are not eligible for conversion from SMS management. The report also indicates whether the volume as a whole is eligible for conversion from SMS management.

To convert a data set from SMS management, the data set's classes are deleted from its catalog entry. Nonspecific volumes also are deleted from the catalog entry. For a VSAM data set, the SMS-related items are deleted from the catalog entry. For a non-VSAM data set, the catalog entries are updated to remove the SMS information. After the catalog and VVDS updates and deletions are made, the VTOC entry is updated to be non-SMS-managed.

Note: You cannot specify the CATALOG and REDETERMINE keywords with NONSMS.

# Special data set requirements for conversion from SMS

When being converted from SMS management, some data sets require special consideration. The following sections discuss some of the special requirements for converting data sets from SMS management.

### Multivolume data sets

All pieces of a multivolume data set must be converted from SMS management at the same time. You can do this by using the SELECTMULTI keyword.

If you do not specify SELECTMULTI, then you must specify all the volumes in the DDNAME or DYNAM volume list on which the data set resides.

If you specify input volumes (with either the DDNAME or DYNAM volume list) for NONSMS processing, a data set is selected based on the following criteria:

- When you either specify SELECTMULTI(ALL) or specify input volumes without specifying the SELECTMULTI keyword, all of the volumes that contain a part of the non-VSAM data set or VSAM base cluster must be in the volume list.
- When you specify SELECTMULTI(ANY), any part of the non-VSAM data set or VSAM base cluster can be on a volume in the volume list.
- When you specify SELECTMULTI(FIRST), the volume list must include the volume that contains the first part of either the non-VSAM data set or the primary data component of the base cluster for a VSAM sphere.

Those volumes not included in the volume list will be placed in the INITIAL state. Being in the INITIAL state locks all allocations to the volume until all data sets residing on it are converted.

DFSMSdss cannot determine whether or not a volume being converted is a candidate volume for one or more data sets in the system. If such a volume is converted, DFSMSdss cannot ensure that all of the volumes of the data set (or sets) for which the volume is a candidate, are converted consistently. This can result in a data set having both SMS-managed and non-SMS-managed volumes in its volume list, which can cause the data set to become unusable.

To avoid this situation when performing CONVERTV operations, if you specify any volume of a multivolume data set in the list of volumes to be converted, ensure that you also include at least one of the primary volumes of the data set. This allows DFSMSdss to ensure that all of the volumes of the data set are converted consistently.

#### GDG data sets

When you convert from SMS management, generation data group (GDG) data sets require special consideration with regard to cataloging. Data sets marked as "deferred roll in and rolled out" are uncataloged.

# Temporary data sets

Data set VTOC entries for temporary data sets are updated to non-SMS status.

### VTOC and VVDS

Data set VTOC entries for the VTOC, VTOC index, and VVDS are updated to non-SMS status.

# Special considerations for using non-SMS-managed targets

When moving to non-SMS-managed targets, there are some special considerations for certain data sets:

• Extended-format data sets cannot be moved to a non-SMS-managed target.

• COPY with DELETE and without RENAMEUNCONDITIONAL is not supported for data sets with DFM attributes. DFM attributes are not maintained for non-SMS data sets.

# **Chapter 9. Managing space with DFSMSdss**

You can use DFSMSdss to help manage your DASD space. This topic discusses how to reclaim DASD space, and how to reduce fragmentation on volumes.

## **Reclaiming DASD space**

You can use DFSMSdss to reclaim DASD space in the following ways:

- Releasing unused space in data sets
- Compressing partitioned data sets to consolidate unused space at the end of the data sets and then releasing the unused space
- Deleting unwanted data sets
- · Combining data set extents.

## Releasing unused space in data sets

The RELEASE command releases allocated but unused space from all sequential, partitioned, and extended-format data sets that you select with INCLUDE, EXCLUDE, or BY criteria. For an explanation of these criteria, see Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259. DFSMSdss selects only data sets that have space that can be released. You can also use ISMF to build a list of data sets based on the amount of unused space and to invoke DFSMSdss to release the unused space in them.

Exclude data sets whose last block pointer in the data set VTOC entry is not maintained in the VTOC by using the EXCLUDE keyword. This can occur if you use an access method other than BSAM, QSAM, BPAM, or VSAM. DFSMSdss does not release space for data sets whose last block pointer in the data set entry is 0.

The following options can help you use the release function more effectively:

#### MINSECQTY(n)

Allows you to specify that space not be released unless the user's secondary allocation is greater than or equal to n. In this way, you ensure that the user can still add to the data set after the release. The default value for n is 1.

#### MINTRACKSUNUSED(n)

Allows you to specify that space not be released unless the number of unused tracks is greater than or equal to n. Without MINTRACKSUNUSED, space is released if the data set has one or more unused tracks.

**Note:** When space in a data set is released, all unused space is released, not just the amount beyond the minimum unused (as specified by MINTRACKSUNUSED).

To protect the user, DFSMSdss does not release any space in a data set if:

- The data set has the maximum number of used extents. A data set with the maximum number of allocated extents but fewer than the maximum number of used extents will have the unused space released.
- The cylinder-allocated data set has unused tracks but not an entire unused cylinder.

 The data set's name begins with SYS1, unless the PROCESS(SYS1) keyword is specified. To limit the use of PROCESS, you need to set up a RACF FACILITY class profile.

## Compressing a PDS

The COMPRESS command compresses a PDS on a specified volume. Compression removes unused space between members in a partitioned data set. This recovered space is then available for reuse at the end of the data set. Depending on the filtering criteria you specify, you can compress all the partitioned data sets or only some of the data sets. This command is useful for compressing system partitioned data sets before applying maintenance (thus avoiding certain space-related abends). You must not compress the data sets that contain DFSMSdss or IEBCOPY executable code.

The actual PDS compression is done in place. To prevent loss of data if the system or the compression operation abnormally ends during processing, back up your volume or data sets that meet the filtering criteria before using this command.

COMPRESS does not support processing partitioned data sets that:

- Are unmovable
- Have no directory

## Deleting unwanted data sets

You can use the DELETE and PURGE keywords and data set filtering with a physical data set dump to delete unwanted data sets from DASD.

Note: This does not apply to VSAM data sets, multivolume non-VSAM data sets, or migrated data sets.

On a logical data set dump when using the DELETE keyword, VSAM, non-VSAM, and multivolume data sets are deleted. DFSMSdss cannot be used to delete migrated data sets.

The following steps show how to delete (scratch and uncatalog) all data sets that have expired and all data sets that have not been referred to in the last year. The data sets are not actually moved to a dump volume.

1. JCL requirement:

```
//NOTAPE DD DUMMY
```

The above JCL prevents moving any data sets.

2. Issue the following control statements to delete (scratch and uncatalog) all data sets not referred to in the last year:

```
DUMP INDD(VOL111) OUTDD(NOTAPE) -
  DATASET(BY(REFDT, LE, *, -366)) -
   DELETE PURGE
```

3. Issue the following control statements to delete all expired data sets:

```
DUMP INDD(VOL111) OUTDD(NOTAPE) -
DATASET(INCLUDE(**) -
BY(EXPDT,LT,*)) -
DELETE
```

**Note:** You can modify the above example to apply to VSAM and multivolume data sets by omitting the INDD statement or by specifying LOGINDD. This JCL results in a logical data set dump operation.

- 4. Issue the following control statements to delete uncataloged non-VSAM data sets.
  - For a physical data set dump:

```
DUMP DATASET(INCLUDE(**) -
BY((DSORG NE VSAM) -
(CATLG EQ NO))) -
INDDNAME(DASD1, DASD2) -
OUTDDNAME(TAPE) -
DELETE PURGE
```

**Note:** The DD named TAPE can be a DD dummy if a dump of the uncataloged data sets is not wanted. DASD1 and DASD2 identify the input volumes. Because a physical data set dump processes each volume in order one at a time, it can handle multiple, uncataloged, single-volume data sets with the same name when multiple input volumes are specified. It cannot handle a multivolume data set even if all the volumes on which it resides are specified as input volumes.

• For a logical data set dump:

```
DUMP DATASET(INCLUDE(**) -
BY((DSORG NE VSAM) -
(CATLG EQ NO))) -
LOGINDDNAME(DASD1,DASD2) -
OUTDDNAME(TAPE) -
DELETE PURGE
```

**Note:** The DD named TAPE can be a DD dummy if a dump of the uncataloged data sets is not wanted. DASD1 and DASD2 identify the input volumes. A logical data set dump cannot handle multiple, uncataloged data sets with the same name in the same job even when all the volumes on which they reside are specified as input volumes.

A logical dump can handle a legitimate multivolume uncataloged data set if all the volumes on which it resides are specified as input volumes and if there is no cataloged data set by the same name on the system.

# Combining data set extents

You can use the CONSOLIDATE command to consolidate the multi-extent data sets that reside on a single volume and are not excluded from data movement. For eligible data sets that consist of contiguous extents in sequential order, DFSMSdss consolidates data sets without extent relocation. Otherwise, DFSMSdss relocates eligible data set extents if contiguous free space exists on the volume to hold the extents.

The CONSOLIDATE command attempts to consolidate data set extents within a managed space of a volume and perform extent reduction for data sets that occupy multiple extents. When you process a volume with the CONSOLIDATE command, DFSMSdss searches each moveable data set. A data set that either is included or is not excluded from data movement is eligible for extent consolidation and extent reduction. For eligible data sets that consist of contiguous extents that are in sequential order, DFSMSdss consolidates without extent relocation. Otherwise, eligible data set extents are relocated if enough free space exists on the volume to combine two or more. When DFSMSdss has completed consolidation for all eligible data sets, or has executed the amount of time specified in the MAXTIME option, processing is quiesced.

For information about specifying the CONSOLIDATE command, refer toz/OS DFSMSdfp Storage Administration.

#### Note:

- 1. The process of combining data set extents can cause the free space to be more fragmented than it was before the operation began.
- 2. Data set extents are not moved between track-managed space and cylinder-managed space of an extended address volume during CONSOLIDATE processing.
- 3. Despite the fact that DFSMSdss might perform freespace defragmentation following the consolidation of data set extents, the fragmentation index might be higher following a CONSOLIDATE operation than before the operation began.

As an alternative to CONSOLIDATE, you can use the DUMP command with the DELETE and PURGE keywords to scratch and uncatalog the data sets from DASD after they are dumped. If you restore these data sets to the same DASD, allocation attempts to obtain the space for the entire data set. In general, if the DASD volume has sufficient contiguous unused space, DFSMSdss allocates space in one contiguous extent. If you do not specify ALLDATA and ALLEXCP for sequential and partitioned data sets, only used spaces are allocated.

**Attention:** Do not use this technique for unmovable data sets such as ABSTR allocated or indexed sequential data sets. DFSMSdss does not delete unmovable data sets and the volume might become more fragmented after combining data sets extents than it was before the operation began. If that happens, you might not be able to restore the data sets.

Use the following steps to dump and delete (scratch and uncatalog) all movable non-VSAM data sets, defragment volumes, and restore all movable non-VSAM data sets.

1. Enter these control statements to dump and delete all movable, single-volume, non-VSAM data sets:

```
DUMP INDD(DASD1) OUTDD(TAPE1) OPTIMIZE(3) -
  DATASET(BY((DSORG, NE, VSAM), (ALLOC, EQ, MOV), (MULTI, EQ, NO))) -
  DELETE PURGE
```

2. Enter this control statement to defragment the volume:

DEFRAG DDN(DASD1)

3. Enter these control statements to restore and catalog all dumped data sets:

```
RESTORE INDD(TAPE1) OUTDD(DASD1) -
DATASET(INCLUDE(**)) -
CATALOG
```

Enter this control statement to defragment the volume, and perform extent reduction if possible:

```
DEFRAG DDN(DASD1) CONSOLIDATE DDN(DASD1)
```

# Consolidating free space and extents on volumes

Because of the nature of allocation algorithms and the frequent creation, extension, and deletion of data sets, free space on DASD volumes becomes fragmented. This results in:

- Inefficient use of DASD storage space
- An increase in space-related abends (abnormal endings)
- · Performance degradation caused by excessive DASD arm movement
- An increase in the time required for functions that are related to direct access device space management (DADSM).

With the DEFRAG command, you can consolidate the free space on volumes and avoid this problem. The DEFRAG command relocates data set extents on a DASD volume to reduce or eliminate freespace fragmentation, and prints a report about free space and other volume statistics. Also, you can specify which data sets, if any, are to be excluded from data-set-extent relocation. Data set extents are not combined as a result of DEFRAG processing.

**Note:** Data set extents will not be moved between the track-managed space and cylinder-managed space of an extended address volume during DEFRAG processing.

### When to run DEFRAG and CONSOLIDATE functions

You can run DEFRAG and CONSOLIDATE functions on a volume at any time. However, these operations lock the VTOC (through the RESERVE macro) and the VVDS, if it exists on the volume. They also serialize on data sets through ENQ or dynamic allocation. These activities might cause excessive wait time for other jobs to update the VTOC. Therefore, times of low system activity are best for DEFRAG and CONSOLIDATE runs.

DFSMSdss erases the source location for every extent that is moved during the DEFRAG or CONSOLIDATE operation when you specify the ADMINISTRATOR keyword. This occurs even if the extent is not part of an erase-on-scratch data set.

DFSMSdss can use FlashCopy during a DEFRAG or CONSOLIDATE operation if the device is in an ESS that supports data set FlashCopy. FlashCopy is much faster than traditional data movement methods, especially when you are moving large amounts of data.

DFSMSdss can also use SnapShot to quickly move the data from the source location to the target location during a DEFRAG or CONSOLIDATE operation if the device is in a RAMAC Virtual Array. SnapShot is much faster than traditional methods of data movement, especially when moving large amounts of data.

### Designating FlashCopy usage

The FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword tells DFSMSdss how you want to use fast replication methods such as FlashCopy. The default is FASTREPLICATION(PREFERRED).

FASTREPLICATION(REQUIRED) specifies that DFSMSdss must use data set FlashCopy for the DEFRAG operation. If FlashCopy cannot be used for one of the following normal reasons, DFSMSdss issues informational message ADR946I and error message ADR938E, which indicates that the processing of the current extent failed. DEFRAG processing attempts to use FlashCopy to move the subsequent extents.

- The target tracks are already the source of a FlashCopy operation.
- The source tracks are already the target of a FlashCopy operation.
- The target tracks will exceed 12 relationships, which is the maximum relationships that are allowed for any source tracks.

If FlashCopy cannot be used for reasons other than the normal reasons, DFSMSdss issues message ADR945W and error message ADR938E, which indicates that the processing of the current extent failed. DFSMSdss terminates DEFRAG processing.

FASTREPLICATION(PREFERRED) specifies that DFSMSdss attempt to use data set FlashCopy before any other I/O method. If data set FlashCopy cannot be used for one of the normal reasons listed earlier, DFSMSdss issues message ADR946I and uses traditional I/O methods to move the current extent. DEFRAG processing attempts to use FlashCopy to move the subsequent extents. If FlashCopy cannot be used for reasons other than the normal reasons, DFSMSdss issues message ADR945W and uses traditional I/O methods to move the current extent and all the subsequent extents on the volume.

**NOTE:** The unexpected FlashCopy failures are logged in the LOGREC by services that DFSMSdss initiates to perform a FlashCopy operation. The normal FlashCopy reasons are not logged in the LOGREC.

FASTREPLICATION(NONE) specifies that DFSMSdss not attempt to use data set FlashCopy during the DEFRAG operation.

For more information about the FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword, refer to *z/OS DFSMSdfp Storage Administration*.

# Preserve Mirror FlashCopy

During DEFRAG and CONSOLIDATE processing, you can choose to allow the target volume of a FlashCopy operation to be a Peer-to-Peer Remote Copy (PPRC) primary device. When the tracks associated with the FlashCopy relationship are copied to the PPRC secondary device, the PPRC (Metro Mirror) pair goes into a duplex pending state, to ensure the integrity of the mirror between the local site and the remote site. When the FlashCopy operation completes, the PPRC SYNC volume pair returns to full duplex state.

IBM Remote Pair FlashCopy FlashCopy (also known as Preserve Mirror) mirrors the FlashCopy command that is issued at the local site, to the remote site. This allows FlashCopy operations to occur to PPRC primary volumes without affecting the PPRC duplex state.

When you specify the FCTOPPRCPrimary keyword on the DEFRAG and CONSOLIDATE command, you are requesting that DFSMSdss allows a PPPRC primary volume to become the target volume of the FlashCopy operation. You can specify the following sub-keywords to indicate whether the PPRCP mirror is allowed to go to duplex pending state if the volume of the FlashCopy operation is a metro mirror device. Use the following sub-keywords to indicate whether the device pair is allowed to go to duplex pending state if the target volume of the FlashCopy operation is a metro mirror primary device:

#### **PRESMIRREQ**

specifies that if the volume is a Metro Mirror Primary device, the pair must not go into a duplex pending state as the result of a FlashCopy operations.

#### PRESMIRPREF

specifies that if the volume is a Metro Mirror primary device, it would be preferable that the pair does not go into a duplex pending state as the result of a FlashCopy operation. However, if a Preserve Mirror operation cannot be accomplished, the FlashCopy operation is still to be performed.

#### PRESMIRNONE

specifies that Preserve Mirror operation is not to be done, even if all of the configuration requirements for a Preserve Mirror operation are met. If the volume specified is a Metro Mirror primary device, the pair is to go into a duplex pending state while the secondary device is updated with the tracks to be copied. PRESMIRONONE is the default if you specify FCTTOPPRCPrimary without a subkeyword.

**Note:** If the volume of FlashCopy operation is not a metro mirror primary volume, then the FCTOPPRCPrimary keyword has no effect on the FlashCopy operation.

For more information about Peer-to-Peer Remote Copy (PPRC) and metro mirror operation, refer to z/OS DFSMS Advanced Copy Services.

For more information about the FCTOPPRCPrimary keyword on the CONSOLIDATE and DEFRAG commands, refer to "CONSOLIDATE command for DFSMSdss" on page 283 and "DEFRAG command for DFSMSdss" on page 374.

# Determining why FlashCopy cannot be used

There may be times when you expect DFSMSdss to use FlashCopy to move the data but FlashCopy was not used. As far as you can tell, your volume meets all the criteria for data set FlashCopy use. Use the DEBUG(FRMSG(MINIMAL | SUMMARIZED | DETAILED)) keyword to help you resolve this situation. Include this keyword indicating the applicable fast replication message level (MIN, SUM, or DTL) in your DEFRAG command. The message level controls the type and amount of information that DFSMSdss provides.

DEBUG(FRMSG(MIN | SUM | DTL)) directs DFSMSdss to issue an informational message that indicates why data set FlashCopy was not used. When you specify FASTREPLICATION(REQUIRED), the informational message is issued in addition to the ADR938E message whether you have specified the DEBUG(FRMSG(MIN | SUM | DTL)) keyword or not.

For more information about the DEBUG(FRMSG(MIN | SUM | DTL)) keyword, refer toz/OS DFSMSdfp Storage Administration.

### Designating SnapShot usage

The FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword tells DFSMSdss how you want to use SnapShot. The default is FASTREPLICATION(PREFERRED).

FASTREPLICATION(REQUIRED) specifies that DFSMSdss must use SnapShot for the DEFRAG operation. If SnapShot cannot be used to move an extent DFSMSdss issues error message ADR938E, which indicates that the DEFRAG operation failed.

FASTREPLICATION(PREFERRED) specifies that DFSMSdss attempt to use SnapShot before any other I/O method. If SnapShot cannot be used, DFSMSdss uses traditional I/O methods to move the current extent and all the subsequent extents on the volume.

FASTREPLICATION(NONE) specifies that DFSMSdss not attempt to use SnapShot during the DEFRAG operation.

For more information about the FASTREPLICATION(REQUIRED | PREFERRED | NONE) keyword, refer to *z/OS DFSMSdfp Storage Administration*.

### Determining why SnapShot cannot be used

There may be times when you expect DFSMSdss to use SnapShot to move the data but SnapShot was not used. As far as you can tell, your volume meet all the criteria for SnapShot use. Use the DEBUG(FRMSG(MINIMAL | SUMMARIZED | DETAILED)) keyword to help you resolve this situation. Include this keyword to indicate the applicable fast replication message level (MIN, SUM, or DTL) in your DEFRAG command. The message level controls the type and amount of information that DFSMSdss provides.

DEBUG(FRMSG(MIN | SUM | DTL)) directs DFSMSdss to issue an informational message that indicates why SnapShot was not used. When you specify FASTREPLICATION(REQUIRED), the informational message is issued in addition to the ADR938E message whether you have specified the DEBUG(FRMSG(MIN | SUM | DTL)) keyword or not.

For more information about the DEBUG(FRMSG(MIN | SUM | DTL)) keyword, refer toz/OS DFSMSdfp Storage Administration.

# Data sets excluded from DEFRAG or CONSOLIDATE processing

DFSMSdss automatically excludes and does not relocate the following types of data sets in a DEFRAG or CONSOLIDATE operation:

- User-specified data sets (EXCLUDE)
- Data sets that do not satisfy all BY criteria
- Indexed sequential data sets
- VSAM data sets not cataloged in an integrated catalog facility catalog
- Key range VSAM data sets
- Catalogs (system and user)
- The VTOC index data set

- RACF control data sets (any data set with a name in the form SYS1.RACF\*.\*\*)
- Page, swap, and SYS1.STGINDEX data sets
- VSAM volume data sets (VVDS)
- Unmovable data sets
- · Data sets allocated by absolute track
- Data sets that it cannot serialize for exclusive access
- VSAM data sets that have Record Level Sharing (RLS) information associated with them (only the first extent of this type of data set is excluded from the DEFRAG operation).
- For CONSOLIDATE operation, user specified data sets (do not satisfy INCLUDE criteria).

Because the DEFRAG and CONSOLIDATE functions do not relocate these data sets, the effectiveness of a DEFRAG and CONSOLIDATE run is affected by their presence.

Place the following data sets in the EXCLUDE list if they are present on the volume being defragmented:

- 1. If you plan to defragment a volume containing the active RACF database, you must place the RACF database data sets in the EXCLUDE list.
- 2. Any data that has been defined as a retained DLF object for use with Hiperbatch.

Note: Exclude system data sets that are opened and are being accessed without an enqueue.

### **DEFRAG** options

You can use the following keywords to make more efficient use of the DEFRAG command:

#### **DYNALLOC**

Uses dynamic allocation to serialize the use of data sets, rather than enqueue. This method does not always provide cross-system serialization.

#### FRAGI(n)

Performs a DEFRAG operation only if the fragmentation index is more than n.

#### MAXMOVE(n,p)

Stops the DEFRAG run when n contiguous free tracks are assembled. If ncontiguous free tracks already exist, DEFRAG processing attempts to further reduce the fragmentation of the volume, but no more than *n* tracks can be relocated. If more than n tracks must be relocated, DFSMSdss does not perform the DEFRAG request.

- The number of free tracks that DFSMSdss is to try to assemble in a contiguous area.
- The number of passes DFSMSdss is to make in attempt to assemble p the tracks.

### MAXTIME(nummins)

Stops the DEFRAG operation after the number of minutes specified has passed. This allows you to control the amount of time that the operation can run. MAXTIME is checked after each data set is prosessed. When the MAXTIME value is reached, the DEFRAG function ends.

#### nummins

Specifies number of minutes a DEFRAG operation can run.

#### MMOVPCT(n,p)

Stops the DEFRAG operation when n% contiguous tracks on the volume are assembled as free. If n% contiguous tracks already exist as free tracks, the DEFRAG function tries to further reduce the fragmentation of the volume but no more than n% tracks are relocated. If more than n% tracks must be relocated, no DEFRAG is performed.

- The percentage of tracks on the volume that DFSMSdss is to try to n assemble as free tracks in a contiguous area.
- The number of passes DFSMSdss is to make in attempting to p assemble the tracks.

#### **PASSDelay**

Specifies the time delay between the passes (p) specified in MAXMOVE(n,p) or MMOVPCT(n,p) to allow access to the volume between passes.

#### **VERSION1**

Specifies which version of DEFRAG is executed. During DEFRAG operations, you might want to execute the pre-z/OS V1R10 version of DFSMSdss DEFRAG. VERSION1 only supports volumes that are 65,520 cylinders or less. Any new function added to DEFRAG with z/OS V1R10 or later is not available.

#### WAIT(s,r)

If the data set is unavailable, wait s seconds before retrying to obtain control of it and retry only *r* times.

To determine the fragmentation index of a volume without actually performing the DEFRAG operation, code the NORUN parameter on the EXEC statement in your JCL. In addition to the fragmentation index, the NORUN parameter lists the number of free cylinders, the number of free tracks, the number of free extents, the largest free extent size, and the percentage of free space on the volume. A map of the volume with the CCHH location of each data set or free space (in ascending order from cylinder 0, track 0) is also issued.

#### General hints

- The MMOVPCT keyword is recommended over MAXMOVE when running DEFRAG on an extended address volume.
- To have the DEFRAG function perform in the shortest period of time, or to create the largest single freespace extent, perform only the first pass. Do so by coding the MAXMOVE(n) parameter using a very high value for n, or code the MMOVPCT(n) parameter using a high percentage amount. When the value is higher than what the DEFRAG function can assemble, the process stops at the end of the first pass. For example:

DEFRAG DYNAM(388002) MAXMOVE(9999)

or

DEFRAG DYNAM(388002) MMOVPCT(75)

• Experimenting with the DEFRAG FRAGI and MAXMOVE or MMOVPCT parameters will allow you to compare results when you use DASD with different fragmentation characteristics. The fragmentation index that can be specified by the DEFRAG options represents a number between 0 and 1 and can be one to three digits long. FRAGI(333) represents 0.333 and FRAGI(3) represents 0.3. By default, MAXMOVE or MMOVPCT use FRAGI(3), which is the recommended value. To defragment DASD volume 388001, you can use the command, as follows:

DEFRAG DYNAM(388001) FRAGI(3)

### Serialization

The DEFRAG command serializes access to the VTOC. The DEFRAG command releases this serialization before it generates the ending statistics provided by message ADR213I. Therefore, the information in message ADR213I may not reflect the state of the volume at the completion of DFSMSdss processing because another job may allocate or delete data sets on the processed volume between the time the serialization is released and the ending statistics are obtained. The serialization scheme is described in *z/OS DFSMSdfp Storage Administration*.

The DEFRAG command does a RESERVE on the VTOC to serialize access to the VTOC. The DEFRAG command also serializes access to each data set before relocating the extent of a data set. The enqueue scheme used by the DEFRAG function ensures integrity on a single processor but does not ensure integrity for data sets on DASD shared between processors. This is due to the use of an ENQ scope of SYSTEM for the SYSDSN resource name. To ensure the integrity of data sets on a shared DASD, you must do one of the following:

- Vary the volume offline from all processors except the one on which DEFRAG runs. After the DEFRAG function finishes, you can vary the volume back online for the other processors.
- In either a JES2 or a JES3 environment, you can use multisystem GRS (or
  equivalent function) to convert the scope of all enqueues with a resource name
  of SYSDSN from SYSTEM to SYSTEMS by placing SYSDSN in the GRS SYSTEM
  INCLusion resource name list (RNL). This allows all systems in the GRS ring to
  be made aware of all SYSDSN enqueues. The default GRS System Inclusion RNL
  includes SYSDSN. However, ensure that this has not been changed on your
  system before using the DEFRAG command on a volume shared between two or
  more processors.

**Note:** GRS must not be used to convert the scope of any of DEFRAG function's SYSTEMS enqueues (including SYSVSAM) to SYSTEM by placing the resource names in the GRS RNL. GRS may, however, be used to convert DEFRAG function's RESERVE on SYSVTOC to a simple enqueue with a scope of SYSTEMS by including it in the GRS "RESERVE CONVERSION RNL". If you choose not to do this, you can avoid doing two global serializations on the volume's VTOC by placing SYSVTOC in the GRS Systems Exclusion RNL, thus changing RESERVE's global enqueue to a local enqueue. For the restrictions that apply to enqueues and dequeues, see *z/OS MVS Planning: Global Resource Serialization*. The DYNALLOC serialization mechanism of DFSMSdss does not solve all cross-system serialization problems. GRS (Global Resource Serialization) is recommended with shared DASD.

• If you are running on a system using JES2 and are not using multisystem GRS (or equivalent function), you can use DEFRAG function's BY filtering to

specifically include or exclude data sets from processing. Both creation date and last-referenced date criteria are needed to ensure that only those data sets that are not in use are selected for DEFRAG function processing. For example, if you choose to defragment a volume with typical TSO or batch data sets, you could select only those data sets that were created and referenced at least twenty-four hours previously, using a selection age of two days. Two days should be a minimum selection age because of the level of precision of the creation date.

In the following example, data set A.B.C is created two minutes before the DEFRAG function begins.

```
TIME OF DAY
               ACTION
    2359
                 Create data set A.B.C
    0001
                 Begin DEFRAG BY(LIST(CREDT LE *,-1)). Data set A.B.C is selected
                 because it has now been one day since creation
```

Because there is a date change between the two actions, A.B.C is selected for the DEFRAG operation.

Using a two-day delay enforces a convention that more than twenty-four hours must pass before a data set is eligible for DEFRAG. In an environment with TSO and batch data sets, the probability that one of these data sets will be open more than twenty-four hours is low. The following example uses a two-day delay to cause DEFRAG processing only for those data sets on volume SHARE3 that were created and referenced more than twenty-four hours previously and that are not temporary data sets.

```
DEFRAG BY(LIST((CREDT LE *,-2),(REFDT LE *,-2))) -
      EXCLUDE(LIST(SYS8*.T*.**)) DYNAM(SHARE3)
```

The two-day criterion is probably sufficient for TSO and batch type data sets. However, if there are applications that use the volumes being defragmented, consider setting the delay time to the maximum time that the application would have a data set open.

If you are running on a system using JES3 with MDS enabled and are not using multisystem GRS (or equivalent function), you can use the DEFRAG command DYNALLOC keyword to provide serialization for data sets on shared DASD.

Note: Not all data sets allocated within a JES3 environment are known to the global. The use of the DYNALLOC keyword does not provide cross-system serialization for these data sets.

- Allocation of existing (old) data sets whose names appear in the RESDSN and DYNALDSN lists are not protected by the DYNALLOC serialization mechanism of DFSMSdss. DEFRAG processing for these data sets can be prevented by placing their names (or filters for the names) in the EXCLUDE LIST for the DEFRAG command.
- New data sets created with nonspecific allocation (no volume serial supplied) are not protected by the DYNALLOC serialization mechanism of DFSMSdss. However, you can use BY filtering with the DEFRAG command to specifically include or exclude data sets from processing. In the following example, the DEFRAG function processes only those data sets on volume SHARE3 that were created more than two days before.

```
DEFRAG BY(LIST(CREDT,LT,*,-2)) DYNALLOC DYNAM(SHARE3)
```

You can also use the EXCLUDE parameter to avoid processing data sets that were created by long-running programs or subsystems more than twenty-four hours previously but that are still allocated. In the following example, if the newly created data sets are temporary, the DEFRAG operation processes only those data sets on volume SHARE3 that were created more than two days before and are not temporary data sets.

```
DEFRAG BY(LIST(CREDT,LT,*,-2)) -
EXCLUDE(LIST(SYS8*.T*.**)) DYNALLOC DYNAM(SHARE3)
```

You can ensure successful DEFRAG processing of volumes having a significant number of free or allocated extents by specifying appropriate SIZE and REGION parameters in the EXEC statement. If you receive a message that the region size is not large enough, specify a larger region size in the EXEC or JOB statement and rerun your job.

**Note:** During DEFRAG processing, a data set VTOC entry with the unique name "SYS1.DFDSS.DEFRAG.xxxxxxxx.volser.DUMMY" is allocated on the volume being defragmented. This data set is not cataloged but is automatically deleted after a successful run. If a job is canceled or abnormally ends, this data set remains on the volume. After the restart, DADSM functions might fail with message IEC602. To correct this problem or to delete the

"SYS1.DFDSS.DEFRAG.xxxxxxxx.volser.DUMMY" entry, rerun the DEFRAG function on the volume.

# Security considerations

For security purposes, the data set tracks used before the relocation are erased after relocation under these conditions:

- When the z/OS Security Server (RACF element) is installed and either:
- The data set was defined to RACF with the RACF ERASE option
- The VSAM data set has the ERASE attribute
- The data set is password protected. (In this case, if the data set is also defined to RACF, the RACF ERASE option is taken. Table 12 on page 164 provides more detail.)

Table 12. Data Set Erase Table for DEFRAG with z/OS Security Server (RACF element).

	Password Protected	Defined ERASE	RACF Protected	Erased on Scratch
User Install Exit=ERASE (default)	No	No	No	No
	Yes	No	No	Yes
		Yes	No	Yes
	No	No	Yes (=ERASE)	Yes
	No	No	Yes (=NOERASE)	No
	No	Yes	Yes (=ERASE)	Yes
	No	Yes	Yes (=NOERASE)	Yes
	Yes	Yes	Yes (=ERASE)	Yes
	Yes	Yes	Yes (=NOERASE)	Yes
User Install Exit=NOERASE	No	No	No	No

Note: The catalog entry contains the ERASE attribute specified when the data set was defined (VSAM only).

The data set tracks that were used before the relocation are also erased after relocation if you have specified the ADMINISTRATOR keyword. This occurs whether the tracks are part of the erase-on-scratch data set or not.

You can prevent the tracks from being erased by using the installation options exit routine.

The DEFRAG function does not relocate protected data sets unless:

- You have RACF DASDVOL update access to the volume.
- You have RACF DATASET read access to the data sets on the volume.
- You specify the read or update password for password-protected data sets, or the Installation Authorization Exit Routine supplied with DFSMSdss is changed to allow relocation of protected data sets.

When RACF DASDVOL class is active and a profile exists for the volume, a DASDVOL authorization failure causes the DEFRAG task to abend with a system code 913. This happens regardless of RACF data set access authority.

For more information about the installation options exit routine, refer to z/OSDFSMS Installation Exits.

# Maximizing track utilization by reblocking data sets

DFSMSdss provides a REBLOCK keyword that allows users to maximize the track usage by data sets during copy and restore processing. When REBLOCK is specified on a fully or partially qualified name of a sequential or partitioned data set during copy or restore processing, DFSMSdss will choose an optimal block size for the data set and the device. However, the installation reblock exit can specify that a different block size be used (except for partitioned load modules during copy operations).

REBLOCK is ignored for:

- Unmovable data sets (unmovable attribute in the DSORG field in the VTOC
- · Data sets with record format of U (except for partitioned load modules during copy operations), V, VB, VBS, or F
- Partitioned data sets with note lists (except for partitioned load modules during copy operations)
- Partitioned data sets that are also specified in the NOPACKING keyword

Partitioned load modules can be reblocked in copy operations, even if they have note lists.

The reblockable indicator in the data set's VTOC entry also determines whether a data set is to be reblocked. When the indicator is on, the data set is always reblocked to a system determined, optimal block size, except when the data set:

- Is a partitioned data set that is also specified in the NOPACKING keyword
- Is an unmovable data set
- · Has a record format of V, VS, VBS, or F

The installation reblock exit is not called if the reblockable indicator is ON.

A PDSE being converted to a PDS will always be reblocked except when the data set has a record format of V, VS, VBS, or F; or when the data set's record length is

For more information about the installation reblock exit routine, refer to z/OSDFSMS Installation Exits.

# Chapter 10. Diagnosing problems in DFSMSdss operations

You might one day experience a problem with DFSMSdss operations that will cause you to contact IBM Service. They will ask you to describe the problem to them so that they might help solve it.

This topic explains how you can diagnose the problem by performing the following actions:

- Systematically develop a set of keywords that describe a DFSMSdss program failure.
- Describe the program failure to the IBM representative by using the keywords.

A keyword is an agreed-upon word or abbreviation that is used to describe a single aspect of a program failure.

In general, use the following procedure as a guide to help you find a resolution to a program failure:

- 1. Select your set of keywords.
- 2. Use the keywords to search the ServiceLink function within IBMLink.
- 3. Determine whether an authorized program analysis report (APAR) has been previously recorded for the failure. A description of the problem and usually a solution (designated by an APAR number) is provided when there is a match to your set of keywords.
  - An APAR is a record of a product operation discrepancy. APAR records are maintained in the IBM Software Support Facility (SSF) database.
- 4. Use the keywords to describe the program failure when you contact IBM for assistance.

The following sections provide more information about diagnosing and reporting problems:

- "Determining the source of the failure: DFSMSdfp, DFSMSdss, or DFSMShsm"
- "Using keywords to identify the problem" on page 168
- "Using the IBM Support Center" on page 176.

# Determining the source of the failure: DFSMSdfp, DFSMSdss, or DFSMShsm

The interactive storage management facility (ISMF) component of DFSMSdfp provides an interactive interface to DFSMSdss and DFSMShsm. Try to determine where the error occurred. Examine the content of the error message and the error logs. It is likely that the error has occurred either in DFSMSdss or in the interface to ISMF if you were performing one of the following functions:

**BUILDSA** 

**CGCREATED** 

**COMPRESS** 

**CONSOLIDATE** 

**CONVERTV** 

**COPY** 

COPYDUMP

**DEFRAG** 

**DUMP** 

**PRINT** 

**RELEASE** 

RESTORE.

If the failure occurred while you were using a function that does not appear in the list, it is possible the failure occurred in either DFSMSdfp or in the ISMF interface to DFSMShsm.

ISMF also uses the functions provided by the DFSMSdfp common services component, which consists of the following three routines:

- · Common filter services
- · DASD calculation services
- · Device information services.

To begin the diagnostic procedure for a DFSMSdss failure, refer to "Using keywords to identify the problem."

For information about the DFSMSdss dump data set, refer to Chapter 13, "Format of the DFSMSdss dump data set," on page 197.

For information about the DFSMSdss patch area, refer to Chapter 21, "Data integrity—serialization," on page 561.

For information about diagnosing DFSMSdfp function failures, refer to z/OS DFSMSdfp Diagnosis.

For information about diagnosing DFSMShsm function failures, refer to z/OS DFSMShsm Diagnosis.

# Using keywords to identify the problem

This topic explains the keywords and their relation to the full set of keywords used in describing a DFSMSdss program failure.

Keywords are made up of the following categories:

- Component identification
- · Release-level
- · Type-of-failure
- Function
- Module
- · Maintenance-level.

Searching SSF or the early warning system (EWS) with only the first keyword (the DFSMSdss component identifier) will detect all reported problems for the entire program product. Each keyword that you add to the search argument, however, makes the search more specific, reducing the number of problem descriptions to be considered. In some cases, a search can locate a correction for a problem with less than a full set of keywords. If for some reason it is difficult to determine a particular keyword, you can omit that keyword.

### Component identification keyword

The component identification keyword is the first keyword in a set. Use this keyword when you suspect that DFSMSdss is the failing component.

**Note:** If you are using the ISMF panels for DFSMSdss, exit this procedure and continue your diagnosis using the *z*/*OS DFSMSdfp Diagnosis*.

Example: 5695DF175

**Procedure:** The component identification number for DFSMSdss is **5695DF175**; see "Release-level keyword."

### Release-level keyword

Using this keyword to identify the release level of DFSMSdss is optional in the SSF or EWS search argument. However, it is required in an APAR.

Example: RA10

**Procedure:** The keyword for z/OS V1R10 DFSMSdss is **RA10**; see "Type-of-failure and function keywords."

# Type-of-failure and function keywords

Select one keyword from Table 13 that best describes the type of failure and see the topic indicated. Most type-of-failure keywords are accompanied by a function keyword. The function keywords are described in the type-of-failure sections. If you are not certain which of two keywords to use for the type of failure, use the one that appears first on your display screen.

Table 13. Summary of Type-of-Failure Keywords

Keyword	Type of Failure	Topic
ABENDxxx	DFSMSdss ends abnormally because of a system-detected error.  Note: The ABENDxxx keyword does not apply to the DFSMSdss stand-alone restore program.	"ABENDxxx"
MSGADRnnnt	An error is related to a DFSMSdss message.	"MSGADRnnnt" on page 170
WAIT	The program does not seem to be doing anything.	"WAIT" on page 171
LOOP	The program is doing something repetitively.	"LOOP" on page 172
INCORROUT	Output from the program is incorrect or missing.	"INCORROUT" on page 172
DOC	Documentation of the program is in error.	"DOC" on page 173
PERFM	Program performance is degraded.	"PERFM" on page 174

#### **ABEND***xxx*

Use this procedure when DFSMSdss ends abnormally. However, if the abend is user abend "0001," skip this topic, and go directly to "MSGADRnnnt" on page 170.

**Note:** Because there are no abends in the DFSMSdss stand-alone restore program, this procedure does not apply to it.

**Example:** 5695DF175 RA10ABENDxxx function

**Procedure:** To determine the keywords for type-of-failure and function, follow these instructions:

1. Replace the xxx in the ABENDxxx keyword with the abend code from either the ending message or the abend dump.

2. Find the function keyword:

Note: When a DFSMSdss task abends, the DFSMSdss scheduler module writes message ADR013I (TASK ABENDED) to the SYSPRINT (or its equivalent) data set. If you do not receive the ADR013I message, use function keyword CNTRL and refer to "Module keyword" on page 174.

a. Record the relative task identifier. The number in parentheses (ttt) that immediately follows the message identifier is the relative task identifier. For example:

```
ADR013I (ttt)-mmmmm(yy), date_and_time TASK ABENDED . . .
```

b. Check prior messages for an ADR101I message with a task identifier that matches the one that you found in step 2a. For example:

```
ADR101I (ttt)-mmmmm(yy), TASKID xxx HAS BEEN ASSIGNED TO COMMAND 'command'
```

The command that is identified in this message is the function that is executing at the time of the abend. This command name is the function keyword.

You have finished when you have identified the function keyword for the ABENDxxx type-of-failure keyword. Refer to "Module keyword" on page 174 to identify the maintenance level of the module that failed.

#### **MSGADR**nnnt

Use this procedure for any of the following conditions:

- A DFSMSdss message indicates that an internal program error has occurred (for example, message ADR799E, "AN UNEXPECTED ERROR HAS OCCURRED").
- A message is not issued when it should have been.
- · A message is issued when it should not have been.

Example: 5695DF175 RA10 MSGADR nnnt ADR mmmmm OC yy

Procedure: To determine the keywords for type-of-failure, module, and occurrence code, follow these instructions:

1. Replace the *nnnt* in **MSGADR***nnnt* with the message number and severity code. For example, if the message is ADR503A, the MSGADRnnnt type-of-failure keyword is MSGADR503A.

2. Replace the *mmmmm* in *ADRmmmmm* with the module identifier from the message (mmmmm in the following example).

```
ADR013I (ttt)-mmmmm(yy), date and time TASK ABENDED . . .
```

The number in the parentheses (ttt) immediately following the message identifier is the relative task identifier. The resulting module keyword is ADRmmmmm.

Note: For the DFSMSdss stand-alone restore program, the module keyword is always ADRDMPRS. If you select this keyword, see "Maintenance-level keyword" on page 176.

3. Replace the yy in **OC**yy with the two-character occurrence code, which is in parentheses following the module identifier in the message. For example, you could have OC01.

You have finished when you have identified the MSGADRnnnt type-of-failure keyword, the module keyword, and the occurrence code for the MSGADRnnnt type-of-failure. To identify the maintenance level of the module, refer to "Maintenance-level keyword" on page 176.

#### WAIT

Use this procedure when DFSMSdss suspends activity while it is waiting for a condition to be satisfied, yet it has not issued a message to tell why it is waiting. Ensure that the wait is not caused by your having specified WAIT subparameters that are too large.

Example: 5695DF175 RA10 WAIT function

**Procedure:** To determine the keywords for type-of-failure and function, follow these instructions:

- 1. Use WAIT as the type-of-failure keyword if all DFSMSdss tasks were in a WAIT
- 2. Obtain an abend dump of the WAIT state. Ensure that the job control language (JCL) has a SYSABEND, SYSMDUMP, or SYSMDUMP data definition (DD) statement.

- 3. Follow these steps to find the function keyword:
  - a. Record the relative task identifier. The relative task identifier is the number in parentheses (ttt) that immediately follows the message identifier in message ADR006I. Message ADR006I is printed when a DFSMSdss task begins. For example:
    - ADR006I (ttt)-mmmm(yy), date\_and\_time EXECUTION BEGINS
  - b. Locate the tasks that are active (message ADR006I without a matching ADR013I). Message ADR013I is printed when a function ends. For example: ADR013I (ttt)-mmmm(yy), date and time TASK COMPLETED
  - c. Use CNTRL as the function keyword if no tasks are active, or if more than one function is active. See "Module keyword" on page 174.
  - d. Check prior messages for an ADR101I message with a task identifier that matches the one that you found in step 3a. For example: ADR101I (ttt)-mmmmm(yy), TASKID xxx HAS BEEN ASSIGNED TO COMMAND 'command'

The command identified in this message is the function that is executing at the time that the wait started. This function name is the function keyword.

You have finished when you have identified the function keyword for the WAIT type-of-failure. To identify the maintenance level of the module that failed, refer to

"Module keyword" on page 174. Guideline: For the DFSMSdss stand-alone restore program, the module keyword is

always ADRDMPRS. If you select this keyword, see "Maintenance-level keyword" on page 176.

#### LOOP

Use this procedure when some part of the program repeats endlessly. If a message repeats endlessly, use the MSGADRnnnt keyword.

Example: 5695DF175 RA10 LOOP function

Procedure: To determine the keywords for type-of-failure and function, follow these instructions:

- 1. Use LOOP as the type-of-failure keyword if a DFSMSdss task was in a loop.
- 2. Obtain an abend dump of the LOOP state. Ensure that the JCL has a SYSABEND, SYSMDUMP, or SYSUDUMP DD statement.

- 3. Follow these steps to find the function keyword:
  - a. Record the relative task identifier. Message ADR006I is printed when a DFSMSdss task begins. The number in parentheses (ttt) immediately following the message identifier is the relative task identifier. For example: ADR006I (ttt)-mmmmm(yy), date and time EXECUTION BEGINS
  - b. Locate the tasks that are active (message ADR006I without a matching ADR013I). Message ADR013I is printed when a function ends. For example: ADR013I (ttt)-mmmmm(yy), date and time TASK COMPLETED
  - c. Use CNTRL as the function keyword if no tasks are active; see "Module keyword" on page 174.
  - d. Analyze the program further to determine which task has failed if more than one function is active. You can best accomplish this by examining each function task in the dump.
  - e. Check prior messages for an ADR101I message with a task identifier that matches the one that you found in step 3a. For example: ADR101I (ttt)-mmmmm(yy), TASKID xxx HAS BEEN ASSIGNED TO COMMAND 'command'

The command that is identified in this message is the function that is executing at the time the loop began. This function name is the function keyword.

You have finished when you have identified the function keyword for the LOOP type-of-failure. To identify the maintenance level of the module that failed, refer to "Module keyword" on page 174.

Guideline: For the DFSMSdss stand-alone restore program, the module keyword is always ADRDMPRS. If you select this keyword, see "Maintenance-level keyword" on page 176.

#### INCORROUT

Use this procedure if you expect output but do not receive it, or if the output is not what you expected.

#### **Examples:**

5695DF175 RA10 INCORROUT MSGADR nnnt ADR mmmmmm OC yy function 5695DF175 RA10 INCORROUT function

**Procedure:** To determine the keywords for type-of-failure, module keyword, occurrence code, and function, follow these instructions:

- 1. Use INCORROUT as the type-of-failure keyword.
- 2. Perform steps 1 on page 170 through 3 on page 171 in "MSGADRnnnt" on page 170, if the output is in the form of an incorrect message, and then return to this procedure.
- 3. Use the name of the DFSMSdss function that you were using as the keyword. Choose from the following list:

**BUILDSA** 

**CGCREATED** 

**COMPRESS** 

**CONSOLIDATE** 

**CONVERTV** 

**COPY** 

**COPYDUMP** 

**DEFRAG** 

**DUMP** 

**PRINT** 

**RELEASE** 

**RESTORE** 

You have now finished obtaining the keywords for type-of-failure, module keyword, occurrence code, and function; see "Using the IBM Support Center" on page 176.

### DOC

Use this procedure when you encounter incorrect or missing information in a DFSMSdss publication. For a minor publication error, use the form for readers' comments at the back of the publication. If the error is serious and of general concern to other users, continue with the procedure described here.

Example: 5695DF175 RA10 DOC xxnnnnnnn

Procedure: To determine the keywords for type-of-failure and document number, follow these steps:

- 1. Use DOC as the type-of-failure keyword.
- 2. Specify the order number of the document after the DOC keyword, omitting the hyphens. If the suffix is one digit, precede it with a zero. For example, for document order number SC35-0423-09, specify the following: DOC SC35042309
- 3. Locate the page of the error in the document and prepare a description of the problem. If you submit an APAR, include this information in the error description.

You have now obtained the keywords for type-of-failure and document number; see "Using the IBM Support Center" on page 176.

### **PERFM**

Use this procedure if performance is less than expectations and the problem cannot be corrected by system tuning.

Example: 5695DF175 RA10 PERFM function

Procedure: To determine the keywords for type-of-failure and function, follow these instructions:

1. Use PERFM as the type-of-failure keyword.

2. Use the name of the function as the function keyword if the performance problem occurred during one of the following functions:

**BUILDSA** 

**CGCREATED** 

**COMPRESS** 

CONSOLIDATE

**CONVERTV** 

**COPY** 

**COPYDUMP** 

**DEFRAG** 

**DUMP** 

**PRINT** 

RELEASE

**RESTORE** 

You have now obtained the keywords for type-of-failure and function; see "Using the IBM Support Center" on page 176.

# Module keyword

This topic applies only to the ABENDxxx, WAIT, and LOOP type-of-failure keywords.

DFSMSdss uses subtasking to isolate functions; thus, a dump might contain a task and subtasks as follows:

- · A DFSMSdss scheduler task
- A subtask for the reader/interpreter
- Subtasks for the DFSMSdss functions (for example, COPY or DUMP)
- A subtask for managing SVC services
- A subtask for managing IGWFAMS
- · A subtask for attached utilities.

Each task has its own task control block (TCB) and request block (RB) chain in the dump. An explanation of the subtasks follows:

- The task for the scheduler is ADRDSSU, as indicated in the program request block/contents directory entry (PRB/CDE). Its normal state is waiting for the return from the EVENTS SVC (X'7D') in ADRDSSU.
- The subtask for the reader/interpreter is ADRRI01, as indicated in the PRB/CDE. Its normal state is waiting for the return from the WAIT SVC (X'01') in ADRRI01.

- The subtasks for the DFSMSdss functions are ADRBLDSA, ADRCGCR, ADRCPYD, ADRPRNT, ADREFRAG, ADRDDTFP, ADRDTDS, ADRDTDSC, ADRDDDS, ADRCMPRO, ADRRLSEO, ADRTDFP, ADRTDDS, or ADRKVOL, as indicated in the PRB/CDE.
- The subtask that manages the SVC services is ADRSVCD. Its normal state is waiting for return from the WAIT SVC (X'01') in ADRSVCD.
- The subtask that manages IGWFAMS is ADRATFMS. Its normal state is waiting for the return from the WAIT SVC (X'01') in ADRATFMS.
- The subtask that manages other attached utilities is ADRMUTIL. Its normal state is waiting for the return from the WAIT SVC (X'01') in ADRMUTIL.

#### **Procedure:** Perform the following.

1. Locate the failing task by comparing the task identifier in the task-related messages to the task identifier in the function blocks for the executing functions. The task identifier is in the third halfword in the function block for the function. The function block is addressed by register 1 at entry to the function. This register is in the first save area on the save area chain under the TCB for the function. The ID in the message is a decimal number; the identifier in the function block is a hexadecimal number.

If the function keyword is CNTRL, the failing task is either the scheduler or the reader/interpreter. If both are present, inspect the program status words (PSWs) for these tasks to determine whether one is not in its normal state, as described in this topic.

#### 2. Locate the active module.

Get the PSW for the failing task. This is usually found in the PRB and might not always be the error PSW identified at the beginning of the dump.

Starting at the address in the PSW, search backward through the dump for the module identifier. The identifier consists of the following two character strings (separated by from 20 to 80 bytes):

```
ADRxxxxx mm/dd/yyHDZ1A10 aparnum
```

. . ptfnum,yr.day,hh:mm:ss

where:

#### **ADR**xxxxx

Module name

#### mm/dd/yy

Maintenance date

#### HDZ1A10

FMID of the release

#### aparnum

Current APAR number or "NONE"

#### ptfnum

Current program temporary fix (PTF) number or "NONE"

yr.day Compile date

#### hh:mm:ss

Compile time

If the PSW does not point within a DFSMSdss module, use register 12 (base) or 14 (return) at the time of the error and repeat this search. You can usually find these registers in the first supervisor request block (SVRB) after the PRB for the failing task.

#### **Examples:**

- a. 5695DF175 RA10 ABEND xxx function module
- b. 5695DF175 RA10 WAIT function module
- c. 5695DF175 RA10 LOOP function module

3. If you already know the PTF number, see "Using the IBM Support Center." Otherwise, see "Maintenance-level keyword."

### Maintenance-level keyword

Use this keyword to identify the maintenance level of the module that failed.

**Procedure:** Perform the following.

- 1. Use the PTF number as the maintenance level keyword. The PTF number is found when you find the module identifier (see Step 2 on page 175 in "Module keyword" on page 174).
- 2. Use the following process to find the PTF number if it is not available as part of the module identifier:
  - a. If you are using preventive service tapes, you can identify the maintenance level of the last tape applied to the system.
  - b. Find the maintenance level of a module by listing the SMP/E control data set (CDS).
  - c. Find the name of the module that the previous steps identified as the cause of the problem, in the name column of the module entries.
  - d. Find the replacement module identifier (RMID) field in the entry for the module. The RMID field contains the PTF number that identifies the maintenance level of the module. For the entire maintenance history of this module (superzaps, user modifications, and so forth), a LIST CD MOD with the keyword XREF and the module name produces a SYSMOD history of this module.

You now have all the necessary information for an effective search of known problems in the Software Support Facility (SSF) database or EWS for APARs and PTFs. Contact the IBM Support Center; see "Using the IBM Support Center."

# Using the IBM Support Center

IBM Support Center personnel have access to several software support databases. They use these databases and the set of keywords that you provide as a search argument to help solve your program failure. Support Center personnel may help you improve the effectiveness of your search argument. If someone already reported the problem, the Support Center personnel review the recorded failure and provide you with a suggested method of corrective action.

The types of software support databases available to the IBM Support Center personnel include the following:

- Software support facility
- IBMLink/ServiceLink
- · Info/System

### Using the software support facility

The software support facility is an IBM online database that contains information about all authorized program analysis reports (APARs) and program temporary fixes (PTFs). IBM Support Center personnel have access to SSF and are responsible for using the set of keywords that you provide as a search argument. Support Center personnel may help you improve the effectiveness of your search argument. They can also retrieve the records of previously reported problems. These records describe the failure and the corrective actions taken.

### Using IBMLink/ServiceLink

IBMLink/ServiceLink is a set of online electronic services available to customers. Some of these services are available to you free of charge as a part of the SoftwareXcel basic contract. Some of these services are available for an additional fee as part of the optional SoftwareXcel Extended contract. Contact your local IBM marketing branch office for more information on SoftwareXcel contracts and services.

The following services are available to you under one of these contracts:

#### **SRCHSERVICE**

Online database of APAR and PTF information, with extensive search capability.

- **PSP** Preventive Service Planning information database. This database contains the latest information concerning the installation of IBM products, including the latest service recommendations.
- **SRD** Service Request and Delivery Facility. This facility provides a means for election ordering and delivery of corrective services, including PTFs and APARS.
- **ASAP** Automatic Software Alert Process. This facility alerts the user when critical service information becomes available on a list of products that are selected by the user.
- ETR Electronic Technical Response. The user may electronically report problems and ask appropriate technical questions about IBM products through this facility. The ETR answers questions and problem reports by utilizing electronic responses. Optionally, you can request to talk to an IBM representative about your problem report. Submit nondefect-related, nontechnical questions to the question and answer (Q&A) queue in Canada on a severity 3, priority 3 basis.
- AST Automatic Status Tracking. This facility allows the user to request notification when the status of a user-selected APAR or PTF changes, or
- VPL View Program Listings. This is an online database of module listings for non-object code only (OCO) modules distributed through PTFs.

# Info/System

Info/System is an interactive online database information retrieval program product. It is available primarily for use by customers with the companion database feature, Info/MVS. The database divides itself into several logical files of related or similar information, such as IBM ServiceLink.

# **Chapter 11. ACS routine information**

This topic contains general-use Programming Interface and Associated Guidance Information.

This topic lists the variables you can use for automatic class selection (ACS) routines during DFSMSdss copy, restore, and CONVERTV operations, and describes the processing of ACS routines. This information is provided for guidance purposes only. It is not associated with any interface provided by DFSMSdss.

Messages generated by ACS routines are not printed by DFSMSdss unless the ACS routine returns a non-zero return code.

**Related reading:** For information about writing ACS routines, see Chapter 22, "Application programming interface," on page 577.

# ACS variables available during Copy function

When automatic class selection (ACS) is invoked during a DFSMSdss copy function, the following variables, as shown in Table 14 are passed to the ACS routines.

Table 14. Variables Passed to ACS Routines during DFSMSdss Copy Function. The following variables are not available to the storage group ACS routine: &ACCT\_JOB, &ACCT\_STEP, &DD, &JOB, &PGM, and &XMODE.

Variable Name	Description	
&ACCT_JOB	Accounting information from the JOB statement.	
&ACCT_STEP	Accounting information on the EXEC statement.	
&ACSENVIR	Environment in which ACS was invoked. Set to 'ALLOC' unless an application has specified an ACS environment in EI22ACSEN.	
&ALLVOL	Output volume serial numbers. References the same volume list as &ANYVOL, but when used in a comparison, returns true only if all volume serial numbers satisfy the condition. &ALLVOL is not available to the storage group ACS routine when VOLCOUNT(ANY) is specified.	
&ANYVOL	Output volume serial numbers. References the same volume list as &ALLVOL, but when used in a comparison, returns true if any volume serial numbers satisfy the condition. &ANYVOL is not available to the storage group ACS routine when VOLCOUNT(ANY) is specified.	
&APPLIC	Application identifier associated with the data set (available only if the RACF component of z/OS Security Server is installed).	
ⅅ	DDNAME	
&DEF_DATACLAS	Default data class name (available only if the RACF component of z/OS Security Server is installed).	
&DEF_MGMTCLAS	Default management class name (available only if the RACF component of z/OS Security Server is installed).	

Table 14. Variables Passed to ACS Routines during DFSMSdss Copy Function (continued). The following variables are not available to the storage group ACS routine: &ACCT\_JOB, &ACCT\_STEP, &DD, &JOB, &PGM, and &XMODE.

Variable Name	Description	
&DEF_STORCLAS	Default storage class name (available only if the RACF component of z/OS Security Server is installed).	
&DSN	Data set name.	
&DSNTYPE	Data set name type (for example: EXT, HFS, LIBRARY, PDS, or null).	
&DSORG	Data set organization.	
&DSOWNER	Owner or group considered to be the data set owner (available only if the RACF component of z/OS Security Server is installed).	
&DSTYPE	Data set type (for example, GDS, PERM, or TEMP).	
&EXPDT	Expiration date.	
&FLASHCPY	Data set allocated to FlashCopy storage group	
&GROUP	Group identifier from the JOB statement.	
&HLQ	High-level qualifier of the data set name.	
&JOB	Job name, started task name, or TSO user ID from the JOB statement.	
&LLQ	Low-level qualifier of the data set name.	
&MAXSIZE	Maximum size of data set in kilobytes. For non-VSAM data sets, the primary value plus 15 secondary extents, or 122 secondary extents for PDSE and extended-format sequential data sets. For VSAM data sets, the primary value plus 122 secondary extents. See "Using SIZE and MAXSIZE variables" on page 182 for more information about this value.	
&NQUAL	Number of qualifiers in the data set name.	
&NVOL	Number of output volumes specified by the user.	
&PGM	Program name from the EXEC card.	
&RECORG	Data set record organization.	
&RETPD	Retention period.	
&SIZE	Size of the data set in kilobytes. See "Using SIZE and MAXSIZE variables" on page 182 for more information about this value.	
&UNIT	Actual unit name (not esoteric names).	
&USER	User ID from the JOB statement or the user ID propagated from the environment when a security product, such as z/OS Security Server, is active.	
&XMODE	Execution mode (for example, TSO, BATCH, or TASK).	

# ACS variables available during RESTORE and CONVERTV processing

When ACS is invoked during DFSMSdss RESTORE or CONVERTV processing, the variables shown in Table 15 are passed to the ACS routines.

Table 15. Variables Passed to ACS Routines during DFSMSdss Restore and CONVERTV Processing

Variable Name	Description
&ACSENVIR	Environment in which ACS was invoked. Set to 'RECOVER' for RESTORE unless an application has specified an ACS environment in EI22ACSEN. Set to 'CONVERT' for CONVERTV.
&ALLVOL	For restore processing, the output volume serial numbers. For CONVERTV processing, the volumes on which the data set resides. References the same volume list as &ANYVOL, but when used in a comparison, returns true only if all volume serial numbers satisfy the condition. &ALLVOL is not available to the storage group ACS routine when VOLCOUNT(ANY) is specified.
&ANYVOL	For restore processing, the output volume serial numbers. For CONVERTV processing, the volumes on which the data set resides. References the same volume list as &ALLVOL, but when used in a comparison, returns true if any volume serial numbers satisfy the condition. &ANYVOL is not available to the storage group ACS routine when VOLCOUNT(ANY) is specified.
&APPLIC	Application identifier associated with the data set (available only if the RACF component of $z/OS$ Security Server is installed).
&DEF_DATACLAS	Default data class name (available only if the RACF component of z/OS Security Server is installed).
&DEF_MGMTCLAS	Default management class name (available only if the RACF component of z/OS Security Server is installed).
&DEF_STORCLAS	Default storage class name (available only if the RACF component of z/OS Security Server is installed).
&DSN	Data set name.
&DSNTYPE	Data set name type (for example: EXT, HFS, LIBRARY, PDS, or null).
&DSORG	Data set organization.
&DSOWNER	Owner or group that is considered to be the data set owner (available only if the RACF component of z/OS Security Server is installed).
&DSTYPE	Data set type (for example, GDS, PERM, or TEMP).
&EXPDT	Expiration date.
&GROUP	Group identifier from the JOB statement. (This variable is passed to ACS routines during processing of RESTORE only, not CONVERTV.)
&HLQ	High-level qualifier of the data set name.
&LLQ	Low-level qualifier of the data set name.
&MAXSIZE	Maximum size of data set in kilobytes. For non-VSAM data sets, the primary value plus 15 secondary extents, or 122 secondary extents for PDSE and extended-format sequential data sets. For VSAM data sets, the primary value plus 122 secondary extents. See "Using SIZE and MAXSIZE variables" on page 182 for more
	information about this value.

Table 15. Variables Passed to ACS Routines during DFSMSdss Restore and CONVERTV Processing (continued)

Variable Name	Description
&NVOL	For restore processing, number of volumes specified by the user. For CONVERTV processing, the number of volumes (including candidate volumes) on which the data set resides.
&RECORG	Data set record organization.
&RETPD	Retention period.
&SIZE	Size of the data set in kilobytes. See "Using SIZE and MAXSIZE variables" for more information about this value.
&UNIT	Actual unit name (not esoteric names).
&USER	User ID from the JOB statement or the user ID propagated from the environment when a security product, such as z/OS Security Server, is active. (This variable is passed to ACS routines during processing of RESTORE only, not CONVERTV.)

### Using SIZE and MAXSIZE variables

The values for SIZE and MAXSIZE (and the space units the values represent) depend on the type of allocation of the data set. For all VSAM data sets, and non-VSAM data sets allocated in device dependent units (tracks or cylinders), the value represents the number of kilobytes using the maximum block size of the device. For example, the maximum block size for a 3390 is 56664. For all other non-VSAM data sets allocated in device independent units (blocks, average block, AVGREC=U, AVGREC=K, AVGREC=M), the value represents the number of data kilobytes (based on the average block size, specified block size, or 4096 if no block size is available).

The values DFSMSdss computes for SIZE and MAXSIZE may not match that of the original allocation. The values may be different if the device type on which the data set now resides is not the same as either of the following:

- The device type used at allocation, or
- The default device type in the CDS when the original allocation was done

DFSMSdss calculates the value based on the device type where the data set currently resides. DFSMSdss has no way of "knowing" what device type was specified or used for the original allocation.

DFSMSdss calculates SIZE and MAXSIZE variables as follows:

- For **PDS** and **PDSE** data sets The values DFSMSdss computes may be different from those computed by SMS because SMS adds space for the directory. Also, DFSMSdss computes MAXSIZE for PDSE data sets based on 122 secondary extents.
- For VSAM data sets DFSMSdss computes the SIZE and MAXSIZE for key-sequenced data sets (KSDS) from the current size and space values of the data component. The index component size is not included. Also, DFSMSdss computes MAXSIZE for VSAM data sets based on 122 secondary extents.
- For extended-format sequential data sets DFSMSdss computes MAXSIZE for extended-format sequential data sets based on 122 secondary extents.
- For data sets allocated with AVGREC=U, K, or M The size values computed during the initial allocation used the specified average block value. Since the average block size value is not stored anywhere and was only available during

the initial allocation, DFSMSdss uses the DCB BLKSIZE value. If the DCB BLKSIZE value is not the same as the average block size value, the values computed for SIZE and MAXSIZE may be different from those computed at initial allocation.

# Chapter 12. Dumping and restoring Linux for System z partitions and volumes

You can include Linux volumes in an existing z/OS backup solution that uses DFSMSdss. If so, you can use DFSMSdss to dump Linux volumes to tape or to a *direct access storage device* (or *DASD*).

This backup solution is intended for the following environments:

- A z/OS-centric environment with z/OS running in several logical partitions (LPARs), in tandem with a few dozen Linux servers running within the virtual image facility (VIF)
- A Linux-focused environment with VM running in BASIC or LPAR mode. Hundreds of Linux guests and one or more z/OS images can perform the DFSMSdss processing.

In this section, the following topics describe how to use DFSMSdss to dump and restore Linux for System z partitions and volumes, and also how to use a z/OS system to back-up Linux partitions that are attached to a Linux for System z image:

- "Preparing to work with Linux volumes"
- "Backing up a Linux volume with partitions" on page 187
- "Using DFSMSdss dump and restore commands" on page 188.

This information is intended for storage administrators who are familiar with Linux for System z. To do this work, you require root authority on Linux and must be authorized to run DFSMSdss batch jobs through RACF, or a functionally equivalent security product.

#### Note:

The examples in this topic were tested with:

- DFSMSdss Release 10
- OS/390<sup>®</sup> Version 2 Release 10
- z/OS Version 1 Release 1.

The procedures might not work with other versions of DFSMS.

# Preparing to work with Linux volumes

This topic describes the following requirements for using DFSMSdss to dump and restore Linux for System z partitions and volumes.

# Understanding the hardware environment

An operating system can run on the processor in one of the following modes:

#### **BASIC**

A single operating system image that owns the entire processor or all processors.

**LPAR** Depending on the model, a processor can be divided into as many as 60 logical partitions, with each partition running its own operating system image.

#### VIRTUAL

IBM offers VM and VIF for Linux systems. Both VM and VIF are hypervisors (an operating system that allows other operating systems to run). VM supports hundreds to thousands of guests. Each guest produces its own operating system image. As an example, one guest using Linux, and another using z/OS, all on the same hardware.

### Choosing VOLSERs for Linux volumes

In a z/OS environment, DASD is divided into logical units known as volumes. You can define a volume to any size, up to a maximum size supported by z/OS environment.

Volumes are further divided into fixed-size tracks. The device's geometry determines the size of the track. Linux supports both the 3380 and 3390 track geometries. You can reference a volume by using a 16-bit device number, and a six-character volume serial number (known as the volser).

When choosing a volser for a volume, follow these rules:

- The volser is six characters long. z/OS accepts fewer than six characters for the volser, but Linux requires that volumes have a six character volser.
- The volser uses uppercase, alphanumeric characters (A-Z, 0-9), and special characters (\$, #, @).

### Formatting and partitioning Linux volumes

You must format and partition a volume before Linux can use it. Specifically, you must format the Linux volumes in the compatible disk layout (cdl) using dasdfmt version 1.0, and partition them using fdasd version 1.0.

This topic describes these steps in more detail:

- "Using dasdfmt to format a Linux volume"
- "Using fdasd to partition a Linux volume" on page 187.

### Using dasdfmt to format a Linux volume

The default disk layout for dasdfmt is cdl. Volumes formatted in the original Linux disk layout (ldl) are not compatible with z/OS, and as such, cannot be backed up by z/OS.

The following example shows how to format a disk with dasdfmt at address 0198, having a byte block size of 4096, and a volser of LNX200:

dasdfmt -n 198 -b 4096 -1 1nx200

The result should appear similar to the following screen:

```
Drive Geometry: 3339 Cylinders * 15 Heads = 50085 Tracks
I am going to format the device 198 in the following way:
   Device number of device : 0x198
   Major number of device : 94
   Minor number of device : 8
                         : yes
   Labelling device
   Disk lahel
                          : VOL1
   Disk identifier
                          : LNX200
   Extent start (trk no) : 0
                           : 50084
   Extent end (trk no)
   Compatible Disk Layout : yes
                          : 4096
   Blocksize
--->> ATTENTION! <<--- All data in the specified range of that device
will be lost. Type "yes" to continue, no will leave the disk untouched.
```

In the example, a 3339 cylinder volume is attached to Linux at address 198. The volser is LNX200, and its block size is 4096 bytes. Linux requires the volser to be six characters in length. The disk label, VOL1, indicates that z/OS can process the volume.

A classic Linux volume has a disk label of LNX1; z/OS cannot process a volume with this disk label.

### Using fdasd to partition a Linux volume

After you have formatted a volume with dasdfmt in the compatible disk layout, you must partition it before Linux can use it. Use the fdasd program to partition the volume.

The fdasd program is similar to the fdisk program that comes with the Linux version that runs on personal computers. One difference is that it creates partitions on extended count-key-data ( $ECKD^{TM}$ ) DASD instead of on hard drives. With fdasd, you can create up to three partitions on a volume and you can set the size of each partition. The partitions appear to z/OS as data sets.

When creating partitions with fdasd that you want to back-up with z/OS, observe the following rules:

- Create partitions by starting from the lowest possible track.
- Do not leave gaps between partitions.
- If you want to restore a partition, do not delete it with fdasd first. Doing so renames the partitions and the data sets.

# Obtaining authorization for Linux volumes

For Linux, you need root authority to mount and unmount the partitions, and to format and partition the volumes using dasdfmt and fdasd.

For z/OS, you need authority to run ADRDSSU, which is the program that is invoked when using DFSMSdss. z/OS treats the Linux partitions as data sets. Also, you can prevent unauthorized access of the Linux partitions by z/OS applications and users by using RACF or an equivalent security product.

# Backing up a Linux volume with partitions

z/OS treats a Linux partition (such as /dev/dasd/0198/part1) as a data set. The data set is named LINUX.Vvolser.PART000x.NATIVE for a data partition, or LINUX.Vvolser.PART000x.SWAP for a swap partition.

Here, volser is the volume serial number assigned to the volume when dasdfmt formatted the volume. fdasd can change the volser, too. The volser must be unique for z/OS to process it.

The x in PART000x is most likely the partition number, minus one. For example, a Linux partition such as /dev/dasd/0198/part2 would be known to z/OS as the data set LINUX.VLNX200.PART0001.NATIVE, where LNX200 is the volser of the volume.

**Attention:** If a partition is mounted read/write while undergoing a dump operation, data written to the partition during the dump operation might not be included in the backup. Because Linux uses deferred writes, unmounting a partition or remounting a partition read-only also serves to flush Linux's internal memory buffers to disk. Instead, process the dump when Linux is down, or when the partitions currently being backed up are unmounted or mounted read-only. If the partitions are mounted read/write, DFSMSdss can back up your data, but the data might be inconsistent. By unmounting or remounting a partition read-only, you can help to ensure that all of your data is backed up. You are not required to do this, but it provides the best copy. Below is an example of mounting a partition read-only:

mount -t ext2 -r /dev/dasd/019b/part1 /mntpoint

The data sets and the partitions they represent use this naming convention:

Data Set Names	Partition Names
LINUX.Vvolser.PART0000.type	/dev/dasd/yyyy/part1
LINUX.Vvolser.PART0001.type	/dev/dasd/yyyy/part2
LINUX.Vvolser.PART0002.type	/dev/dasd/yyyy/part3

#### where:

- volser is the volume serial number of the volume where the data set resides.
- yyyy is the device number of the volume in the Linux environment.
- type can be NATIVE or SWAP. You might decide that you need to back up only certain NATIVE partitions. SWAP partitions are the Linux equivalent to z/OS page packs.

Do not rename the data sets. fdasd expects the 24th character to be an 'N' or an 'S'. Otherwise, fdasd cannot recognize the partition type.

# Using DFSMSdss dump and restore commands

This topic contains examples of batch jobs that use DFSMSdss functions to dump and restore Linux for System z partitions and volumes. To submit these jobs for processing, you can either submit them to z/OS from your TSO/E user ID, or FTP them to a z/OS system from a Linux system, as described in "Submitting JCL batch jobs to a z/OS system using FTP" on page 195.

This topic contains the following examples for your reference:

- "Example 1. DUMP FULL" on page 189
- "Example 2. DUMP FULL with CONCURRENT COPY" on page 190
- "Example 3. DUMP DATASET" on page 190
- "Example 4. COPY FULL" on page 191
- "Example 5. COPY FULL COPYVOLID ALLEXCP" on page 192
- "Example 6. RESTORE FULL" on page 192
- "Example 7. RESTORE DATASET" on page 193
- "Example 8. COPYDUMP" on page 195.

#### Note:

- 1. IBM recommends using only the ADRDSSU keywords, which are shown between //SYSIN and /\* in the examples in this section.
- 2. You must include ALLEXCP among the keywords you specify for any DFSMSdss DUMP batch job or COPY batch job that processes Linux cdl volumes.
- 3. For information about JCL rules and syntax, see the following publications:
  - z/OS MVS JCL User's Guide
  - z/OS MVS JCL Reference.

### **Example 1. DUMP FULL**

You can use DFSMSdss to dump the entire contents of a volume to tape or DASD, and have DFSMSdss restore the dump at a later time. Here, you can use the DFSMSdss DUMP FULL command. After you create a dump of the boot volume, you can restore the volume to multiple volumes as a way of making identical copies of the basic Linux system.

On the DUMP FULL command, include the keyword ALLEXCP to cause DFSMSdss to process all of the data set or partition, even if unused. ALLEXCP is required; your data is not backed up if you do not specify it.

Figure 4 shows an example of the JCL (the Linux volume has volser LNX200).

```
//LXD2D1BB JOB ,'IBMUSER',MSGLEVEL=(1,1),TIME=(5,0),REGION=4096K,
// MSGCLASS=H,CLASS=A
//STEPT02 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SOURCE DD UNIT=3390,VOL=SER=LNX200,DISP=OLD
//TARGET DD UNIT=TAPE,VOL=(PRIVAT,SER=111111),DISP=(NEW,CATLG),
// DSN=TDS.DUMP200,LABEL=(1,SL)
//SYSIN DD *
DUMP FULL INDDNAME(SOURCE) OUTDDNAME(TARGET) -
ALLEXCP
/*
```

Figure 4. Sample JCL for dumping the contents of a volume.

You can also dump to two or more output tapes at the same time, for example, if you wanted a backup and a copy of the backup for storage off-site.

Figure 5 on page 190 shows an example of the JCL.

```
//LXD2D1XX JOB ,'IBMUSER', MSGLEVEL=(1,1), TIME=(5,0), REGION=4096K,
       MSGCLASS=H,CLASS=A
//STEPT02 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SOURCE DD UNIT=3390, VOL=SER=LNX200, DISP=OLD
//TARGET1 DD UNIT=TAPE, VOL=(PRIVAT, SER=111111), DISP=(NEW, CATLG),
            DSN=TDS.DUMP200,LABEL=(1,SL)
//TARGET2 DD UNIT=TAPE, VOL=(PRIVAT, SER=222222), DISP=(NEW, KEEP),
            DSN=TDS.DUMP200, LABEL=(1,SL)
//TARGET3 DD UNIT=3390, VOL=SER=WRKVOL, DISP=(NEW, KEEP),
            DSN=TDS.DUMP200
//SYSIN
         DD *
DUMP FULL INDDNAME (SOURCE) OUTDDNAME (TARGET1, TARGET2, TARGET3) -
```

Figure 5. Sample JCL for dumping two or more output tapes at the same time.

### Example 2. DUMP FULL with CONCURRENT COPY

You can use the volume being dumped without the dump being affected, much sooner than with the normal full volume dump. You might want to use this method when the Linux partitions that are being backed up need to be available in read/write mode.

On the DUMP FULL command, include the keyword CONCURRENT.

Figure 6 shows an example of the JCL.

```
//LXD2D2BB JOB ,'IBMUSER',MSGLEVEL=(1,1),TIME=(5,0),REGION=4096K,
       MSGCLASS=H,CLASS=A
//STEPT02 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SOURCE DD UNIT=3390, VOL=SER=LNX200, DISP=OLD //TARGET DD UNIT=TAPE, VOL=(PRIVAT, SER=111111), DISP=(NEW, CATLG),
             DSN=TDS.DUMP200,LABEL=(1,SL)
//SYSIN
            DD *
DUMP FULL INDDNAME (SOURCE) OUTDDNAME (TARGET) -
       CONCURRENT ALLEXCP
```

Figure 6. Sample JCL for DUMP FULL with CONCURRENT COPY.

The dump will reflect whatever data was present when the concurrent copy job started.

When you see message ADR734I as shown in the following example, you can remount the partitions to the Linux system and continue using them:

ADR734I (001)-TOMI (03), 2001.168 14:38:22 CONCURRENT COPY INITIALIZATION SUCCESSFUL FOR VOLUME LNX200. SERIALIZATION FOR THIS DATA IS RELEASED IF DFSMSDSS HELD IT. THE INTERMEDIATE RETURN CODE IS 0000.

# Example 3. DUMP DATASET

You can dump individual partitions by using physical processing. Doing might help if you have a swap partition on a particular volume and you only want to back up the native, data holding partitions (there is probably no reason to back-up a swap partition).

Figure 7 on page 191 shows an example of the JCL.

Figure 7. Sample JCL for DUMP DATASET.

You can also dump all of the Linux partitions. Figure 8 shows an example of the JCL.

Figure 8. Sample JCL for dumping all of the Linux partitions.

### **Example 4. COPY FULL**

You can make a full volume copy of a volume. Doing so would allow you, for example, to populate a new server with a standard configuration.

The COPY FULL function can also be useful because of FlashCopy for Enterprise Storage Server (ESS) devices, or SnapShot for RAMAC Virtual Array (RVA) devices. DFSMSdss attempts to use the fastest copy method possible before using the traditional data movement methods. FlashCopy or SnapShot make a virtually instantaneous copy of the volume, allowing you to continue using the volume.

Using FlashCopy requires the volumes to be in the same ESS that supports FlashCopy Version 2 (data set FlashCopy), or in the same logical subsystem in an ESS that supports FlashCopy Version 1, but not support FlashCopy Version 2 (data set FlashCopy) or later functions.

Similarly, when using SnapShot, the volume on which create a copy must be within the same subsystem as the source volume. In an RVA device, the four SSIDs that are defined to the RVA are considered to be within the same subsystem.

After the COPY FULL command completes, the data on LNX900 is the same as LNX200, except that the volser is LNX900. Figure 9 on page 192 shows an example of the JCL.

```
//LXD2C1BB JOB , 'IBMUSER', MSGLEVEL=(1,1), TIME=(5,0), REGION=4096K,
       MSGCLASS=H,CLASS=A
//STEPT02 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SOURCE DD UNIT=3390, VOL=SER=LNX200, DISP=OLD
         DD UNIT=3390, VOL=SER=LNX900, DISP=OLD
//SYSIN
COPY FULL INDDNAME(SOURCE) OUTDDNAME(TARGET) -
```

Figure 9. Sample JCL for making a full volume copy of a volume.

### **Example 5. COPY FULL COPYVOLID ALLEXCP**

You can create a backup copy of a Linux volume.

On the DFSMSdss COPY FULL command, include the COPYVOLID keyword to cause DFSMSdss to copy the volser to the new volume. When the copy operation completes, the two volumes are identical, including the volser. Because z/OS allows only one volume with a particular volser to be online at a time, DFSMSdss varies offline the volume that was the target of the copy.

On the COPY FULL command, include the keyword ALLEXCP to cause DFSMSdss to process all of the data set or partition, even if unused. ALLEXCP is required; your data is not backed up if you do not specify ALLEXCP.

Figure 10 shows an example of the JCL.

```
//LXD2C2BB JOB ,'IBMUSER',MSGLEVEL=(1,1),TIME=(5,0),REGION=4096K,
     MSGCLASS=H,CLASS=A
//STEPT02 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SOURCE DD UNIT=3390, VOL=SER=LNX200, DISP=OLD
//TARGET DD UNIT=3390, VOL=SER=LNX900, DISP=OLD
//SYSIN
         DD *
COPY FULL INDDNAME(SOURCE) OUTDDNAME(TARGET) -
      COPYVOLID ALLEXCP
```

Figure 10. Sample JCL for creating a backup copy of a Linux volume.

# Example 6. RESTORE FULL

You can restore a full volume from a dump taken by DFSMSdss. You would use this command when you want a Linux volume from a DFSMSdss dump that was created earlier.

Specify the RESTORE command with the FULL keyword. This action restores the entire contents from the original volume.

Figure 11 on page 193 shows an example of the JCL.

```
//LXD2D1BB JOB ,'IBMUSER',MSGLEVEL=(1,1),TIME=(5,0),REGION=4096K,
// MSGCLASS=A,CLASS=A
//STEPT03 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SOURCE DD UNIT=3390,DISP=OLD,DSN=TDS.DUMP200
//TARGET DD UNIT=3390,VOL=SER=LNX200,DISP=OLD
//SYSIN DD *
RESTORE FULL INDDNAME(SOURCE) OUTDDNAME(TARGET) PURGE
/*
```

Figure 11. Sample JCL for restoring a full volume from a DFSMSdss dump.

In Figure 11, observe the following:

- The Linux volume is *volser* LNX200
- The dump that was stored in data set TDS.DUMP200 is being restored to LNX200
- The SOURCE DD statement identifies where DFSMSdss is to find the information to restore
- The TARGET DD statement identifies where DFSMSdss is to restore the volume information and data.

You can overwrite any data sets that are on the LNX200 volume currently with unexpired dates when you specify PURGE. All Linux partitions are permanent, and thus have "never expire" dates.

### **Example 7. RESTORE DATASET**

You can restore individual partitions or data sets that were part of a full volume dump or that were from a data set level dump previously taken by DFSMSdss. You might want to do this to restore those particular partitions that were corrupted. Restoration of data sets from a data set level dump is similar to restoring full volumes.

Figure 12 shows an example of the JCL.

Figure 12. Sample JCL for restoring individual partitions or data sets.

In Figure 12, notice that the keyword REPLACE is specified instead of PURGE. For data set level restores, REPLACE causes DFSMSdss to replace any existing data sets on the volume with the restored versions. If the data set you are restoring exists and you do not specify REPLACE, the restore will fail and you will not obtain the backup version. Also in Figure 12, the INCLUDE statement indicates that DFSMSdss is to restore any data sets that start with LINUX and end with NATIVE (and have anything in-between). The '\*\*' means any number of eight-letter qualifiers. Be careful to use two asterisks (one asterisk has a different meaning).

When preparing to restore a partition, do not use fdasd to delete the partition before running DFSMSdss to restore it. When fdasd deletes a partition, it reorders

and renames the remaining partitions on the same volume. A subsequent restore can result in the wrong partition being overlaid.

To restore a deleted partition or a partition that never existed, use fdasd, which can create a new partition that is exactly the same size and in the same location as the deleted partition. Use the same starting and ending track. fdasd will create the correct names for the data sets. When you restore that data set or partition, the data is placed correctly and you do not lose any partitions. The reason is that the name of the second partition is the same as the restored first partition.

For example, if you delete /dev/dasd/xxxx/part1 (known to z/OS as LINUX.VLNX200.PART0000.NATIVE), fdasd renames the other partitions (fdasd subtracts one from the former name). part2 becomes part1 and part3 becomes part2.

The data set names change, too. After fdasd deletes LINUX.VLNX200.PART0000.NATIVE, it renames LINUX.VLNX200.PART0001.NATIVE to LINUX.VLNX200.PART0000.NATIVE. If you then use DFSMSdss to restore the first partition (named LINUX.VLNX200.PART0000.NATIVE), you will lose the second partition.

You can also use the RENAMEUNCONDITIONAL keyword to change the names of the data sets that you are restoring. Figure 13 shows an example of the JCL.

```
//LXD2S1XX JOB ,'IBMUSER', MSGLEVEL=(1,1), TIME=(5,0), REGION=OM,
       MSGCLASS=A, CLASS=A
//STEPT03 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SOURCE DD UNIT=3390.DISP=0LD.DSN=TDS.DUMP200
//TARGET DD UNIT=3390, VOL=SER=LNX300, DISP=OLD
//SYSIN
RESTORE INDDNAME(SOURCE) OUTDDNAME(TARGET) -
        DATASET(INCLUDE(LINUX.VLNX200.PART0001.NATIVE))
        RENAMEUNCONDITIONAL (LINUX.VLNX200.PART0001.NATIVE, -
        LINUX.VLNX300.PART0001))
```

Figure 13. Sample JCL for renaming data sets to be restored.

If you want to change the data set, change only the volser or the last character of the partition name (PART000x). If you change anything else, Linux might not recognize the partition.

Assume that you have three partitions on a volume in which:

- Partition 1 contains programs
- · Partition 2 contains data
- Partition 3 is a swap partition.

Now suppose that someone with root authority accidentally deletes the programs on Partition 1. As a result, you need to restore the backup versions of those programs, but leave the data partition (Partition 2) alone. You might not have to restore Partition 3 because it is swap space.

Figure 14 on page 195 shows an example of the JCL you might use to restore only the first partition, LINUX.VLNX200.PART0000.NATIVE.

Figure 14. Sample JCL for restoring only one partition of a volume.

## **Example 8. COPYDUMP**

With DFSMSdss, you can copy Linux volume dumps. You might want to do this if you need to have copies of your dump tapes for disaster recovery purposes. Some installations, for example, keep an on-site backup tape in addition to an off-site copy of the dump.

To copy a Linux volume dump, use the DFSMSdss COPYDUMP command. You can copy a dump immediately after creating it, or you can make a copy of an older dump.

Figure 15 shows an example of the JCL.

Figure 15. Sample JCL for copying Linux volume dumps.

# Submitting JCL batch jobs to a z/OS system using FTP

You can use FTP to submit your JCL batch jobs to a z/OS system from a Linux image. When you FTP to the z/OS system, enter the site file=jes command. The FTP server on the z/OS system should rout any file that it receives to the job entry subsystem (JES) for execution. (Your login id must have sufficient authority to run DFSMSdss batch jobs, as mentioned in "Obtaining authorization for Linux volumes" on page 187).

Then, "put" your JCL batch jobs to the z/OS system. Save your jobs as text files that do not exceed 80 characters in length.

# Using DFSMSdss stand-alone services

You can use DFSMSdss stand-alone services to create an IPL-able (that is, bootable) image on tape. With the IPL-able image, you can use the DFSMSdss stand-alone restore program to restore a Linux volume that was backed up by DFSMSdss. You can do this without having to start z/OS.

For a list of devices you can use with the DFSMSdss stand-alone restore program, see the topic on DFSMSdss stand-alone services in Chapter 19, "DFSMSdss stand-alone services," on page 511.

# Chapter 13. Format of the DFSMSdss dump data set

This topic describes the formats of the DFSMSdss dump data set, and data areas ADRBMB (Table 16 on page 198) and ADRTAPB (Table 18 on page 199).

For information about ADRUFO, refer to *z/OS DFSMS Installation Exits*.

For information about ADREID0, refer to "ADREID0 data area" on page 607.

## Format of the DFSMSdss dump data set

- For a physical dump, the volume record may also contain an encryption record following the volume header when encryption was performed during the dump. The volume record may also contain an extended volume record if any data was dumped from an EAV, if zCompression was used, or the block size of the output dump data set on tape is greater than 65,520 bytes. The extended volume record follows the:
  - Encryption record, if encryption was performed
  - Volume record, if encryption was not performed.
- For a logical dump, the tape header record also contains an encryption record following the DFSMSdss tape header when encryption was performed during the dump. The tape header record may also contain an extended volume record if zCompression was used, or if the block size of the output dump data set on tape is greater than 65,520 bytes. The extended tape header record follows the:
  - Encryption record, if encryption was performed
  - Tape header record, if encryption was not performed.
- If hardware-assisted compression was used (HWCOMPRESS keyword), a data track record may be preceded by an expansion dictionary record.

For a physical dump, each logical volume of a DFSMSdss dump data set contains the following data in the following sequence:

- 1. Volume header record, which identifies and contains data pertinent to the whole volume and identifies the type of operation that created the dump.
- 2. Map record or records, which map the tracks that were dumped. The data in this record is described by the "ADRBMB data area" on page 198.
- **3**. Track 0: dump of track 0 of cylinder 0.
- 4. VSAM volume data set (VVDS) track records, if VSAM or SMS-managed data sets exist on the volume and were dumped.
- 5. Volume table of contents (VTOC) track records.
- 6. Data track records, which include VVDS if it is part of the dump. This item is repeated for all tracks being dumped.
- 7. Two volume trailer records, which identify the end of the data for the DASD volume.

For a logical dump, the format of the DFSMSdss dump data set contains the following data in the following sequence:

- 1. Tape header record.
- 2. List of potential data sets record.
- 3. Data set header record.

- 4. Volume header record (one for non-VSAM data sets, one for each VSAM
- 5. Sphere information record (if the SPHERE keyword was specified and this data set is part of a sphere).
- 6. Data track records (one or more for each track of the data set on this volume).
- 7. Two data set trailer records.

#### Note:

- 1. For each data set, repeat items 3 on page 197 through 7.
- 2. For each volume of the data set, repeat items 4 and 6.

Every record on a DFSMSdss dump data set is described by the "ADRTAPB data area" on page 199.

## **ADRBMB** data area

Table 16. ADRBMB Mapping Macro

Off	sets				
Dec	Hex	Туре	Len	Name (Dim)	Description
0	(0)	CHARACTER	*	ADRBMB	
0	(0)	CHARACTER	12	BMHDR	BITMAP HEADER
0	(0)	CHARACTER	4	BMID	BLK IDENTIFIER EBCDIC "BMBB"
4	(4)	ADDRESS	4	BMNPTR	ADDR OF NEXT BITMAP SEGMENT/0
8	(8)	UNSIGNED	4	BMNTRK	NUMBER OF TRACKS MAPPED BY SEGMENT
8	(8)	UNSIGNED	2	BMNTRKTP	NUMBER OF TRACKS MAPPED BY SEGMENT
10	(A)	CHARACTER	2	*	RESERVED
12	(C)	BITSTRING	0	BMBITMAP	BITMAP LAYOUT, CONTIGUOUS BITS FOR EACH TRACK. 1=OPERATE ON CORRESPONDING TRACK, 0=SKIP TRACK
Note:					
0	(0)	STRUCTURE	*	ADRCMB	CHUNK MAP BLOCK
0	(0)	CHARACTER	12	CMHDR	CHUNK MAP HEADER
0	(0)	CHARACTER	4	CMID	BLOCK EYECATCHER
4	(4)	ADDRESS	4	CMNPTR	PTR TO NEXT CHUNKMAP
8	(8)	UNSIGNED	4	CMNCHNK	NUMBER OF CHUNKS MAPPED
8	(8)	UNSIGNED	2	CMNCHKTP	SHIFTED NUMBER OF CHUNKS
10	(A)	CHARACTER	2	*	RESERVED BY THIS SEGMENT
12	(C)	BITSTRING	0	CMBITMAP	BITMAP LAYOUT, CONTIG BITS FOR EACH 21 CYL CHUNK TO BE PROCESSED
Note:					
0	(0)	STRUCTURE	*	ADRTSMB	TRACK SUBMAP
0	(0)	CHARACTER	8	TSMHDR	TRACK SUBMAP HEADER
0	(0)	CHARACTER	4	TSMID	TRACK SUBMAP EYECATCHER
4	(4)	SIGNED	4	TSMCHKCC	CYL ADDR OF CHUNK START
8	(8)	BIT(*)	*	TSMBITMP	TRACK SUB BITMAP

## **ADRBMB** constants

Table 17. ADRBMB Mapping Macro

Length	Type	Value	Name	Description
4	CHARACTER	CMBB	ADRCMID	BLOCK IDENTIFIER
4	DECIMAL	197	CMAXSEG#	MAX NUM OF BITMAP
4	DECIMAL	315	CHKTRKS	15*21 TRACKS / CHUNK
4	DECIMAL	21	CHUNKSZ	21 CYLS PER CHUNK
4	CHARACTER	TSMB	ADRTSMID	BLOCK IDENTIFIER
4	DECIMAL	40	CSTRKSZ	SIZE OF TRACK SUBMAP

## **ADRBMB** cross-reference

N	am	6

	Hex Offset
ADRBMB	0
ADRCMB	0
ADRTSMB	0
BMBITMAP	12
BMHDR	0
BMID	0
BMNPTR	4
BMNTRK	8
CMBITMAP	12
CMHDR	0
CMID	0
CMNCHKTP	8
CMNCHNK	8
CMNPTR	4
TSMBITMP	8
TSMCHKCC	4
TSMHDR	0
TSMID	0

## **ADRTAPB** data area

Table 18. ADRTAPB Mapping Macro

OFI	FSET							
Dec	Hex	Type	Len	Name (Dim)	Description			
	Mapping of main prefix area (first thing in every record).							
0	(0)	STRUCTURE	16	ADRTAPB				
0	(0)	CHARACTER	6	DTPSCHK				
0	(0)	SIGNED	4	DTPSEQNO	SEGMENT SEQUENCE NUMBER			
4	(4)	UNSIGNED	1	DTPNOSEG	NUM OF SEGMENTS PER RECORD			
5	(5)	UNSIGNED	1	DTPSEGNO	SEGMENT NUM OF RECORD			
6	(6)	UNSIGNED	2	DTPSEGLN	SEGMENT LENGTH INCL PREFIX			

Table 18. ADRTAPB Mapping Macro (continued)

	FSET	PB Mapping Macro(			
Dec	Hex	Туре	Len	Name (Dim)	Description
8	(8)	UNSIGNED	1	DTPPFXLN	LENGTH OF PREFIX(CONSTANT 16)
9	(9)	CHARACTER	1	DTPDMPID	TYPE OF DUMP ID
		1		DTPFULD	80 - FULL DUMP
		.1		DTPPARTD	40 - PARTIAL DUMP
		1		DTPDASDD	20 - DATASET DUMP
		1		DTPLOGCL	10 - LOGICAL DUMP - THIS BIT IS CALLED DTPCATDD IN V2.1, V2.2 - DTPLOGCL MUST BE 4TH. BIT IN STRUCTURE TO MAINTAIN COMPATIBILITY BETWEEN V2.1, V2.2 AND V2.3
		1111		*	RESERVED - DO NOT USE LAST 4 BITS IN DTPDMPID TO ENSURE DOWNWARD COMPATIBILTY
10	(A)	BIT(8)	1	DTPRCID1	RECORD IDENTIFIER 1
		1		DTPVHDR	80 - VOLUME HEADER (SEE DTVOL)
		1		DTPTHDR	- TAPE HEADER (see DTHDR)
		.1		DTPBTM	40 - MAP OF DUMPED TRKS (see DTBTMR)
		.1		DTPDSNL	- DS NAME/CATALOG LST (see DTLDSN)
		1		DTPTRK0	20 - TRACK 0 (see DTTTRK)
		1		DTPDSHDR	- DATA SET HEADER (see DTDSHDR)
		1		DTPVTOC	10 - VTOC TRACK (see DTTTRK)
		1		DTPVOLD	- VOLUME DEFINITION (see DTMVOL)
		1		DTPDATA	08 - DATA TRACK (see DTTTRK)
		1		DTPVTRLR	04 - VOLUME TRAILER (see DTRTLR)
		1		DTPDTRLR	- DS TRAILER (see DTRTLR)
		1.		DTPVVDS	02 - VVDS TRACK (see DTTTRK)
		1		DTPSPHDR	01 - SPHERE REC HEADER (see DTSPHERE)
11	(B)	BIT(8)	1	DTPRCFL1	FLAG BYTE
		1		DTPDDISP	IF ON, DATA EQUAL TO LENGTH OF ADRTAPB HAS BEEN DISPLACED FROM THIS SEGMENT TO THE LAST SEGMENT OF THE TRACK
		.1		DTPDDDSP	IF ON, LAST SEGMENT DISPLACED DATA MUST BE REPLACED FIRST (SEE DTPDDISP)
		1		DTPENDNT	1=END OF NON-TRACK DATA SET (EG, CDF DATA SET OR VSAM DATA SET DUMPED BY VSAM I/O)
		1		DTPENDKR	1=END OF A KEY RANGE FOR DS DUMPED BY VSAM I/O
		1		DTPBWOE	1=BWODSN ONLY USED FOR DUMP OF DSET (OPEN DSET)
		1		DTPDUMPC	SOURCE FROM DUMPCOND VOL
		1.		DTPSELFD	SELF DESC RECORDS EXIST
		1		*	RESERVED
12	(C)	CHARACTER	2	DTPVER#	ADRTAPB VERSION NUMBER
14	(E)	CHARACTER	2	*	RESERVED
16	(10)	CHARACTER	0	DTPBODY	START OF REMAINDER OF RECORD
		REST O	F VOLUM	E HEADER RECO	RD (follows ADRTAPB).
0	(0)	STRUCTURE	46	DTVOL	
0	(0)	CHARACTER	4	DTVTOCB	VTOC BEGINNING CCHH

Table 18. ADRTAPB Mapping Macro (continued)

OFI	FSET				
Dec	Hex	Type	Len	Name (Dim)	Description
4	(4)	CHARACTER	4	DTVTOCE	VTOC ENDING CCHH
8	(8)	CHARACTER	4	DTVOLSZ	VOLUME SIZE(DS4DEVSZ)
8	(8)	UNSIGNED	2	DTVLOGCY	# OF CYLINDERS IN VOLUME
10	(A)	UNSIGNED	2	DTVTRKCY	# OF TRACKS PER CYLINDER
12	(C)	UNSIGNED	2	DTVBLKSZ	MAXIMUM BLOCKSIZE
14	(E)	UNSIGNED	2	DTVMAXCB	MAXIMUM COMPRESS BUFFER IN WORDS
16	(10)	CHARACTER	6	DTVSERL	VOLUME SERIAL OF SOURCE VOL
22	(16)	CHARACTER	1	DTVVTOCI	VTOC INDICATORS
23	(17)	CHARACTER	8	DTVTIMD	DATE & TIME OF DAY OF DUMP
23	(17)	CHARACTER	4	DTVDAY	DATE - 00YYDDDC
27	(1B)	CHARACTER	4	DTVTIME	TIME OF DAY IN DECIMAL
31	(1F)	CHARACTER	4	DTVDEVTY	DEVTYP OF VOLUME(UCBTBYT4)
35	(23)	UNSIGNED	1	DTVMODNO	MODEL NUMBER
36	(24)	BIT(8)	1	DTVIND1	VOLUME TYPE INDICATORS
		1		DTVVIRT	80 - VIRTUAL VOLUME
		.1		DTVMINI	40 - MINI DISK
		1		DTVCVAF	20 - VOLUME HAS INDEXED VTOC
		1		DTVCPVOL	10 - CP volume fmt
		1		DTVFCMP	08 - FILE COMPRESSED
		1		DTVUNLCD	04 - UNALLOCATED SPACE DUMPED
		1.		DTVLVF	02 - OTHER LOGICAL VOLUMES MAY FOLLOW THIS LOGICAL VOLUME
		1		DTVVVDS	01 - VVDS DATASET DUMPED BEFORE VTOC
37	(25)	UNSIGNED	2	DTVBMSZ	BITMAP SIZE IN WORDS
39	(27)	BIT(8)	1	DTVIND2	VOLUME TYPE INDICATORS
		1		DTVLNVI	80-NONVSAM DATA SETS NOT ON VOLUME
		.1		DTVLVI	40-VSAM DATA SETS NOT ON VOLUME
		1		DTVGNVI	20-NONVSAM DATA SETS NOT ON ANY VOLUME
		1		DTVGVI	10-VSAM DATA SETS NOT ON ANY VOLUME
		1		DTVSMS	SOURCE VOLUME IS SMS MANAGED
		1		DTVSMSI	SOURCE VOL IS SMS INITIAL STAGE
		1.		DTVFHCMP	HARDWARE COMPRESS USED
		1		*	UNUSED
40	(28)	UNSIGNED	2	DTVLEN	LEN OF HEADER (SEGMENT LEN - PREFIX
42	(2A)	UNSIGNED	1	DTVVERNO	DFDSS VERSION NUMBER
43	(2B)	UNSIGNED	1	DTVLVLNO	DFDSS MODIFIC. NUMBER
44	(2C)	UNSIGNED	1	DTVVXTNO	NUMBER OF VVDS EXTENTS
45	(2D)	UNSIGNED	1	DTVVXTOF	OFFSET TO VVDS EXTENT
		Mapping	of additi	onal volume informat	tion (follows DTVOL).
0	(0)	STRUCTURE *		DTVEND	FIELDS FROM DTVOL START
0	(0)	CHARACTER	0	*	
	1		Mappins	g of VVDS extents (in	DTVEND).
0	(0)	STRUCTURE		DTVVXTNT(*)	VVDS EXTENTS, IN DSCB FORMAT
0	(0)	CHARACTER		DTVVXLEN	

Table 18. ADRTAPB Mapping Macro (continued)

		PB Mapping Macro (c	 	' <i>)</i> 	I
OFF		Trumo	т	Nama (Dim)	Description
Dec	Hex	Type PECT OF LOC		Name (Dim)	DER (follows ADRTAPB).
0	(0)		1	I	DER (IOHOWS ADRIAFD).
	(0)	STRUCTURE		DTHDR	DATE & TRAC / DAY OF DUMP
0	(0)	CHARACTER		DTHTIMD	DATE & TIME/DAY OF DUMP
0	(0)	CHARACTER		DTHDAY	DAY
4	(4)	CHARACTER		DTHTIME	TIME
8	(8)	CHARACTER	1	DTHIND2	DATA SET TYPE INDICATORS
		1		DTHGNVI	NO NON-VSAM DATA SETS
		.1		DTHGVI	NO VSAM DATA SETS
		1		DTHGT64K	ON=MORE THAN 65535 DATA SETS ON VOLUME
		1 1111		*	RESERVED
9	(9)	UNSIGNED	2	DTHLEN	HEADER LEN
11	(B)	UNSIGNED	1	DTHVERNO	DFDSS VERSION NUMBER
12	(C)	UNSIGNED	1	DTHLVLNO	DFDSS MODIFIC. NUMBER
13	(D)	UNSIGNED	2	DTHBLKSZ	MAX BLKSIZE
15	(F)	UNSIGNED	2	DTHNDS	# DS IN LIST
17	(11)	CHARACTER	1	DTHIND1	INDICATORS
		1		DTHFCMP	FILE COMPRESSED
		.1		DTHUNLCD	UNALLOCATED SPACE DUMPED
		1		DTHSFER	SPHERE OPTION
		1		DTHFHCMP	HARDWARE COMPRESSION
		1		DTHEFSAM	EF SAM DS HAVE DTTTRK
		111		*	RESERVED
		REST OF DA	ATA SET	NAME/CATALOG LIS	ST (follows ADRTAPB).
0	(0)	STRUCTURE	45	DTLDSN	
0	(0)	UNSIGNED	1	DTLLEN	LENGTH OF DATA SET NAME
1	(1)	CHARACTER	44	DTLCAT	CATALOG NAME
		REST OF	DATA SE	ET HEADER RECORD	(follows ADRTAPB).
0	(0)	STRUCTURE	106	DTDSHDR	
0	(0)	UNSIGNED	1	DTDLEN	LENGTH OF DATA SET NAME
1	(1)	UNSIGNED	1	DTDCATLN	LENGTH OF CATALOG NAME
2	(2)	CHARACTER		DTDDSORG	DATA SET ORGA (FROM F1)
4	(4)	CHARACTER	1	DTDOPTCD	DS OPTION CODE (FROM F1)
5	(5)	CHARACTER		DTDNVOL	NUMBER VOLS FOR DATA SET
6	(6)	BIT(8)	1	DTDIND	DATA SET INDICATOR
	(*)	1		DTDIPWD	PASSWORD SUPPLIED 1=YES
		.1		DTDTPWD	TYPE PASSWORD 0=D.S. 1=CATALOG
		1		DTDIRACF	RACF PROFILE
		1 1		DTDRACFP	RACF PROFILE FLAGS
		1		DTDRACFD	1 = RACF DISCRETE PROFILE
				DTDRACFG	1 = RACF DISCRETE PROFILE  1 = RACF GENERIC PROFILE
		1			
		1		DTDALIAS	1 = USER CATALOG ALIAS
		1.		DTDSPER	1 = SPHERE RECORD FOLLOWS
	( <del>-</del> 7)	1		DTDSMS	1=SMS MANAGED DATA SET
7	(7)	CHARACTER	8	DTDPWD	PASSWORD

Table 18. ADRTAPB Mapping Macro (continued)

	FSET	_			
Dec	Hex	Туре	Len	Name (Dim)	Description
15	(F)	CHARACTER	44	DTDCAT	CATALOG NAME
59	(3B)	CHARACTER	44	DTDDSN	DATA SET NAME
103	(67)	CHARACTER	2	DTDVOLCT	SMS VOL CNT (FROM BCS)
103	(67)	UNSIGNED	1	DTDVCTD	VOLCOUNT FOR DATA COMPONENT OR NONVSAM DATA SET
104	(68)	UNSIGNED	1	DTDVCTI	VOLCOUNT FOR INDEX COMPONENT OR ZERO FOR NO INDEX
105	(69)	CHARACTER	1	DTDIND2	DATA SET INDICATOR 2
		1		DTDAIXSP	AIX® & PART OF A SPHERE
		.1		DTDCDF	1=COMMON DATA FORMAT DSET
		1		DTDPDSE	1=PDSE DATA SET
		1		DTDNTALL	1=DUMPED WITHOUT USING ALLD OR ALLX
		1		DTDSAI	1=DS ADTL INFO
		1		DTDNOIDX	1=VSAM INDEXED DATA SET DUMPED USING VALIDATE OPTION (INDEX NOT DUMPED, DATA CI'S IN ORDER)
		1.		DTDPDSET	1=PDSE DUMPED AS TRACK IMAGES
		1		DTDSDM	USE SYSTEM DATA MOVER
		N	lapping o	of sphere information	n (in DTSAIXS).
		SPHERE RECO	ORD FOR	CATALOG FILTER	DUMP (follows ADRTAPB).
0	(0)	STRUCTURE	4	DTSPHERE	
0	(0)	SIGNED	4	DTSLEN	LENGTH OF SPHERE RECORD
0	(0)	STRUCTURE	102	DTSINFO	SPHERE INFORMATION
0	(0)	CHARACTER	44	DTSAIXNM	AIX NAME
44	(2C)	CHARACTER	44	DTSPATHN	PATH NAME
88	(58)	CHARACTER	1	DTSPATHA	PATH ATTRIBUTE
89	(59)	BIT(8)	1	DTSPATHF	PATH INFO FLAG
		1		DTSPATHI	IF SET, PATH OWNERID IS CONTAINED IN THIS BLOCK (SEE DTSPTHON FOR DESCRIPTION)
		.1		DTSPATHE	PATH EXPIRATION DATE IS CONTAINED IN THI BLOCK (SEE DTSPTHEP FOR DESCRIPTION). IF NOT SET, IGNORE THE EXPIR FIELDS.
		1		DTSPATHP	PATH HAS PASSWORD THAT IS CONTAINED IN THIS BLOCK (SEE DTSEXPIR FOR DESCRIPTION) IF EXISTS, BEGINS AT DTSPATHD.
		1 1		DTSPRACF	PATH RACF FLAGS
		1		DTSRACFD	1=DISCRETE PROFILE
		1		DTSRACFG	1=GENERIC PROFILE
		111		*	NOT USED
		CHARACTER	8	DTSPTHON	FORMAT OF OWNERID
90	(5A)		1	DTSPTHEP	
90 98	(5A) (62)	CHARACTER	4	D131 111E1	EXPIRATION DATE FORMAT:
	` ′	CHARACTER CHARACTER	3	DTSEXPIR	EXPIRATION DATE FORMAT:  YYDDDF FORMAT
98	(62)				
98 98	(62) (62)	CHARACTER	3	DTSEXPIR	YYDDDF FORMAT

Table 18. ADRTAPB Mapping Macro (continued)

OFI	FSET				
Dec	Hex	Type	Len	Name (Dim)	Description
0	(0)	STRUCTURE	52	DTSPASSW	SECURITY INFO TABLE
0	(0)	CHARACTER	8	DTSMSTRP	MASTER PASSWORD. MUST HAVE IN ORDER TO HAVE ANY OTHER PASSWORDS.
8	(8)	CHARACTER	8	DTSCNTLP	CONTROL INTERVAL PASSWORD
16	(10)	CHARACTER	8	DTSUPDAT	UPDATE PASSWORD
24	(18)	CHARACTER	8	DTSREADP	READ PASSWORD
32	(20)	CHARACTER	8	DTSCODEN	CODE NAME
40	(28)	SIGNED	2	DTSNUMAT	NUMBER OF ATTEMPTS
42	(2A)	CHARACTER	8	DTSAUTNM	ADDR OF AUTHORIZATION MOD
50	(32)	SIGNED	2	DTSAUTHR	AUTHORIZATION REC LENGTH
		COMMON DAT	TA FORM	AT DATA SET ATT	RIBUTES (follows DTDSHDR).
0	(0)	STRUCTURE	64	DTCDFATT	CDF ATTRIBUTE
0	(0)	SIGNED	4	DTCHURPN	HIGH USED PAGE NUMBER
4	(4)	CHARACTER	1	DTCDFIND	CDF flags
		1		DTDPDSEX	PDSEX flag
5	(5)	CHARACTER	3	*	RESERVED FOR FUTURE
8	(8)	UNSIGNED	4	DTC#DIRB	DIRECTORY BLOCK CNT
12	(C)	CHARACTER	52	*	RESERVED FOR FUTURE
64	(40)	CHARACTER	0	*	LAST
		Ma	pping for	additional data (fo	llows DTCDFATT).
0	(0)	STRUCTURE	*	DTDSAIR	
0	(0)	SIGNED	4	DTDSAIDL	ADD. DATA LENGTH
4	(4)	CHARACTER	*	DTDSAID	ADD. DATA FOLLOWS
		REST OF V	OLUME	DEFINITION REC	ORD (follows ADRTAPB).
0	(0)	STRUCTURE	28	DTMVOL	
0	(0)	CHARACTER	6	DTMVSERL	VOLUME SERIAL ID
6	(6)	CHARACTER	4	DTMDEVTY	DEVTYPE (UCBTBYT4)
10	(A)	CHARACTER	2	*	SLACK FILLER
12	(C)	CHARACTER	8	DTMVOLSZ	VOLUME SIZE (DS4DEVSZ)
12	(C)	UNSIGNED	4	DTMTRKCP	#BYTES/TRK (TRACK CAPACITY WITH OVERHEAD).
16	(10)	UNSIGNED	2	DTMLOGCY	# CYLINDERS PER VOLUME
18	(12)	UNSIGNED	2	DTMTRKCY	# TRACKS PER VOLUME
20	(14)	UNSIGNED	2	DTMMAXCB	MAX COMPRESS BUF IN WORDS
22	(16)	CHARACTER	2	DTMIND	VOLUME INDICAT
		1		DTMVIRT	VIRTUAL VOLUME
		.1		DTMMINI	MINI VOLUME
		1		DTMCVAF	VOLUME HAS INDEXED VTOC
		1		DTMTIME	Time stamp follows VVR
		1		DTMBWOT	RLS time stamps are BWO
22	(16)	BIT(11) POS(6)	2	*	unused
24	(18)	UNSIGNED	1	DTM#VVRS	# OF VVRS/NVRS DUMPED
25	(19)	UNSIGNED	1	DTM#DSCB	# OF DSCBS DUMPED
26	(1A)	UNSIGNED	1		# OF EXTENTS DUMPED

Table 18. ADRTAPB Mapping Macro (continued)

OF	FSET				
Dec	Hex	Туре	Len	Name (Dim)	Description
27	(1B)	CHARACTER	1	DTMMODNO	MODEL NUMBER
		Mapping	of the DS	CBs, extents and V	VRs (follows DTMVOL).
0	(0)	STRUCTURE	*	DTMVDATA	DSCBS (1&2) FOR DS, FOLLOWED BY EXTENT LIST, FOLLOWED BY VVRS OR NVR DATA SET CLUSTER.
0	(0)	CHARACTER	0	*	
		REST OF RECOR	D THAT N	MAPS THE TRACK	S DUMPED (follows ADRTAPB).
0	(0)	STRUCTURE	12	DTBTMR	
0	(0)	CHARACTER	12	DTBHDR	RESERVED
0	(0)	CHARACTER	4	DTBBMID	ID OF THE BLOCK = BMBB
4	(4)	SIGNED	4	DTBADDR	@ OF NEXT BMBB SEGMENT COPIED FROM ADRBMB BLOCK
8	(8)	UNSIGNED	4	DTBTRK#	# OF TRKS MAPPED IN BMBB SEGMENT
8	(8)	UNSIGNED	2	DTBTRK#P	# OF TRKS MAPPED IN BMBB SEGMENT
10	(A)	CHARACTER	2	*	RESERVED
		M	apping of	the bitmap data (fo	ollows DTBTMR).
0	(0)	STRUCTURE	*	DTBBITM	BITMAP
0	(0)	CHARACTER	0	*	
subseau	ient track s	segments are not preced			ed by ADRTAPB. The remaining track image data begins
	T	T		mediately after AD	
0	(0)	STRUCTURE	24	DTTTRK	MAPS THE TRACK
0 0	(0)	CHARACTER	24 16	DTTTRK DTTHDR	MAPS THE TRACK HEADER FOR EACH TRACK SEGMENT
0 0 0	(0)	CHARACTER UNSIGNED	24 16 2	DTTTRK DTTHDR DTTTRKLN	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK
0 0	(0)	CHARACTER UNSIGNED CHARACTER	24 16	DTTTRK DTTHDR DTTTRKLN DTTTRKID	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS
0 0 0	(0)	CHARACTER UNSIGNED	24 16 2	DTTTRK DTTHDR DTTTRKLN DTTTRKID DTTIOER	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK
0 0 0	(0)	CHARACTER UNSIGNED CHARACTER	24 16 2	DTTTRK DTTHDR DTTTRKLN DTTTRKID	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS
0 0 0	(0)	CHARACTER UNSIGNED CHARACTER 1	24 16 2	DTTTRK DTTHDR DTTTRKLN DTTTRKID DTTIOER	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED
0 0 0	(0)	CHARACTER UNSIGNED CHARACTER 1	24 16 2	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTROVF	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)
0 0 0	(0)	CHARACTER UNSIGNED CHARACTER 1	24 16 2	DTTTRK DTTHDR DTTTRKLN DTTTRKID DTTIOER DTTTROVF DTTTCMP	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED
0 0 0	(0)	CHARACTER UNSIGNED CHARACTER 1	24 16 2	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTROVF  DTTTCMP  DTTVFRST	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD
0 0 0	(0)	CHARACTER  UNSIGNED  CHARACTER  1	24 16 2	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTROVF  DTTTCMP  DTTVFRST  DTTINVT	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT
0 0 0 2	(0) (0) (2)	CHARACTER  UNSIGNED  CHARACTER  1	24 16 2 1	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTROVF  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD
0 0 0 2	(0) (0) (2) (2)	CHARACTER  UNSIGNED  CHARACTER  1  .1  .1  .1   UNSIGNED	24 16 2 1	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS
0 0 0 2 2 3 7	(0) (0) (2) (3) (7)	CHARACTER UNSIGNED CHARACTER 1111 UNSIGNED SIGNED	24 16 2 1	DTTTRK  DTTHDR  DTTTRKIN  DTTTRKID  DTTIOER  DTTTROVF  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH  DTTLRCNT	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)
0 0 0 2	(0) (0) (2) (3) (7)	CHARACTER UNSIGNED CHARACTER 1111 UNSIGNED SIGNED UNSIGNED	24 16 2 1	DTTTRK DTTHDR DTTTRKLN DTTTRKID DTTIOER DTTTROVF DTTTCMP DTTVFRST DTTINVT DTTSTAT DTTCCHH DTTLRCNT	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)  EXTRA ENC DATA LEN
0 0 0 2 2 3 7	(0) (0) (2) (2) (3) (7) (B) (C)	CHARACTER UNSIGNED CHARACTER 1111 UNSIGNED SIGNED UNSIGNED CHARACTER	24 16 2 1	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH  DTTLRCNT  DTTXDLEN  *	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)  EXTRA ENC DATA LEN  RESERVED
0 0 0 2 3 7 11 12 16	(0) (0) (2) (2) (3) (7) (B) (C) (10)	CHARACTER UNSIGNED CHARACTER 1111 UNSIGNED SIGNED UNSIGNED CHARACTER CHARACTER	24 16 2 1 1 4 4 4 8 0	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH  DTTLRCNT  DTTXDLEN  *  DTTRODAT	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)  EXTRA ENC DATA LEN  RESERVED  RCRD 0 DATA, ONLY ON 1ST SEG  R1- RN RECORDS ON TRACK
0 0 0 2 3 7 11 12 16	(0) (0) (2) (2) (3) (7) (B) (C) (10)	CHARACTER UNSIGNED CHARACTER 1111 UNSIGNED SIGNED UNSIGNED CHARACTER CHARACTER	24 16 2 1 1 4 4 4 8 0 Count fi	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH  DTTLRCNT  *  DTTXDLEN  *  DTTRODAT  DTTBODY	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)  EXTRA ENC DATA LEN  RESERVED  RCRD 0 DATA, ONLY ON 1ST SEG  R1- RN RECORDS ON TRACK
0 0 0 2 2 3 7 11 12 16 24	(0) (0) (2) (2) (3) (7) (B) (C) (10) (18)	CHARACTER UNSIGNED CHARACTER 11 UNSIGNED UNSIGNED UNSIGNED CHARACTER CHARACTER CHARACTER CHARACTER	24 16 2 1 1 4 4 4 8 0 Count fi	DTTTRK  DTTHDR  DTTTRKIN  DTTTRKID  DTTIOER  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH  DTTLRCNT  *  DTTXDLEN  *  DTTRODAT  DTTBODY  eld format (in track)	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED I ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)  EXTRA ENC DATA LEN  RESERVED  RCRD 0 DATA, ONLY ON 1ST SEG  R1- RN RECORDS ON TRACK
0 0 0 2 3 7 11 12 16 24	(0) (0) (2) (2) (3) (7) (B) (C) (10) (18)	CHARACTER UNSIGNED CHARACTER 11	24 16 2 1 1 4 4 4 8 0 Count fi	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH  DTTLRCNT   DTTXDLEN  *  DTTR0DAT  DTTBODY  eld format (in track)	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)  EXTRA ENC DATA LEN  RESERVED  RCRD 0 DATA, ONLY ON 1ST SEG  R1- RN RECORDS ON TRACK  Limage data).  CNT, KEY & DATA FIELDS ON TRK
0 0 0 2 2 3 7 11 12 16 24	(0) (0) (2) (2) (3) (7) (B) (C) (10) (18) (0) (0)	CHARACTER UNSIGNED CHARACTER 1111 UNSIGNED SIGNED UNSIGNED CHARACTER CHARACTER CHARACTER STRUCTURE CHARACTER	24 16 2 1 1 4 4 4 8 0 Count fi	DTTTRK  DTTHDR  DTTTRKLN  DTTTRKID  DTTIOER  DTTTCMP  DTTVFRST  DTTINVT  DTTSTAT  DTTCCHH  DTTLRCNT  *  DTTXDLEN  *  DTTRODAT  DTTBODY  eld format (in track)  DTTCKD  DTTCKD	MAPS THE TRACK  HEADER FOR EACH TRACK SEGMENT  LENGTH OF DATA ON TRK  TRACK INDICATORS  I/O ERROR ON TRACK  LAST REC ON TRK IS OVFLO REC (maintained for restore compatibility only, do not set)  IF ON, TRACK COMPRESSED  FIRST VVDS RECORD  INVALID TRACK FORMAT  USER STATISTICAL RECORD  CCHH OF TRACK 2@SVD  LR COUNT FOR THE DS (THIS FIELD IS FILLED IS ON THE LAST DATA CA TRACKS FOR A VS DUMPED BY VSAM I/O)  EXTRA ENC DATA LEN  RESERVED  RCRD 0 DATA, ONLY ON 1ST SEG  R1- RN RECORDS ON TRACK  Timage data).  CNT, KEY & DATA FIELDS ON TRK  COUNT FIELD

Table 18. ADRTAPB Mapping Macro (continued)

OFI	FSET				
Dec	Hex	Type	Len	Name (Dim)	Description
5	(5)	UNSIGNED	1	DTTKELEN	KEY LENGTH
6	(6)	UNSIGNED	2	DTTDATLN	DATA LENGTH
		Ke	y or Data	field mapping (foll	ows count field).
0	(0)	STRUCTURE	*	DTTKD	KEY AND DATA FIELDS
0	(0)	CHARACTER	0	*	
	l	REST OF RECORD	THAT N	MAPS THE TRAILE	R RECORD (follows ADRTAPB).
0	(0)	STRUCTURE	6	DTRTLR	
0	(0)	CHARACTER	6	DTRSERL	VOLUME SERIAL OF FILE (USED FOR PHYSICAL DUMP ONLY) V26
0	(0)	SIGNED	4	DTRRECNT	NUMBER OF LOGICAL RECORDS DUMPED (USED FOR LOGICAL DATA SET DUMP ONLY) V26
4	(4)	CHARACTER	2	*	RESERVED - LOGICAL DUMP
0	(0)	STRUCTURE	4	DTSDHDR	
0	(0)	UNSIGNED	2	DTSDLEN	LEN OF SELF DESC REC
2	(2)	CHARACTER	1	DTSDTYPE	TYPE OF SELF DSC REC
3	(3)	CHARACTER	1	DTSDIND1	SELF DESC REC FLAGS
		1		DTSDLAST	LAST SELF DESC REC
		.111 1111		*	RESERVED
4	(4)	CHARACTER	0	DTSDEND	START SELF DESC REC ON A WORD BOUNDARY
0	(0)	STRUCTURE	356	DTCIPHB	CIPHER BLOCK
0	(0)	CHARACTER	1	DTCFLAG1	ENCRYPTION TYPES
		1		DTCCTDES	CLRTDES
		.1		DTCCA128	CLRAES128
		1		DTCETDES	ENCTDES
		1 1111		*	RESERVED
1	(1)	CHARACTER	3	*	RESERVED
4	(4)	CHARACTER	16	DTCDATAS	SAMPLE DATA
20	(14)	CHARACTER	64	DTCRSAL	RSA LABEL
84	(54)	CHARACTER	256	DTCRDKL	RSA CIPHD DATA LABEL
340	(154)	SIGNED	4	DTCICNT	ITERATION COUNT
344	(158)	CHARACTER	8	DTCSALT	SALT FOR ADRPWKEY
352	(160)	SIGNED	4	DTCRDKLN	RSA CIPHD DATA LAB LN@DDE
	(		nary bi	LOCK. Immediately	follows a self-describing record header
0	(0)	STRUCTURE		DTCDCT	FOLLOWS A DTSDHDR
0	(0)	CHARACTER	16	DTCFLDS	
0	(0)	SIGNED	4	DTCMAXD	MAX DICT SIZE
4	(4)	CHARACTER	12	*	RESERVED
0	(0)	STRUCTURE	*	DTCDICT	EXPANSION DICTIONARY AFTER DTCDCT
0	(0)	CHARACTER	0	*	AREA
	· · · · /		VOLUMI	E RECORD FOUND	IN FIRST TAPE RECORD
0	(0)	STRUCTURE		DTSDEVOL	EXTENDED VOL SD REC
0	(0)	SIGNED		DTELOGCYL	# OF CYLINDERS - EAV
4	(4)	UNSIGNED	2	DTELCYL	LARGE UNIT REGION
6	(6)	CHARACTER	2	*	RESERVED

Table 18. ADRTAPB Mapping Macro (continued)

OFI	FSET				
Dec	Hex	Type	Len	Name (Dim)	Description
8	(8)	UNSIGNED	4	DTCBITM#	SIZE OF CHUNK MAP
12	(C)	CHARACTER	4	*	RESERVED
16	(10)	UNSIGNED	8	DTEVBLOCKSIZE	OUTPUT BLOCKSIZE
16	(10)	UNSIGNED	4	DTEVHIBLKSZ	HIGH WORD BLKSIZE
20	(14)	UNSIGNED	4	DTEVBLKSZ	LOW WORD BLKSIZE WHEN DTVBLKSZ=X'FFFE'
24	(18)	BIT(8)	1	DTEFLGS	EXT VOLUME FLAG BYTE
		1		DTERESET	RESET SPECIFIED ON DUMP
		.1		DTECYLMG	CYLINDER MANAGED SPACE
		1		DTEVZCOMP	ZCOMPRESS SPECIFIED
		1 1111		*	RESERVED
25	(19)	CHARACTER	27	*	RESERVED
		EXTENDE	D TAPE 1	RECORD FOUND IN	FIRST TAPE RECORD
0	(0)	STRUCTURE	52	DTSDEHDR	EXT TAPE SD RECORD
0	(0)	UNSIGNED	8	DTEHBLOCKSIZE	OUTPUT BLOCKSIZE
0	(0)	UNSIGNED	4	DTEHHIBLKSZ	HIGH WORD BLKSIZE
4	(4)	UNSIGNED	4	DTEHBLKSZ	LOW WORD BLKSIZE WHEN DTHBLKSZ=X'FFFE'
8	(8)	BIT(8)	1	DTETFLGS	EXT TAPE FLAG BYTE
		1		DTETZCOMP	ZCOMPRESS SPECIFIED
9	(9)	CHARACTER	43	*	RESERVED
0	(0)	STRUCTURE	64	BFRPREFX	BUFFER PREFIX AREA@V22H
0	(0)	UNSIGNED	2	BPSCOC	OFFSET IN BUFFER FROM BEGINNING OF RODATA TO COUNT FIELD IN ERROR
2	(2)	UNSIGNED	2	BPSCOD	OFFSET IN BUFFER FROM BEGINNING OF RODATA TO DATA FIELD IN ERROR
4	(4)	SIGNED	4	BPHWMRK	ADDRESS OF NEXT AVAILABLE BYTE (HIGH WATER MARK OF USED STORAGE)
8	(8)	CHARACTER	56	BPWORKA	WORK AREA FOR OPTIMIZE@V22H
64	(40)		0	BPBODY	LOCATION OF REST OF BUFFER
0	(0)	STRUCTURE	*	DSAUTHR	AUTHORIZATION RECORD.
0	(0)	CHARACTER	0	*	
0	(0)	STRUCTURE	68	DTCHKSUM	CHECKSUM RECORD
0	(0)	CHARACTER	1	DTCKTYPE	TYPE OF CHECKSUM
		1		DTCK_MD5	MD5 HASH
		.111 1111		**	UNUSED
1	(1)	CHARACTER	3	*	UNUSED
4	(4)	CHARACTER	64	DTCKHASH	HASH VALUE
4	(4)	CHARACTER	16	DTCK_MD5HASH	MD5 HASH VALUE
		•			-
0	(0)	STRUCTURE	*	DTLDSCMP	COMPRESSED DATA SET NAME
0	(0)	CHARACTER	0	*	
	1	M	lapping o	f sphere information (	(in DTSAIXS).
0	(0)	STRUCTURE	*	DTSAIXS	AIX SPHERE INFO
0	(0)	CHARACTER	0	*	
	<u> </u>				1

Table 18. ADRTAPB Mapping Macro (continued)

OF	FSET							
Dec	Hex	Type	Len	Name (Dim)	Description			
0	(0)	STRUCTURE	*	DTSPATHD	START PATH SECURITY INFO			
0	(0)	CHARACTER	0	*				
	Self-Describing Record constants CIPHER BLOCK RECORD							
"1"	"1" "CHAR HEX" "01" DTSDCIPH CIPHER BLOCK SD REC				CIPHER BLOCK SD REC			
	COMPRESSION DICTIONARY RECORD							
"1"   "CHAR HEX"		"02"	DTSDCDCT	COMPRESSION DICT SELF-DESC REC TYPE				
EXTENDED ADDRESSABLE VOLUME RECORD								
"1" "CHAR HEX"		"03"	DTSDVOLE	EXTENDED VOLUME SELF-DESC REC TYPE				
EXTENDED DATA SET RECORD								
"1" "CHAR HEX"		"04"	DTSDHDRE TAPE HDR EXTENSION SELF-DESC REC TYPE					
CHECKSUM RECORD								
"1" "CHAR HEX"		"05"	DTSDCHKSUM	CHECKSUM SELF-DESC REC TYPE				
"2"	"DECIMA	L"	"1"	DTPVERC	Version			

## **ADRTAPB** constants

Table 19. ADRTAPB Mapping Macro

Length	Type	Value	Name	Description
1	CONSTANT	X'01'	DTSDCIPH	CIPHER BLOCK SELF DESCRIBING RECORD CONSTANT
1	CONSTANT	X'02'	DTSDCDCT	COMPRESSION DICTIONARY SELF DESCRIBING RECORD CONSTANT
1	CONSTANT	X'03'	DTSDVOLE	EXTENDED VOLUME SELF-DESC REC TYPE
1	CONSTANT	X'04'	DTSDHDRE	TAPE HEADER EXTENSION SELF-DESC REC TYPE

## **ADRTAPB** cross-reference

Name	Hex Offset	Hex Value
ADRTAPB	0	
BFRPREFX	0	
BPBODY	40	
BPHWMRK	4	
BPSCOC	0	
BPSCOD	2	
BPWORKA	8	
DSAUTHR	0	
DTBADDR	4	
DTBBITM	0	
DTBBMID	0	

Name	Hex Offset	Hex Value
DTBHDR	0	
DTBTMR	0	
DTBTRK#	8	
DTBTRK#P	8	
DTC#DIRB	8	
DTCBITM#	8	
DTCCA128	0	40
DTCCTDES	0	80
DTCDATAS	4	20
DTCDCT	0	
DTCDFATT	0	
DTCDFIND	4	
DTCDICT	0	
DTCETDES	0	20
DTCFLAG1	0	
DTCFLDS	0	
DTCHURPN	0	
DTCICNT	154	
DTCIPHB	0	
DTCMAXD	0	
DTCRDKL	54	
DTCRDKLN	160	
DTCRSAL	14	
DTCSALT	158	
DTDAIXSP	69	80
DTDALIAS	6	04
DTDCAT	F	
DTDCATLN	1	
DTDCDF	69	40
DTDDSN	3B	
DTDDSORG	2	
DTDIND	6	
DTDIND2	69	
DTDIPWD	6	80
DTDIRACF	6	20
DTDLEN	0	
DTDNOIDX	69	04
DTDNTALL	69	10
DTDNVOL	5	
DTDOPTCD	4	
DTDPDSE	69	20

Name	Hex Offset	Hex Value
DTDPDSET	69	02
DTDPDSEX	4	80
DTDPWD	7	
DTDRACFD	6	10
DTDRACFG	6	08
DTDRACFP	6	18
DTDSAI	69	08
DTDSAID	4	
DTDSAIDL	0	
DTDSAIR	0	
DTDSDM	69	01
DTDSHDR	0	
DTDSMS	6	01
DTDSPER	6	02
DTDTPWD	6	40
DTDVCTD	67	
DTDVCTI	68	
DTDVOLCT	67	
DTEDSBLKSZ	4	
DTEDSBLOCKSIZE	0	
DTEDSHIBLKSZ	0	
DTELCYL	4	
DTELOGCYL	0	
DTEVBLKSZ	14	
DTEVBLOCKSIZE	10	
DTEVHIBLKSZ	10	
DTHBLKSZ	D	
DTHDAY	0	
DTHDR	0	
DTHEFSAM	11	08
DTHFCMP	11	80
DTHFHCMP	11	10
DTHGNVI	8	80
DTHGT64K	8	20
DTHGVI	8	40
DTHIND1	11	
DTHIND2	8	
DTHLEN	9	
DTHLVLNO	С	
DTHNDS	F	
DTHSFER	11	20

Name	Hex Offset	Hex Value
DTHTIMD	0	
DTHTIME	4	
DTHUNLCD	11	40
DTHVERNO	В	
DTLCAT	1	
DTLDSCMP	0	
DTLDSN	0	
DTLLEN	0	
DTM#DSCB	19	
DTM#EXT	1A	
DTM#VVRS	18	
DTMBWOT	16	08
DTMCVAF	16	20
DTMDEVTY	6	
DTMIND	16	
DTMLOGCY	10	
DTMMAXCB	14	
DTMMINI	16	40
DTMMODNO	1B	
DTMTIME	16	10
DTMTRKCP	С	
DTMTRKCY	12	
DTMVDATA	0	
DTMVIRT	16	80
DTMVOL	0	
DTMVOLSZ	С	
DTMVSERL	0	
DTPBODY	10	
DTPBTM	A	40
DTPBWOE	В	08
DTPDASDD	9	20
DTPDATA	A	08
DTPDDDSP	В	40
DTPDDISP	В	80
DTPDMPID	9	
DTPDSHDR	A	20
DTPDSNL	A	40
DTPDTRLR	A	04
DTPDUMPC	В	04
DTPENDKR	В	10
DTPENDNT	В	20

Name	Hex Offset	Hex Value
DTPFULD	9	80
DTPLOGCL	9	10
DTPNOSEG	4	
DTPPARTD	9	40
DTPPFXLN	8	
DTPRCFL1	В	
DTPRCID1	A	
DTPSCHK	0	
DTPSEGLN	6	
DTPSEGNO	5	
DTPSELFD	В	02
DTPSEQNO	0	
DTPSPHDR	A	01
DTPTHDR	A	80
DTPTRK0	A	20
DTPVER#	С	
DTPVHDR	A	80
DTPVOLD	A	10
DTPVTOC	A	10
DTPVTRLR	A	04
DTPVVDS	A	02
DTRRECNT	0	С
DTRSERL	0	
DTRTLR	0	
DTSAIXNM	0	
DTSAIXS	0	
DTSAUTHR	32	
DTSAUTNM	2A	
DTSCNTLP	8	
DTSCODEN	20	
DTSDEDS	0	
DTSDEND	4	
DTSDEVOL	0	
DTSDHDR	0	
DTSDIND1	3	
DTSDLAST	3	80
DTSDLEN	0	
DTSDTYPE	2	
DTSERDAY	63	
DTSEXCNY	65	
DTSEXPIR	62	

Name	Hex Offset	Hex Value
DTSEYEAR	62	
DTSINFO	0	
DTSLEN	0	
DTSMSTRP	0	
DTSNUMAT	28	
DTSPASSW	0	
DTSPATHA	58	
DTSPATHD	0	
DTSPATHE	59	40
DTSPATHF	59	
DTSPATHI	59	80
DTSPATHN	2C	
DTSPATHP	59	20
DTSPHERE	0	
DTSPRACF	59	18
DTSPTHEP	62	
DTSPTHON	5A	
DTSRACFD	59	10
DTSRACFG	59	08
DTSREADP	18	
DTSUPDAT	10	
DTTBODY	18	
DTTCCCHH	0	
DTTCCHH	3	
DTTCCHHR	0	
DTTCKD	0	
DTTCNT	0	
DTTCRCRD	4	
DTTDATLN	6	
DTTHDR	0	
DTTINVT	2	08
DTTIOER	2	80
DTTKD	0	
DTTKELEN	5	
DTTLRCNT	7	
DTTR0DAT	10	
DTTSTAT	2	04
DTTTCMP	2	20
DTTTRK	0	
DTTTRKID	2	
DTTTRKLN	0	

Name	Hex Offset	Hex Value
DTTTROVF	2	40
DTTVFRST	2	10
DTTXDLEN	В	
DTVBLKSZ	С	
DTVBMSZ	25	
DTVCPVOL	24	10
DTVCVAF	24	20
DTVDAY	17	
DTVDEVTY	1F	
DTVEND	0	
DTVFCMP	24	08
DTVFHCMP	27	02
DTVGNVI	27	20
DTVGVI	27	10
DTVIND1	24	
DTVIND2	27	
DTVLEN	28	
DTVLNVI	27	80
DTVLOGCY	8	
DTVLVF	24	02
DTVLVI	27	40
DTVLVLNO	2B	
DTVMAXCB	Е	
DTVMINI	24	40
DTVMODNO	23	
DTVOL	0	
DTVOLSZ	8	
DTVSERL	10	
DTVSMS	27	08
DTVSMSI	27	04
DTVTIMD	17	
DTVTIME	1B	
DTVTOCB	0	
DTVTOCE	4	
DTVTRKCY	A	
DTVUNLCD	24	04
DTVVERNO	2A	
DTVVIRT	24	80
DTVVTOCI	16	
DTVVVDS	24	01
DTVVXLEN	0	

Name	Hex Offset	Hex Value
DTVVXTNO	2C	
DTVVXTNT	0	
DTVVXTOF	2D	

# Chapter 14. DFSMSdss patch area

This topic describes how to customize certain DFSMSdss functions by setting flags in ADRPATCH, a module in the DFSMSdss load module (ADRDSSU). You can set the flags in ADRPATCH dynamically through the DFSMSdss SET PATCH auxiliary command, or you can set them in ADRPATCH permanently through the AMASPZAP program.

The SET PATCH offset=value command specifies that DFSMSdss set the patch byte, at the specified offset to the specified value. You must have READ access authorization to that profile to use the SET PATCH command. Your installation can limit use of the SET PATCH command with the RACF FACILITY class profile STGADMIN.ADR.PATCH.

The following sample JCL sets the flags in ADRPATCH. The specific offsets and values of the flags are explained in the sections that follow. For the mapping of the flags in ADRPATCH, see the ADRPTCHB data area description in Table 20 on page 242.

## Sample JCL

As an alternative to using the above JCL to set flags in ADRPATCH, you can customize certain DFSMSdss functions by temporarily setting patch bytes during DFSMSdss processing through a SET PATCH command. For information about the SET command, see "Controlling task processing" on page 504.

## Forcing the use of preallocated VSAM data sets (PN04574)

You can force the use of preallocated VSAM data sets by setting the flag at offset X'08' in ADRPATCH. The settings are:

**X'00'** DFSMSdss functions normally, deleting and reallocating VSAM data sets, as necessary, before restoring data to them.

#### Any setting other than X'00'

During a logical RESTORE of VSAM data sets to preallocated targets, DFSMSdss unconditionally uses the preallocated data sets without deleting and reallocating them. DFSMSdss also assumes the targets are reusable and resets the high use RBA to 0 during OPEN if the target data sets are not empty. You can ensure that the preallocated targets are defined using the REUSE attribute.

**Note:** If you want DFSMSdss to restore a single-volume VSAM data set to multiple volumes, the preallocated target data set must have the reusable attribute and have data allocated across multiple primary volumes. DFSMSdss will not recognize candidate volumes.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on (for example, X'FF') permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
   NAME ADRDSSU ADRPATCH
   VFR
        98
                   00
   REP
                   FF
```

## Ignoring VSAM duplicate key errors (PN05529)

If you set the flag at offset X'09' in ADRPATCH on (any value other than X'00'), DFSMSdss provides a serviceability aid that determines which records have duplicate keys. DFSMSdss restores all records of a keyed VSAM data set, ignoring any duplicate key error conditions that have occurred.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on (for example, X'FF') permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
  VER
       09
                  00
  REP
        09
                  FF
```

You can set a slip trap and use generalized trace facility (GTF) as follows:

1. Use AMBLIST to locate the displacement (xxxx) of label ADRSLIP1 within ADRDSSU. The displacement of label ADRSLIP1 is used in setting the slip trap.

```
//AMBLIST JOB...
//* SAMPLE JCL TO LOCATE THE DISPLACEMENT OF LABEL ADRSLIP1
//* WITHIN ADRDSSU. THE DISPLACEMENT OF ADRSLIP1 IS NEEDED
//* TO SET THE SLIP TRAP.
//*********************************
//LISTIT EXEC PGM=AMBLIST
//SYSPRINT DD SYSOUT*
//SYSLIB DD DISP=SHR,DSN=LIBNAME.LINKLIB
//SYSIN DD *
```

2. Set a slip trap from the system console. The displacement label of ADRSLIP1 obtained with AMBLIST is 'xxxx'. Registers 7 and 8 must be used as shown below:

```
SLIP SET, IF, ACTION=TRACE, TRDATA=(STD, 7R?, 8R?),
PVTMOD=(ADRDSSU,xxxx),JOBNAME=nnnnnnn,END
```

**3**. Start the GTF trace at the system console:

- a. Enter S GTF.
- b. Respond **TRACE=SLIP,USR** to message AHL125A ("SPECIFY TRACE OPTIONS").
- c. Respond U to message AHL125A ("RESPECIFY TRACE OPTIONS OR REPLY U").
- d. Run the DFSMSdss job.
- **e**. Use the Interactive Problem Control System (IPCS) to analyze the GTF trace output to determine which records are in error.

#### Note:

- 1. The duplicate key error occurs only after the first record with a duplicate key gets written to the data set. Second and subsequent records with the same key are recognized as duplicates.
- 2. Only the first 65 535 bytes of each duplicate record can be written to the trace data set.

# Modifying the timeout period for enqueue lockout detection (PL84514)

The timeout period for enqueue lockout detection is 90 seconds. You can customize the timeout period by setting the halfword at offset X'0A' in ADRPATCH to the number of seconds to wait. Setting the field to X'FFFF' disables enqueue lockout detection.

To set the timeout period dynamically, use the SET PATCH command. To set the timeout period permanently, (for example, 120 seconds), modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 0A 0000
REP 0A 0078
```

To disable lockout detection, use the SET PATCH command or modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 0A 0000
REP 0A FFFF
```

# Controlling the wait/retry time for serialization of system resources (PN11523)

For system resources (such as the VTOC or VVDS), the default wait time is 3 seconds and the default retry count is 30. Therefore, the total default wait time is 90 seconds. To modify these defaults, you must set the byte at each of the following offsets:

- **X'0D'** An indicator that new wait/retry values are specified. Any nonzero value is valid.
- X'0E' The new wait time in seconds. Valid values are X'00' through X'FF' (0 255).
- **X'0F'** The new retry count. Valid values are X'00' through X'FF' (0 255).

To have DFSMSdss use a wait time of 60 seconds and a retry count of 10 (for a total wait time of ten minutes), do one of the following:

- Use the SET PATCH command to set the wait/retry time dynamically
- Modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
DD *
//SYSIN
  NAME ADRDSSU ADRPATCH
  VER
         000D
                 000000
                             /* Verify all three bytes are zero */
  REP
         000D
                 FF
                             /* Set indicator flag to nonzero */
  REP
         000E
                 3C
                             /* Set wait time to 60 seconds
                                                                */
  REP
         000F
                 0Α
                             /* Set retry count to 10
                                                                 */
```

# Using CONVERTV on data sets with a revoked user ID in the RESOWNER field (OY59957)

DFSMSdss lets you perform CONVERTV operations on data sets that have a revoked user ID, in the RESOWNER field in the profile. The byte at offset X'11' in ADRPATCH can be used to give that resource owner authority to the SMS constructs.

To use ADRPATCH to set the revoked RESOWNER on, set the byte at offset X'11' in module ADRPATCH to a X'FF'. You can use the SET PATCH command to set the patch byte dynamically or modify the sample JCL (see "Sample JCL" on page 217) as follows to set the patch byte permanently:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 11 00
REP 11 FF
```

#### Note:

- 1. Catalog APAR OY56724 must be applied for this fix to work for VSAM data sets.
- 2. Normal DFSMSdss COPY and RESTORE processing is not changed to bypass MGMTCLAS and STORCLAS authorization checking. See "Bypassing storage and management class authorization checking during RESTORE (OY65348)" on page 222.

## Restoring inconsistent PDSE data sets (OY60301)

If during a logical restore operation, DFSMSdss cannot tell if the data set is a PDS or a PDSE, it issues message ADR793E, indicating that the data set is an inconsistent PDSE. Setting the flag at offset X'12' in ADRPATCH tells DFSMSdss how to process these data sets during the restore. The settings are listed below:

X'01' DFSMSdss tries to restore the data set as a PDSE. Before the attempt, DFSMSdss issues message ADR794W to warn you that DFSMSdss assumes that the data set to be restored is a PDSE.

## Note:

- 1. If the data set is a PDS and you try to restore it as a PDSE, it will be unusable.
- 2. If you try to restore the data set to an unlike device, the restore fails and DFSMSdss issues message ADR792E, indicating to which device type the data set must be restored.
- 3. If you try to restore the data set to a preallocated target data set, the restore fails because DFSMSdss does not recognize the preallocated data set as usable.

X'02' DFSMSdss tries to restore the data set as a PDS. Before the attempt,

DFSMSdss issues message ADR794W to warn you that DFSMSdss assumes that the data set to be restored is a PDS.

The data set is restored only if it is a PDS.

#### Any setting other than X'01' or X'02'

DFSMSdss does not restore the data set and issues message ADR793E.

To set the patch byte value dynamically, use the SET PATCH command. To set the patch byte value permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 12 00
REP 12 01
```

## Changing default protection status during RESTORE (PN37489)

By default, DFSMSdss maintains the protection status of the data set during a logical RESTORE. If the source data set was protected by RACF, a component of the Security Server for z/OS, at dump time, the target data set is RACF-indicated at restore time.

This function is affected by setting the flag at offset X'13' in ADRPATCH. The settings are listed below:

**X'00'** DFSMSdss functions as previously described.

#### Any setting other than X'00'

DFSMSdss does not RACF-indicate the target data set during a logical RESTORE, even if the source data set was RACF-indicated at dump time, the MENTITY keyword was not specified, and the target data set was protected by a generic profile.

To set the flag to <u>on</u> dynamically, use the SET PATCH command. To set the flag to <u>on</u> permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 13 00
REP 13 FF
```

# Restoring or copying undefined, multivolume SMS-managed data sets (OY63818)

Messages ADR709E and IGD17040I might be received when copying or restoring the following types of non-VSAM, multivolume data sets:

- Empty, multivolume data sets dumped with the ALLEXCP keyword
- Undefined data sets
- TTR-organized BDAM data sets
- Data sets with BLKSIZE=0

This function is affected by setting the flag at offset X'14' in ADRPATCH. The settings are listed below:

X'00' DFSMSdss functions normally; these data sets are allocated as multivolume data sets.

#### Any setting other than X'00'

These data sets are allocated as single volume data sets.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
   VFR
                   FF
   REP
         14
```

## Bypassing backup-while-open processing (OY63531)

When DFSMSdss encounters a data set marked as backup-while-open (BWO) eligible, DFSMSdss processes it accordingly. If the BWO indication is on erroneously, the BWO processing may be bypassed for a logical data set dump.

This function is affected by setting the flag at offset X'15' in ADRPATCH. The settings are listed below:

X'00' BWO processing is performed.

#### Any setting other than X'00'

BWO processing is bypassed.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
   VER
        15
   REP
         15
                   FF
```

# Bypassing storage and management class authorization checking during RESTORE (OY65348)

For a logical RESTORE and a physical data set restore, storage class and management class authorization checking is normally conducted. This checking can be bypassed to let the storage administrator restore data sets that are protected by data set profiles whose RESOWNER field contains a user ID that has been revoked.

This function is affected by setting the flag at offset X'16' in ADRPATCH. The settings are listed below:

DFSMSdss functions normally and conducts authorization checking.

#### Any setting other than X'00'

Authorization checking is bypassed.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
   VER
        16
                   FF
   REP
         16
```

## Issuing notification for tape and migrated data sets (OY66092)

On a logical data set copy or dump, a data set can be specified with a partially qualified name. If that name resolves to a data set cataloged to tape or to a migrated data set, DFSMSdss does not issue a warning message that the data set was not selected.

This function is affected by setting the flag at offset X'17' in ADRPATCH. The settings are listed below:

X'00' DFSMSdss functions normally and issues no warning message.

#### Any setting other than X'00'

DFSMSdss issues a warning message.

To set the flag to <u>on</u> dynamically, use the SET PATCH command. To set the flag to <u>on</u> permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 17 00
REP 17 FF
```

## **Using RESET with concurrent copy (OY65555)**

The RESET keyword specifies that DFSMSdss resets the data-set-changed indicator for data sets after the dump is complete. By default, the RESET keyword is ignored when the CONCURRENT keyword is also specified with the DUMP command.

Setting the byte at offset X'18' in ADRPATCH to a nonzero value causes DFSMSdss to perform RESET processing when both the RESET and CONCURRENT keywords are specified with the DUMP command. In this case, the data-set-changed indicator is reset after concurrent copy initialization is complete and before the data set is written to the output.

To dynamically enable RESET processing with concurrent copy, use the SET PATCH command. To enable RESET processing with concurrent copy permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 18 00
REP 18 FF
```

After the data-set-changed indicator has been reset, if the concurrent copy dump is unsuccessful for any reason, the data-set-changed indicator for the data set remains reset even though you might not have a usable dump of the data. For this reason, you must carefully evaluate the risks of using this patch to enable RESET processing with concurrent copy. Rather than using this patch to accomplish incremental backup in DFSMSdss with concurrent copy, use DFSMShsm instead.

In the event that the data-set-changed indicators have been reset and the dump subsequently fails, your recovery action can be either of the following:

- Turn the data-set-changed indicators back on by using AMASPZAP.
- Dump the data again. Because the data-set-changed indicators are still off, you must not specify "BY(DSCHA,EQ,YES)" in the dump command.

## Forcing RESTORE after message ADR482E (OY67532)

If message ADR727E was received while DFSMSdss was dumping an SMS-managed user catalog with aliases, the dump tape might be unusable and message ADR482E might be received during RESTORE. If you set the flag at offset X'19' in ADRPATCH on, DFSMSdss forces the restore to continue after receiving message ADR482E.

**Note:** If you use the AMASPZAP program to set the patch permanently, turn off this patch after restoring the problem dump tape, so that legitimate message ADR482E condition are detected.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
   VER
       19
                   FF
   REP
```

# Restoring VSAM KSDS or VRRDS after messages ADR789W, ADR364W, and ADR417W (OY67942)

Prior to the fix of APAR OY67724, DFSMSdss sometimes (when using the CONCURRENT and VALIDATE options) created dumps with empty track records for imbedded sequence set tracks and with zero in the total record count dumped for the data set. The sequence set records are not necessary when restoring data sets dumped with VALIDATE. Without patch byte X'1A' on the following messages are generated:

- ADR364W and ADR417W (because of the empty tracks)
- ADR789W (because of the missing record count)

and the restore fails.

If message ADR789W, or message ADR364W and message ADR417W, or all three messages are received during a logical restore of a KSDS or VRRDS from a dump created while using CONCURRENT and VALIDATE either by keyword or by default, you can retrieve your data sets by setting the flag at offset X'1A' in ADRPATCH and rerunning the restore job. The settings are listed below:

X'00' DFSMSdss functions normally. It fails to restore data sets that have errors in the dump.

#### Any setting other than X'00'

During a logical RESTORE of a KSDS or VRRDS, if DFSMSdss detects an empty record in the dump or a missing count of the total number of records dumped for the data set, or both, it restores all of the data for the data set in the dump and keeps the resulting data set. You still get message ADR789W with a valid output record count. You can compare this valid output record count to the record count from message ADR788I from the dump job to ensure DFSMSdss has retrieved all the data.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 1A 00
REP 1A EF
```

## Restoring VSAM data sets with expiration date of 1999365 (OW00780)

Prior to the fix of APAR OW00780, DFSMSdss sometimes mishandled VSAM expiration dates during logical data set DUMP and RESTORE operations. Non-SMS VSAM data sets that had an expiration date of 1999365 were dumped and restored with no expiration date (an expiration date of 0000000).

The byte at offset X'1B' of module ADRPATCH has been defined to allow special processing for VSAM data sets with an expiration date of 1999365 that were dumped without the fix for OW00780. The possible settings for the flag byte are listed below:

X'00' Non-SMS VSAM data sets that had an expiration date of 1999365 and that were dumped without the fix for OW00780 are restored with no expiration date.

X'FF' Any non-SMS VSAM data set that had an expiration date of 1999365 and that was dumped without the fix for OW00780 are restored with an expiration date of 1999365. However, non-SMS VSAM data sets that originally had no expiration date are also restored with an expiration date of 1999365.

**Note:** This flag byte should only be used when restoring VSAM data sets dumped without the APAR OW00780 fix and with an expiration date of 1999365.

To set the flag to <u>on</u> dynamically, use the SET PATCH command. To set the flag to <u>on</u> permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 1B 00
REP 1B FF
```

# Restoring VSAM data sets with expiration dates beyond 2000 (OW00780)

Prior to the fix of APAR OW00780, DFSMSdss sometimes mishandled VSAM expiration dates during logical data set DUMP and RESTORE operations. Data sets that had expiration dates in the year 2000 or beyond were dumped and restored as though they had expired in the 1900s.

The byte of offset X'1C' of module ADRPATCH has been defined to allow special processing for VSAM data sets with expiration dates in the year 2000 or beyond that were dumped without the fix of OW00780. The possible settings for the flag byte are listed below:

**X'00'** Any VSAM data sets that expired in the years 20nn or 21nn and that were dumped without the fix for OW00780 are restored with an expiration date of 19nn.

X'FF' Any VSAM data set that was dumped with an expiration date less than 1980 will have 100 years added to the expiration date. This includes not only data sets that were dumped without the fix for OW00780 that had

expiration dates for 2000 to 2080 or from 2100 to 2180, but also any VSAM data set that actually had an expiration date less than 1980.

**Note:** This patch does not yield the correct expiration dates for data sets that expire beyond the year 2100. However, it at least causes the data sets to be restored with an expiration date that has not already passed. Users then have several years to correct the date.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
   NAME ADRDSSU ADRPATCH
  VFR 1C
                   00
                   FF
  REP
        1C
```

# Changing default insertion of EOF track during COPY with ALLDATA specified (OW15003)

When multivolume sequential data sets are copied to a single-volume like device and ALLDATA is specified, the default action inserts an explicit EOF track in the target data set, when required. A patch is provided that allows an installation to change this default. If the patch byte at offset X'1D' of module ADRPATCH is set to X'FF', no explicit EOF track is added to the target data set.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
   VER 1D
                  00
   REP
        1 D
```

## Using RESET or UNCATALOG in a logical data set dump (PN60114)

For a logical data set dump operation, use of the RESET or UNCATALOG keyword causes the enqueue on a data set to be held until all data sets are dumped. DFSMSdss does not reset the data-set-changed indicator or uncatalog the data set until after all data sets are dumped.

This function is affected by setting the flag at offset X'1E' in ADRPATCH. The settings are listed below:

DFSMSdss functions normally as described above.

#### Any setting other than X'00'

DFSMSdss resets the data-set-changed indicator or uncatalog the data set when the data set is dumped. The enqueue on a data set is released after DFSMSdss has completed resetting the data-set-changed indicator or uncataloging the data set.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

//SYSIN DD \*
NAME ADRDSSU ADRPATCH
VER 1E 00
REP 1E FF

# Changing secondary allocation quantity in format 1 DSCB for PDSE data sets (OW07755)

PTFs UW06768 and UW06769 for APAR OW04199 caused the target PDSE secondary allocation quantity (DS1SCAL3) in the Format 1 DSCB to increase or decrease by a ratio of "blocks per track of blocksize" divided by "blocks per track of 4096" during data set COPY and RESTORE processing. As part of the fix to this problem, three pairs of 4-byte fields at offset X'20' through X'37' in ADRPATCH are provided for installations to change the incorrect secondary allocation quantity of an unpreallocated target PDSE during COPY and RESTORE processing. The secondary allocation quantity of the source PDSE is not affected by the patch.

**Note:** Use this patch to change the incorrect secondary allocation quantity resulting from PTFs UW06768 and UW06769. Set the high threshold value with caution to avoid changing the secondary allocation quantity of PDSE data sets that are not affected by PTFs UW06768 and UW06769.

To use this function when the source PDSE is allocated in cylinders, you must modify the 4-byte field at each of the following offsets:

X'20' A nonzero, 4-byte value indicates a threshold in cylinders. DFSMSdss compares the secondary allocation quantity of the source PDSE to this threshold. If the secondary allocation quantity is greater than this threshold, the value set at offset X'24' is used as the secondary allocation quantity in the calculation for the target PDSE.

A zero, 4-byte value indicates this function is not activated.

**X'24'** This value is used as the secondary allocation quantity in cylinders, if applicable.

To use this function when the source PDSE is allocated in tracks, you must modify the 4-byte field at each of the following offsets:

X'28' A nonzero, 4-byte value indicates a threshold in tracks. DFSMSdss compares the secondary allocation quantity of the source PDSE to this threshold. If the secondary allocation quantity is greater than this threshold, the value set at offset X'2C' is used as the secondary allocation quantity in the calculation for the target PDSE.

A zero, 4-byte value indicates this function is not activated.

**X'2C'** This value is used as the secondary allocation quantity in tracks, if applicable.

To use this function when the source PDSE is allocated in blocks, you must modify the 4-byte field at each of the following offsets:

X'30' A nonzero, 4-byte value indicates a threshold in blocks. DFSMSdss compares the secondary allocation quantity of the source PDSE to this threshold. If the secondary allocation quantity is greater than this threshold, the value set at offset X'34' is used as the secondary allocation quantity in the calculation for the target PDSE.

A zero, 4-byte value indicates this function is not activated.

**X'34'** This value is used as the secondary allocation quantity in blocks, if applicable.

You can specify one, two, or all three pairs of values. For example, you should make the modifications shown in the JCL example below to the sample JCL (see "Sample JCL" on page 217) to cause DFSMSdss to do the following:

- Use 250 cylinders as the secondary allocation quantity when the source PDSE is allocated in cylinders and has a secondary allocation quantity greater than 5000 cylinders.
- Use 2500 tracks as the secondary allocation quantity when the source PDSE is allocated in tracks and has a secondary allocation quantity greater than 50 000 tracks.
- Use 12 500 blocks as the secondary allocation quantity when the source PDSE is allocated in blocks and has a secondary allocation quantity greater than 250 000 blocks.

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
  VER
        20
                 00000000
                               /* Verify value is 0
                 00001388
                               /* If > 5000 cylinders */
  RFP
        20
  VER
        24
                 00000000
                                   Verify value is 0
                               /* Then use 250 cyls
  REP
        24
                 000000FA
       28
                 00000000
                               /* Verify value is 0
  VFR
                               /* If > 50000 tracks
  REP
        28
                 0000C350
  VER
       20
                 00000000
                               /* Verify value is 0
  RFP
        20
                 000009C4
                               /* Then use 2500 tracks */
                               /* Verify value is 0
  VER
                 00000000
        30
  REP
        30
                 0003D090
                               /* If > 250000 blocks
                                                        */
  VER
        34
                 00000000
                                    Verify value is 0
  RFP
        34
                 000030D4
                                   Then use 12500 blks
```

**NOTE:** As an alternative, you can use the SET PATCH command to set the patch bytes dynamically

# Changing reference date default settings during data set COPY and RESTORE processing (OW12011)

During RESTORE and COPY operations, source and target data set reference dates remain the same, unless the data set is renamed. However, if you rename the restored or copied data set, the current date (TODAY) replaces the reference date in the target data set's DS1REFD field.

DFSMSdss provides four patch bytes that allow you to change the method of setting the DS1REFD field. Below are the patch bytes:

- If the patch byte at offset X'38' of module ADRPATCH is set to X'FF', the reference date of the target data set that is restored without a rename is set to the current date.
- If the patch byte at offset X'39' of module ADRPATCH is set to X'FF', the reference date of the target data set that is restored and renamed is set to the source data set's reference date.
- If the patch byte at offset X'3A' of module ADRPATCH is set to X'FF', the reference date of the target data set that is copied without a rename is set to the current date.
- If the patch byte at offset X'3B' of module ADRPATCH is set to X'FF', the reference date of the target data set that is copied and renamed is set to the source data set's reference date.

To cause DFSMSdss to set the reference date to the current date for all data sets being copied and restored and not renamed, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 38 00
REP 38 FF
VER 3A 00
REP 3A FF
```

**NOTE:** As an alternative, you can use the SET PATCH command to set the patch bytes dynamically

## Changing default protection processing during COPY (OW10314)

By default, DFSMSdss issues message ADR757E during COPY with DELETE specified if the data set is RACF-indicated, but a discrete profile is not associated with the data set.

This function is affected by setting the flag at offset X'3C' in ADRPATCH. The settings are listed below:

X'00' DFSMSdss functions normally as described above.

#### Any setting other than X'00'

DFSMSdss does not fail the COPY operation with message ADR757E, but allows the data set to be processed and issues either message ADR759W or ADR771W, depending on the SAF return codes.

To set the flag to <u>on</u> dynamically, use the SET PATCH command. To set the flag to <u>on</u> permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 3C 00
REP 3C FF
```

# Bypassing management and storage class access checks during COPY (PN72592)

A COPY operation might not be successful when the owner of the data set does not have read access to the STORCLAS or MGMTCLAS routines that allocate the target data set, even though the ADMINISTRATOR keyword is specified. The ADMINISTRATOR keyword gives access to the data set, not to the automatic class selection (ACS) routines that are used for STORCLAS or MGMTCLAS processing.

This function is affected by setting the flag at offset X'3D' in ADRPATCH. The settings are listed below:

X'00' DFSMSdss functions normally as described above.

#### Any setting other than X'00'

When the ADMINISTRATOR keyword is specified, DFSMSdss causes SMS to bypass access authorization checking to the ACS routines for STORCLAS and MGMTCLAS when allocating the target data set during a COPY operation.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
  VER 3D
                  00
  REP
```

# Changing default handling of invalid tracks created during data set **COPY and RESTORE processing (OW08174)**

When invalid tracks are created during COPY and RESTORE processing, message ADR367E is issued and the invalid tracks are erased from the target volume, regardless of whether CANCELERROR is specified. The copy or restore of the data set ends and the target data set is deleted. The COPY or RESTORE operation continues with the next data set.

A patch byte is provided that allows you to change the default handling of invalid tracks created during COPY and RESTORE processing. If the patch byte at offset X'3E' of module ADRPATCH is set to X'FF', CANCELERROR specification will determine the action taken. When CANCELERROR is specified, the action is to issue message ADR367E and erase the invalid track from the target volume. The restore or copy of the data set receiving the error is terminated and the target data set is deleted. The RESTORE or COPY processing continues with the next data set. When CANCELERROR is not specified, the action is to issue message ADR366W and leave the invalid track on the volume. The RESTORE or COPY operation continues.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
   VER
       3E
                   00
   REP
                   FF
```

## Forcing RESTORE to the same volumes as the source VSAM data set (OW07077)

If a user does not specify output volumes, you can force the RESTORE operation to attempt to return a VSAM data set assigned to an SMS storage class with guaranteed space to the same set of primary volumes that the source data set had occupied when dumped.

This function is affected by setting the flag at offset X'3F' in ADRPATCH. The settings are listed below:

X'00' Unless the user specifies output volumes, RESTORE processing does not pass the source volume list to SMS, and the restored data set probably does not occupy the same primary volumes that the source data set occupied when it was dumped. Because this allows the use of any volumes in the storage group, there is less chance of a failure due to lack of space on volumes.

#### Any setting other than X'00'

Unless the user specifies output volumes, RESTORE processing passes the source volume list to SMS, forcing the restored data set to occupy the same primary volumes that the source data set had occupied when it was dumped, provided that it is assigned to an SMS storage class with guaranteed space. If it will not fit, RESTORE fails processing.

#### Note:

- 1. DFSMSdss cannot ensure that the order of volumes are maintained during a restore of a multivolume data set. SMS determines volume order.
- 2. This patch does not support data sets with candidate space volumes. The restore of such a data set will fail with an ADR709E message.

To set the flag to <u>on</u> dynamically, use the SET PATCH command. To set the flag to <u>on</u> permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 3F 00
REP 3F FF
```

# Modifying number of volumes allocated for SMS data sets during logical RESTORE and COPY (OW15880)

When processing SMS data sets, the total number of volumes DFSMSdss allocates for the target data set is the same as the total number of volumes that were allocated for the source data set, unless the source data set was multivolume and output volumes are specified. When the source data set was multivolume and a list of output volumes is supplied with OUTDDNAME or OUTDYNAM, the number of volumes DFSMSdss allocates is the number of volumes in the volume output list.

The number of output volumes allocated for SMS data sets can be modified by setting an enabling flag at offset X'40' in ADRPATCH and a count value at offset X'41' in ADRPATCH. After the enabling flag is set, the following are true:

- When an output volume list is specified and the patch count value is not zero, the allocated number of volumes is the lesser of either the number of volumes in the output list or the patch count value.
- When an output volume list is specified and the patch count value is zero, the
  allocated number of volumes is the lesser of either the number of volumes in the
  output list, or the allocated number of volumes that were for the source data set.
- When no output volume list is specified, the allocated number of volumes is the greater of either the number of volumes that were allocated for the source data set, or the patch count value.

The patch bytes are defined as follows:

Offset X'40'

X'00' Use current DFSMSdss SMS allocation rules

X'20' Modify DFSMSdss SMS allocation rules

Offset X'41'

The hexadecimal representation of the number of volumes to be used for SMS data set allocation. Any value between 0 and 59 (X'00' through X'3B') can be specified. If a value larger than 59 is specified, the value of 59 (X'3B') is used.

#### Note:

#### **DFSMSdss Patch Area**

- 1. For any keyed VSAM data set, there must be sufficient space for a primary extent on each volume that is to contain data. No space is allocated on candidate volumes.
- 2. For any guaranteed space keyed VSAM data set, there also must be sufficient volumes in the target storage group to provide volume serial numbers for each primary and candidate volume.
- 3. This patch does not modify the number of volumes allocated for data sets whose DSORG is PO (for example, PDS, PDSE and HFS), and does not modify the number of volumes allocated for VSAM linear data sets.
- 4. When this patch is activated, the MAKEMULTI keyword is ignored.

To cause DFSMSdss to use ten volumes for SMS data set allocation, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
   VER 40
                  00
   REP
        40
                  20
   VER
       41
                  00
   RFP
                  ΘΑ
```

**NOTE:** As an alternative, you can use the SET PATCH command to set the patch bytes dynamically

## Dumping a keyed VSAM data set that has data CAs without corresponding index CIs (OW17877)

When a KSDS is logically dumped with DFSMSdss using the VALIDATE option, a check is performed to determine if there are data control areas (CAs)) without corresponding index control intervals (CIs). If there are missing index CIs, ADR970E is issued and the dump of this data set fails.

This function is affected by setting the flag at offset X'42' in ADRPATCH. The settings are listed below:

X'00' DFSMSdss functions normally as described above.

X'01' DFSMSdss issues ADR985W instead of ADR970E when a possible missing index CI condition is detected during logical data set DUMP using the VALIDATE option.

#### Any setting other than X'00' or X'01'

DFSMSdss issues ADR974I instead of ADR970E when a possible missing index CI condition is detected during logical data set DUMP using the VALIDATE option.

**Note:** This patch byte should only be used when you know that the KSDS being dumped has incomplete CA spits. It should be used with caution since if the data set is actually broken, the backup copy could be incomplete. Also, use caution when specifying the DELETE keyword in conjunction with setting this patch byte. If this patch byte is used to allow a KSDS with more data CAs than index CIs to be successfully dumped, the source KSDS will be deleted if the DELETE keyword is also specified.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 42 00
REP 42 FF
```

## Changing the default DEFRAG processing of checkpointed data sets (OW20285)

When DEFRAG selects an extent for movement and the associated data set's FORMAT 1 DSCB in the VTOC has the DS1CPOIT flag set indicating that a checkpoint was taken while the data set was open, DEFRAG cannot relocate the data set extent. Message ADR211I is issued to indicate when this occurs. A patch byte is provided to allow an installation to change the default DEFRAG processing of checkpointed data set extents.

This function is affected by setting the flag at offset X'43' in ADRPATCH. The settings are listed below:

X'00' DFSMSdss functions normally as described above.

#### Any setting other than X'00'

DEFRAG moves selected extents, even when the data set DS1CPOIT flag is set on. Message ADR252I is issued when the patch byte is set on to indicate that the installation is overriding normal DEFRAG processing.

To set the flag to <u>on</u> dynamically, use the SET PATCH command. To set the flag to <u>on</u> permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 43 00
REP 43 FF
```

## Setting the percentage to overallocate target data set space (OW27837)

When restoring an extended-format non-VSAM data set to a device which does not support extended-format, the data set is converted to a nonextended-format. During this type of conversion, DFSMSdss is not able to calculate the exact amount of space that the target data set will require. Therefore, it is possible for the target data set to be underallocated, causing RESTORE to fail with message ADR910E, return code 40000004, reason code 0000000D. To avoid underallocating the target data set, a new patch byte has been created. The hex value set in this patch byte is the percentage to overallocate by. This function is affected by setting the flag at offset X'44' in ADRPATCH.

To use ADRPATCH to overallocate the target data set by a decimal 10%, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 44 00
REP 44 0A
```

#### Note:

- 1. As an alternative, you can use the SET PATCH command to set the patch byte dynamically.
- 2. Set this patch only for those data sets that have failed to convert. Reset the patch to zero after the failing data set is restored, so that other converted data

sets are not needlessly overallocated. Also, the required percentage of overallocated space can vary by data set. In other words, some data sets might require an overallocation of 10%, while some require additional space. Adjust the overallocation percentage, as needed.

## Bypassing RLS processing (OW32817)

For SMS-managed VSAM data sets, DFSMSdss performs serialization that provides data integrity during logical dump and copy in both the RLS and the non-RLS environments. This serialization includes communications with VSAM RLS to determine the type of enqueues to be performed, based on the type of access that the data set is currently being used for by other jobs.

You can bypass the communication between DFSMSdss and VSAM RLS, which results in DFSMSdss performing non-RLS serialization, regardless of how the data set is currently being accessed. Use of this function can compromise data integrity when the data set is being accessed through RLS by some other job while the dump or copy is being performed. Use this function only if you are willing to tolerate the exposure of not having data integrity in order to force the successful completion of the operation or to prevent updates to the data set from failing during the operation.

When the communication between DFSMSdss and VSAM RLS is bypassed, communication with CICS<sup>®</sup> is also bypassed. Therefore, use this function should only in an environment where forward recovery logging and forward recovery is managed entirely by the application.

This function is affected by setting the flag at offset X'45' in ADRPATCH. The settings are listed below:

X'00' DFSMSdss functions normally. The communications with VSAM RLS are performed and DFSMSdss provides RLS or non-RLS serialization accordingly.

#### Any setting other than X'00'

DFSMSdss bypasses RLS processing. The communications with VSAM RLS are not performed and DFSMSdss performs non-RLS serialization.

To set the flag to on dynamically, use the SET PATCH command. To set the flag to on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
  NAME ADRDSSU ADRPATCH
  VER 45
                 00
  RFP
        45
```

## Changing creation date default settings during data set COPY and **RESTORE (OW19618)**

During RESTORE and COPY operations, source and target data set creation dates remain the same, unless the data set is renamed. However, if you rename the restored or copied data set, the current date (TODAY) replaces the creation date in the target data set's DS1CREDT field.

DFSMSdss provides four patch bytes that allow you to change the method of setting the DS1CREDT field. These patch bytes apply only to data sets that are allocated by DFSMSdss (not prealocated data sets). The patch bytes are below:

- If the patch byte at offset X'46' of module ADRPATCH is set to X'FF', the creation date of the target data set that is restored without a rename is set to the current date.
- If the patch byte at offset X'47' of module ADRPATCH is set to X'FF', the creation date of the target data set that is restored and renamed is set to the source data set's creation date.
- If the patch byte at offset X'48' of module ADRPATCH is set to X'FF', the creation date of the target data set that is copied without a rename is set to the current date.
- If the patch byte at offset X'49' of module ADRPATCH is set to X'FF', the creation date of the target data set that is copied and renamed is set to the source data set's creation date.

To cause DFSMSdss to set the creation date to the current date for all data sets being copied and restored and not renamed, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 46 00
REP 46 FF
VER 48 00
REP 48 FF
```

#### Note:

- 1. As an alternative, you can use the SET PATCH command to set the patch bytes dynamically
- 2. For a preallocated target that has F8/F9 DSCBs, the F9 DSCB field DS9CREAT is set ON, and is being scratched and reallocated, these patch byte settings will not be honored. These types of data sets have a field in the F9 DSCB which corresponds to the number of milliseconds past midnight in which the data set was created (DS9TIME). In order for the DS9TIME to be usable, the creation date and the time past midnight of the preallocated target will be preserved as its value prior to scratching.

## Copying and dumping a PDSE data set using the VALIDATE PDSE option (OW48074)

DFSMSdss sometimes invokes the file and attribute management services (FAMS) to process PDSE data sets in logical data set COPY and DUMP operations. By default, DFSMSdss does not enable the FAMS validation option because validation can slow the processing time. However, a DFSMSdss logical COPY or logical DUMP operation with the FAMS validation disabled might not detect a potentially broken PDSE. It might copy or dump the invalid PDSE with return code zero—without processing all members.

To change the VALIDATE PDSE option, set the flag at offset X'4B' in ADRPATCH. Use the following settings:

X'00' DFSMSdss functions without using the FAMS VALIDATE PDSE option.

#### Any setting other than X'00'

DFSMSdss functions using the FAMS VALIDATE PDSE option.

**Note:** This patch byte is only valid for logical COPY and DUMP operations when you do not specify the CONCURRENT keyword.

#### **DFSMSdss Patch Area**

You can use the SET PATCH command to set the patch byte at offset X'4B' to X'FF', or you can modify the sample JCL (see "Sample JCL" on page 217) as shown below:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 4B
                00
 REP
                FF
```

## Changing the default maximum number of active parallel subtasks

During processing in PARALLEL mode, DFSMSdss limits the number of active subtasks to avoid exhausting virtual storage in the DFSMSdss address space. When the number of active parallel subtasks reaches the DFSMSdss determined value, DFSMSdss waits for any executing subtasks to complete before scheduling a new subtask.

This function is affected by setting the one byte field at offset X'4C' in ADRPATCH. The settings are listed below:

DFSMSdss functions normally as described above. The maximum number of active parallel substasks is determined by DFSMSdss.

#### Any setting from X'01' to X'FF'

Specifies the maximum number of active subtasks that DFSMSdss should allow to execute in parallel.

To override the default dynamically, you can use the SET PATCH command to set the patch byte at offset X'4C' to any value from X'01' through X'FF'. To override the default permanently (for example, to allow a maximum of X'32' active parallel subtasks), modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
 NAME ADRDSSU ADRPATCH
 VER 4C
                 00
  REP
       4C
                 32
```

## Changing the default initialization processing during DUMP with FCWITHDRAW (OA18929)

For a DUMP FULL or DUMP TRACKS operation, DFSMSdss invokes ICKDSF to initialize the source volume of the DUMP operation at the end of the dump processing when all of the following conditions are met:

- FCWITHDRAW is specified
- The VTOC tracks on the source volume of the DUMP operation are the target of a FlashCopy relationship
- The TRACKS keyword, if specified, designates one extent range that represents the entire volume
- The volume is not a VM-format volume (CP volume)
- The volume supports data set FlashCopy or space efficient FlashCopy.

You can control this function by setting the flag at offset X'4D' in ADRPATCH. The valid settings are:

DFSMSdss functions as described in this topic.

#### Any setting other than X'00'

DFSMSdss does not initialize the source volume when a DUMP FCWITHDRAW operation completes.

To set the flag <u>on</u> dynamically, use the SET PATCH command to set the patch byte at offset X'4D' to a value of X'FF'. To set the flag to <u>on</u> permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 4D 00
REP 4D FF
```

**Note:** For a space efficient volume, DFSMSdss issues an informational message when all of the following conditions are true:

- This patch byte is set
- The volume is the target of a FlashCopy relationship
- FCWITHDRAW is specified for the FlashCopy relationship.

The message indicates that the physical space on the space efficient volume remains allocated. To release the physical space, you must initialize the volume through the ICKDSF INIT command.

For more information about FCWITHDRAW and volume initialization processing, see "FCWITHDRAW" on page 406.

## Changing the default DEFRAG processing of LINKLIST-indicated data sets (OW43874)

During DEFRAG operations, DFSMSdss does not relocate extents for data sets that are LINKLIST-indicated. Installations must be able to indicate to DEFRAG that it must move such extents. This capability is most likely to be needed for volumes that have been cloned and where the linklist data sets contained on the cloned volume are not being used in a production environment.

DFSMSdss provides a patch byte to allow you to change the DEFRAG command default processing of LINKLIST-indicated data set extents. This patch byte is honored only when the SET PATCH command sets it on, dynamically.

This function is affected by setting the flag at offset X'4E' using the SET PATCH command. The settings are:

**X'00'** DFSMSdss functions normally. DEFRAG does not relocate extents for data sets that are LINKLIST-indicated.

#### Any setting other than X'00'

DEFRAG command processing then moves as needed, any selected extents of a LINKLIST-indicated data set that are contained on the volume. This occurs, even if you cannot obtain serialization for the data set.

DFSMSdss issues message ADR254I during function task start-up. Message ADR254I indicates that the DEFRAG command is using the installation patch byte to override the normal default processing of LINKLIST-indicated data sets.

**Recommendation:** Due to the possible misuse of this capability, you might want to restrict its use. The patch byte is honored only when the SET PATCH command sets it on, dynamically. You can restrict who can dynamically set patch bytes with the SET PATCH command. To do this, use a RACF FACILITY class that requires read access to STGADMIN.ADR.PATCH. In addition, use a RACF FACILITY class that requires read access to STGADMIN.ADR.DEFRAG to restrict the use of the DEFRAG command.

## Changing the FASTREPLICATION default setting during Copy and Defrag (OA11637)

During DEFRAG and COPY operations, fast replication method is used when it can be; this is considered FASTREPLICATION(PREFERRED) which is the DFSMSdss default setting when the FASTREPLICATION keyword is not specified. The FASTREPLICATION keyword overrides this default.

DFSMSdss now provides a patch byte that allows you to change this default setting to not use fast replication unless you specify FASTREPLICATION(PREFERRED) or FASTREPLICATION(REQUIRED).

The FASTREPLICATION default is affected by setting the flag at offset X'4F' in ADRPATCH. The settings are:

**X'00'** If the FASTREPLICATION keyword is not specified, thenDFSMSdss processes as if the FASTREPLICATION(PREFERRED) keyword was specified.

#### Any setting other than X'00'

If the FASTREPLICATION keyword is not specified, DFSMSdss processes as if the FASTREPLICATION(NONE) keyword was specified.

**Note:** The Options Installation Exit Routine, ADRUIXIT, allows the final override to the FASTREPLICATION setting. In this exit there is no indication that the FASTREPLICATION setting is the default or if the keyword is specified.

To set the flag on (for example, X'FF'), modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 4F 00
REP 4F FF
```

## Tuning hardware assisted compression (OA13300)

You can tune hardware assisted compression to improve the performance of DUMP processing. With hardware assisted compression, a compression dictionary is built using user data. This dictionary is then used to compress that user data and subsequent user data. Unfortunately, building the compression dictionary is expensive in terms of performance, so it is preferable to avoid building the compression dictionary too often. However, data could be compressed better, resulting in smaller output dump data sets, if the dictionary was rebuilt sooner.

During a physical dump process, the quality of compression is recorded and used in deciding when to rebuild the compression dictionary. Two measurements are used. The first measurement is the quality of compression achieved. This is a percentage, calculated by dividing the compressed size of the data by the original size of the data. A compression is considered poor when the percentage is greater than a threshold value. The default threshold value is 94%.

The second measurement is how many poor compressions are allowed before rebuilding the compression dictionary. The default value for the number of poor compressions allowed before rebuilding the compression dictionary is 15.

DFSMSdss provides patch bytes to change the number of poor compressions and the threshold value. To change the number of poor compressions allowed before rebuilding the compression, you can modify the value at offset X'50' using the SET PATCH command. The valid settings are:

**X'00'** DFSMSdss functions normally. The default value of 15 poor compressions is used to decide when to rebuild the compression dictionary.

#### Any setting other than X'00'

DFSMSdss uses the value set as the number of poor compressions to allow before rebuilding the compression dictionary.

To modify the target compression threshold, you can set the value at offset X'51', using the SET PATCH command. The settings are:

**X'00'** DFSMSdss functions normally. The default value of 94% is used as a threshold to make a decision whether to count the compression as poor or not.

X'01' - X'64'

DFSMSdss uses this value (1%-100%) as the target compression threshold.

X'65' - X'FF'

These values are invalid as a compression threshold percentage and will be ignored. When ignored, the default value of 94% is used as the threshold.

## Resetting the data-set-changed indicator during physical full or partial RESTORE operation (OA20907)

The data-set-changed indicator (DS1DSCHA) bit is automatically turned off during a physical full volume or tracks RESTORE operation. You can reset the indicator by setting the flag at offset X'52' in ADRPATCH . The valid settings are:

**X'00'** DFSMSdss turns off the DS1DSCHA bit during a physical full volume or tracks RESTORE operation.

#### Any setting other than X'00'

DFSMSdss does not reset the DS1DSCHA indicator during a physical full volume or tracks RESTORE operation.

To set the flag on dynamically, use the SET PATCH command. To set the flag on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

//SYSIN DD \*
NAME ADRDSSU ADRPATCH
VER 52 00
REP 52 FF

**Note:** If you use an application program interface (API) to invoke DFSMSdss, this patch is not used and the DS1DSCHA bit is reset as usual.

## Requesting that DFSMSdss double-check data set high used RBA values for LDS data sets (OA23805)

You can use the patch byte at offset X'53' to request that DFSMSdss is to do a sequential scan of the VSAM volume data set to re-find the VSAM volume record for a linear data set, and compare its Data Set High Used RBA value with the one obtained earlier in DFSMSdss processing. The valid settings are:

X'00' DFSMSdss does not try to re-obtain the VSAM record for a linear data set during a logical data set COPY.

#### Any setting other than X'00'

DFSMSdss tries to re-obtain the VSAM volume record for a linear data set during a logical data set COPY and then compares the values of the Data Set High Used RBA. If they are not the same, DFSMSdss issues an ADR432E message along with other diagnostic information. Additionally, DFSMSdss issues ADR898D message to the system that requests a PRINT of VVDS on the specified volume. Processing of any data sets that receive the ADR432E message fails. DFSMSdss does not delete these data sets even if you specify the DELETE keyword.

To set the flag on dynamically, use the SET PATCH command. To set the flag on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
NAME ADRDSSU ADRPATCH
VER 53
REP
```

Note: If you use this Patch byte, DFSMSdss processing might take a long time, especially when the VSAM volume data set is large, because DFSMSdss might scan the entire VSAM volume data set to find the VSAM volume record.

## Enabling or disabling use of the catalog search interface for data set name filtering

You can enable or disable the use of the Catalog Search Interface (CSI) during DFSMSdss catalog filtering for logical data set COPY, DUMP or RELEASE commands. DFSMSdss catalog filtering is performed whenever no input volumes are specified on the COPY, DUMP or RELEASE commands. Catalog filtering can use either:

- Catalog search interface (CSI)
- Generic catalog locates.

DFSMSdss provides a patch byte to enable or disable the use of the CSI during DFSMSdss catalog filtering. Modify the value at offset X'54' using the SET PATCH command. The valid settings are as follows.

DFSMSdss uses the CSI to convert generic filter criteria to a list of data sets that are cataloged.

#### Any other value

DFSMSdss uses generic catalog locates to generate a list of data sets that are cataloged.

## Requesting that DFSMSdss restore the VM-formatted volume that was DUMPed by z/OS V1R10 before OA27531 was applied.

You can use the patch byte at offset X'55' to request that DFSMSdss restore the VM formatted volume that was DUMP on a z/OS V1R10 system before OA27531 was applied.

Note that this patch byte is only valid for RESTORE tracks operations, and the patch byte is honored only when the SET PATCH command sets it on,

dynamically. You must also ensure that the DUMP is a VM formatted volume made with the CPVOLUME keyword specified.

The settings are:

X'00' DFSMSdss functions normally.

#### Any setting other than X'00'

The RESTORE will treat the contents of the DUMP as a VM formatted volume.

### Adding timestamps to messages

You can use the patch byte at offset X'58' to request that DFSMSdss add timestamps to certain message classes as follows:

X'00' Specific messages

X'80' Informational messages

X'40' Warning messages

X'20' Error messages

X'10' Terminating messages

The values may be added together to get combinations of messages. For example, if you want timestamps on warning and error messages, set the value to X'60'.

## **Enabling building appropriate channel programs**

DFSMSdss tape read channel programs are built to read the maximum possible amount of data that any version of DFSMSdss can create. DFSMSdss provides a patch byte to modify how DFSMSdss builds channel programs to read tape blocks. You can control this function by setting the flag at offset X'59' in ADRPATCH. The valid settings are:

#### X'00'

DFSMSdss continues to build channel programs to read the maximum amount of data that can be created by DFSMSdss.

#### Any other value

DFSMSdss builds channel programs to read the maximum block size written to the dump data set that the restore is being performed on.

To set the flag on dynamically, use the SET PATCH command to set the patch byte at offset X'59' to a value of X'FF'. To set the flag on permanently, modify the sample JCL (see "Sample JCL" on page 217) as follows:

```
//SYSIN DD *
NAME ADRDSSU ADRPATCH
VER 59 00
REP 59 FF
```

## Requesting that DFSMSdss attempt to fix ESDSes with corrupted RDFs

Use the flag at offset X'57' to request that DFSMSdss attempt to fix entry sequenced data sets (ESDSes) that have record descriptor fields (RDFs) that incorrectly indicate repeated records. The values are:

#### **DFSMSdss Patch Area**

#### X'00'

DFSMSdss operates normally

#### Any other value

DFSMSdss attempts to fix the ESDSes during logical data set RESTORE processing when VSAM I/O is needed to restore the data set. DFSMSdss examines each RDF when using VSAM I/O to put records into an ESDS. If the RDF indicates incorrectly that it describes repeated records, it is modified to describe a single record. Message ADR925W is issued to indicate that modifications were done during the restore of the data set. The ADR925W message is also written to the console for use by automation.

To set the flag on dynamically, use the SET PATCH command to set the flag at offset X'57' to a value of X'FF'. To set the flag permanently, modify the sample JCL as follows:

//SYSIN DD \* NAME ADRDSSU ADRPATCH VER 57 00 REP FF 57

#### **ADRPTCHB** data area

Table 20 lists the mapping of flags in ADRPTCHB.

Table 20. ADRPTCHB Mapping Macro

Off	sets				
Dec	Hex	Туре	Len	Name (Dim)	Description
0	(0)	STRUCTURE	4096	ADRPTCHB	
0	(0)	CHARACTER	8	PTCHEYE	
8	(8)	UNSIGNED	1	PTCHARRY	
				(4088)	
8	(8)	UNSIGNED	1	PBUVSPRE	USE PREALLOCATED VSAM
9	(9)	UNSIGNED	1	PBDUPKEY	DUPLICATE VSAM KEY
10	(A)	UNSIGNED	2	PBTIMOUT	TIMEOUT CONSTANT
12	(C)	UNSIGNED	1	PBADINFO	VARIABLE USED FOR ADTL INFO XT@NA03602 IN ADRDTDSC & IN ADRFDSRL
13	(D)	UNSIGNED	1	PBWAITFG	WAIT/RETRY FLAG FOR VTOC/VVDS ENQ OR RESERVE
14	(E)	UNSIGNED	1	PBWAIT#	WAIT TIME FOR VTOC/VVDS ENQ OR RESERVE
15	(F)	UNSIGNED	1	PBRETRY#	RETRY COUNT FOR VTOC/VVDS ENQ OR RESERVE
16	(10)	UNSIGNED	1	PBRESERV	RESERVE BYTE TO ACCOUNT FOR OFFSET ERRORS
17	(11)	UNSIGNED	1	PBREVOKE	GIVE REVOKED DS OWNER ACCESS TO SMS CONSTRUCTS
18	(12)	UNSIGNED	1	PBBPDSE	BROKEN PDSE RESTORE FLAG
19	(13)	UNSIGNED	1	PBNRACFI	NO INDIC. FOR LOG. REST.
20	(14)	UNSIGNED	1	PBNMVNCV	NO MV ALLOC IF ALSO UNDEFINED DATA SET
21	(15)	UNSIGNED	1	PBBYPBWO	BYPASS BWO
22		UNSIGNED	1	PBNACSAU	NO ACS AUTH. CHECKING DURING RESTORE
23	(17)		1	PBNSLECT	WARNING MESSAGE FOR DATA SETS NOT SELECTED.
24	(18)	UNSIGNED	1	PBCCRESE	DO RESET WITH CONCURRENT COPY

Table 20. ADRPTCHB Mapping Macro (continued)

Offs	sets				
Dec	Hex	Туре	Len	Name (Dim)	Description
25	(19)	UNSIGNED	1	PBNO482E	RESTORE DS FROM DUMP TAPE WHICH HAD MSGADR727E
26	(1A)	UNSIGNED	1	PBMISCNT	RESTORE DS FROM DUMP TAPE DUMPED WITH CC PRIOR TO INSTALLATION OF FIX FOR OY67724
27	(1B)	UNSIGNED	1	PBX99365	TREAT ALL F1 DSCB EXP DATE 1999.365 FROM DUMP AS ACTUAL EXP DATE WHEN DEFINING TARGET
28	(1C)	UNSIGNED	1	PBEX2000	TREAT ALL F1 DSCB SMALL EXP DATES FROM DUMP AS 2NNN EXP DATES WHEN DEFINING TARGET
29	(1D)	UNSIGNED	1	PBEOFNO	DO NOT INSERT EOF DURING COPY ALLDATA FROM MULTIVOLUME TO SINGLE-VOLUME DATASET
30	(1E)	UNSIGNED	1	PBBYLENQ	BYPASS PN27748 CODE WHICH DELAYS RESET UNCAT AND HOLDS LONGER ENQUEUES
31	(1F)	UNSIGNED	1	*	RESERVED BYTE

**Note:** The following 6 fields starting at offset X'20' are intended for installations to "adjust" target PDSE DS1SCAL3 which may have been incorrectly altered by PE-OW04199. The logic is: IF 2nd\_qty > PBCYLHI THEN 2nd\_qty = PBCYLQTY. Any non-zero value in PBCYLHI, PBTRKHI, or PBBLKHI will activate the "adjustment code" for the corresponding allocation type in ADRNEWDS.

		, , , ,			
32	(20)	UNSIGNED	4	PBCYLHI	HI THRESHOLD FOR CHECKING DS1SCAL3 IN
2.	(2.1)	T IN TOT ON THE		DD CL / CTL /	CYL ALLOCATION
36	(24)	UNSIGNED	4	PBCYLQTY	CHANGE DS1SCAL3 TO THIS VALUE IF IT IS >
					PBCYLHI
40	(28)	UNSIGNED	4	PBTRKHI	HI THRESHOLD FOR CHECKING DS1SCAL3 IN
					TRK ALLOCATION
44	(2C)	UNSIGNED	4	PBTRKQTY	CHANGE DS1SCAL3 TO THIS VALUE IF IT IS >
					PBTRKHI
48	(30)	UNSIGNED	4	PBBLKHI	HI THRESHOLD FOR CHECKING DS1SCAL3 IN
					BLK ALLOCATION
52	(34)	UNSIGNED	4	PBBLKQTY	CHANGE DS1SCAL3 TO THIS VALUE IF IT IS >
	, ,				PBBLKHI
56	(38)	UNSIGNED	1	PBROREFD	DS1REFD RESTORE OLD 0 = USE OLD DATE 1
	(00)		_		= USE TODAY'S DATE
57	(39)	UNSIGNED	1	PBRNREFD	DS1REFD RESTORE NEW 1 = USE OLD DATE 0
	(0)	CITOIGITED	1	T DIG VICE I	= USE TODAY'S DATE
58	(3A)	UNSIGNED	1	PBCOREFD	DS1REFD COPY OLD 0 = USE OLD DATE 1 =
30	(5A)	UNSIGNED	1	TECKETE	USE TODAY'S DATE
59	(3R)	UNSIGNED	1	PBCNREFD	DS1REFD COPY NEW 1 = USE OLD DATE 0 =
39	(30)	UNSIGNED	1	I DCINKEI'D	USE TODAY'S DATE
60	(3C)	UNSIGNED	1	PBCDELNP	DEGRADE 'E' MSG TO 'W' IF COPY DEL NO
00	(SC)	UNSIGNED	1	POCDELNI	TGT PROFILE
(1	(0.D)	LINICIONIED	1	DDNIA CCA C	
61	(3D)	UNSIGNED	1	PBNACSAC	NO ACS AUTHORIZATION CHECKING
	(2.17)	T IN TOT ON THE		DDD II III OX	DURING COPY
62	(3E)	UNSIGNED	1	PBINVTOK	DON'T ERASE INVALID TRACK DURING
					COPY/RESTORE
63	(3F)	UNSIGNED	1	PBSRCVOL	PASS SOURCE PRIMARY VOLUMES FROM
					WHICH DS WAS DUMPED
64	(40)	UNSIGNED	1	PBVOLOPT	'PATCHABLE' VOLCOUNT OPTION FLAG
					DATA SET
		1		PBVCCUR	VOLCOUNT(*)
		.1		PBVCSRC	VOLCOUNT(SRC)
		l			I .

#### **DFSMSdss Patch Area**

Table 20. ADRPTCHB Mapping Macro (continued)

Offse	ets				
Dec	Hex	Туре	Len	Name (Dim)	Description
		1		PBVCNUM	VOLCOUNT(N(NN))
		1		PBVCANY	VOLCOUNT(ANY)
		1111		*	UNUSED
65	(41)	UNSIGNED	1	PBVCVAL	NUMBER OF VOLUMES TO USE FOR OUTPO
66	(42)	UNSIGNED	1	PBMSCIOK	OK TO HAVE MISSING INDEX CI IN KEYED VSAM DATA SET - VALIDATE
67	(43)	UNSIGNED	1	PBRESV60	WAS FOR DEFRAG TO MOVE CHECKPOINT INDICATED DATA SET
68	(44)	UNSIGNED	1	PBFUDGE	OVER ALLOCATE DATA SET BY % IN FUDGFACTOR
69	(45)	UNSIGNED	1	PBNORLS	DO NOT DO RLS QUIESCE
70	. ,	UNSIGNED	1	PBROCRED	DS1CREDT RESTORE OLD 0 = USE OLD DATE = USE TODAY'S DATE
71	(47)	UNSIGNED	1	PBRNCRED	DS1CREDT RESTORE NEW 1 = USE OLD DA 0 = USE TODAY'S DATE
72	, ,	UNSIGNED	1	PBCOCRED	DS1CREDT COPY OLD 0 = USE OLD DATE 1 USE TODAY'S DATE
73	, ,	UNSIGNED	1	PBCNCRED	DS1CREDT COPY NEW 1 = USE OLD DATE USE TODAY'S DATE
74	. ,	UNSIGNED	1	*	RESERVED
75	, ,	UNSIGNED	1	PBVDPDSE	VALIDATE PDSE 1 = ENABLE VALIDATION DISABLE VALIDATION
76	, ,	UNSIGNED	1	PBMXPTSK	MAXIMUM NUMBER OF ACTIVE PARALLI SUBTASKS  X'01' THROUGH X'FF' =  USER SPECIFIED THRESHOLD VALUE  X'00' = DFSMSDSS DETERMINED THRESHO
77	(4D)	UNSIGNED	1	PBNOINIT	CHANGE DEFAULT INIT PROCESSING DURING DUMP FCWITHDRAW 1 = DO NOT INIT VOLUME 0 = INIT DUMP SOURCE VOLUME WHEN APPLICABLE
78	, ,	UNSIGNED	1	PBMOVLL	OVERRIDE DEFRAG TO MOVE LINKLIST-INDICATED DATA SET
79		UNSIGNED		PBFCDEF	OVERRIDE FAST REPLICATION DEFAULT SETTING TO NONE
80	( )	UNSIGNED		PBDCTBD	REBUILD COMPRESSION DICTIONARY AFT THIS MANY BAD COMPRESSIONS
81	, ,	UNSIGNED	_	PBCMPTH	POOR COMPRESSION THRESHOLD VALUE 1-100
82	, ,	UNSIGNED	1	PBDSCHA	OVERRIDE RESET OF DSCHA BIT ON FULL PART RESTORE 0 = DS1DSCHA RESET 1 = DSCHA NOT RESET
83	, ,	UNSIGNED	1		DOUBLE CHECK THE DSHURBA VALUE FO LDS DATA SETS
84	(54)	UNSIGNED	1	PBCSIEN	ENABLE USAGE OF THE CATALOG SEARCH INTERFACE FOR GENERIC FILTER
85	(55)	UNSIGNED	1	PBCPVOL	1 = TREAT RESTORE AS A CPVOL - ONLY BY THE SET PATCH CMD
86	(56)		1	PBRESDS	TREAT ESDS AS LDS WHEN ATTEMPTING LOGICAL RESTORE OF INVALID DB2 ESDS
87	(57)	UNSIGNED	1	PBMSGTIME	ADD TIMESTAMPS TO MESSAGES IN EACH THE VARIOUS CLASSES

## **ADRPTCHB** cross-reference

Name	Hex Offset	Hex Value
ADRPTCHB	0	
PBADINFO	C	
PBBLKHI	30	
PBBLKQTY	34	
PBBPDSE	12	
PBBYLENQ	1E	
PBBYPBWO	15	
PBCCRESE	18	
PBCDELNP	3C	
PBCMPTH	51	
PBCNCRED	49	
PBCNREFD	3B	
PBCOCRED	48	
PBCOREFD	3A	
PBCYLHI	20	
PBCYLQTY	24	
PBDCTBD	50	
PBDSCHA	52	
PBDUPKEY	9	
PBEOFNO	1D	
PBEX2000	1C	
PBFCDEF	4F	
PBFUDGE	44	
PBINVTOK	3E	
PBMISCNT	1A	
PBMOVLL	4E	
PBMSCIOK	42	
PBMXPTSK	4C	
PBNACSAC	3D	
PBNACSAU	16	
PBNMVNCV	14	
PBNOINIT	4D	
PBNORLS	45	
PBNO482E	19	
PBNRACFI	13	
PBNSLECT	17	
PBRESERV	10	
PBRESV60	43	
PBRETRY#	F	
PBREVOKE	11	
PBRNCRED	47	
PBRNREFD	39	
PBROCRED	46	
PBROREFD	38	
PBSRCVOL	3F	
PBTIMOUT	A	
PBTRKHI	28	
PBTRKQTY	2C	
PBUVSPRE	8	
I DO VOI KE	U	

#### **DFSMSdss Patch Area**

Name	Hex Offset	Hex Value	
PBVCVAL	41		
PBVDPDSE	4B		
PBVOLOPT	40		
PBWAIT#	E		
PBWAITFG	D		
PBWFUMOD	4A		
PBX99365	1B		
PTCHARRY	8		
PTCHEYE	0		

## Part 2. DFSMSdss Storage Administration Reference

## Chapter 15. Specifying DFSMSdss commands

This topic is divided into the following sections:

- "Command syntax" describes syntax requirements.
- "How many subkeywords are allowed?" on page 250 explains the allowable number of subkeywords that you can specify in the input (command) stream.
- "Specifying subkeywords in a command data set" on page 250 explains how to use keywords in a command data set.
- "How to read syntax diagrams" on page 251 explains the syntax conventions used in this book.
- "JCL that you need" on page 252 summarizes the job control language (JCL) that you might need to use DFSMSdss.

## **Command syntax**

You can write DFSMSdss commands in free form in columns 2 through 72 (inclusive). Any character in column 1 or beyond column 72 is ignored, causing unpredictable results when the task is processed. Syntax requirements are:

#### Commands:

A command must appear first, followed by its keywords. Each command must take up only one line, unless a continuation character is used to indicate continuation of the command on the next line. A command is separated from its keywords by one or more blanks, a comment, or both. For example:

```
DUMP FULL INDD(DASD1) OUTDD(TAPE1)
or
DUMP FULL INDD(DASD1) -
OUTDD(TAPE1)
```

#### **Comments:**

A comment is a string of characters that begins with a /\* and ends with an \*/. For example:

```
/*THIS IS A COMMENT */
```

A comment that does not begin and end on the same line must contain a continuation character, or syntax errors will result. For example:

```
/* THIS IS A MULTI -
LINE COMMENT */
```

#### **Separators:**

A separator can be a comma (,), one or more blanks, or a comment. Separators shown in the syntax diagrams in this manual are always commas, but any of the three types can be used.

#### **Keywords:**

Keywords are parameters separated by one or more separators.

#### Subkeywords:

Subkeywords follow their associated keyword and are separated from them by a pair of enclosing parentheses. One or more blanks can precede and follow each parenthesis in the pair. For example:

#### Command Syntax

```
REBLOCK( DATASET1 )
REBLOCK(DATASET1)
```

If two or more subkeywords are permissible for a single keyword, they are separated from one another by one or more blanks or by commas. Each comma can be preceded and followed by one or more blanks. For example:

```
REBLOCK(DATASET1, DATASET2)
REBLOCK(DATASET1, DATASET2)
REBLOCK(DATASET1 DATASET2)
```

#### **Continuation:**

Continuation of a command is specified by a hyphen (-) as the right-most nonblank character, preceded by one or more blanks. If a continuation character is used, the following line is read as if it were part of the previous line. Since only one command is allowed per line, no additional commands may be included on the continued line. If no continuation character is used, the first word on the following line must be a command. For example:

```
COPY DATASET (INCLUDE(DATASET1)) ALLDATA(*) -
    CATALOG REBLOCK(DATASET1)
```

For examples of the continuation usage, see "Continuation rules for IF-THEN-ELSE command sequencing" on page 508, using the IF-THEN-ELSE command sequence.

The absence of such a hyphen indicates the end of the command. If a keyword or subkeyword cannot fit on the remainder of a line, it can be started on that line, followed immediately by a plus sign (+) in column 72, and continued on the next line.

#### End of a command:

The end of a command can be specified by a semicolon (;). Everything to the right of the semicolon is ignored.

## How many subkeywords are allowed?

DFSMSdss allows most command keywords to have a maximum of 255 subkeywords specified within the inline command stream. Exceptions to this rule are noted within individual command descriptions.

## Specifying subkeywords in a command data set

Rather than specifying the data set names in the inline (command) stream, you can instead specify the ddname of a sequential data set or a member of a partitioned data set that contains the list of data set names. This allows you to specify more than 255 data set names.

The following keywords allow this ddname specification:

```
DATASET
      (FILTERDD(ddn))
EXCLUDE
      (DDNAME(ddn))
FILTERDD
      (ddn)
```

PASSWORD (ddn)

## How to read syntax diagrams

To read syntax diagrams, follow one line at a time from the beginning to the end, and code everything you encounter on that line.

The following conventions apply to all syntax diagrams for DFSMSdss commands:

- Read the syntax diagrams from left to right and top to bottom.
- Each syntax diagram begins with a double arrowhead (►►) and ends with opposing arrows (►◄).
- An arrow (→) at the end of a line indicates that the syntax continues on the next line. A continuation line begins with an arrow (►).
- Commands and keywords are shown in uppercase and lowercase letters. The uppercase portion is the minimum needed to code the command properly; the lowercase portion is optional. For example, COPYDump can be coded in any of the following ways: COPYD, COPYDU, COPYDUM, or COPYDUMP.

**Note:** Commands *must* be entered in uppercase. Lowercase is not recognized.

• Some commands and keywords have alternative abbreviations; these appear as part of the stack for that command or keyword. For example, the alternative abbreviation for COPYDump is CPYD.



- Words in all lowercase letters represent information you supply. For example, *volser* or *ddn*.
- You must provide all items enclosed in parentheses, ( ), and you must include the parentheses.
- Where you can choose from two or more keywords, the choices are stacked one
  above the other. If one choice within the stack lies on the main path, you must
  choose a keyword. In the following example you must choose either BLK, TRK, or
  SOURCE.




• If one or more keywords are below the main path, they are optional. In the following example CATalog and RECATalog are optional keywords. You can choose one, or the other, or none.



• If a stack of keywords are below the main path and one keyword is above the main path, the use of the keyword is optional, and the above item is the default. In the following example, if no keywords are specified, the default TGTAlloc(SOURCE) is taken.

#### **Syntax Conventions**



• The repeat symbol is shown below:



The repeat symbol appearing above keywords and variables indicates that you can specify those keywords and variables more than once. If a comma appears in the repeat symbol, you must separate repeated keywords or variables with a comma or any valid separator.

For example, after the keyword BYPASSACS, you can enter multiple data set names separated by commas.



Substitution blocks are used to simplify the diagrams. They indicate that blocks of the syntax diagram are located outside of the main diagram. You insert the keywords for that block where the symbol appears, and return to the main diagram to continue with the command.


In the following example the substitution block, A, points to a block of the syntax diagram that immediately follows the FULL keyword.



#### A: Optional Keywords Used With FULL:



The above example is equivalent to the following:



## JCL that you need

The examples in this manual are shown with the necessary JCL. You may need the following JCL to use DFSMSdss:

Statement

Usage

JOB (required)

Initiates your job.

#### **EXEC** (required)

Specifies the program name (PGM=ADRDSSU) or, if the job control statements reside in a procedure library, the procedure name. See "How to control DFSMSdss through PARM information in the EXEC statement" on page 254 for additional information that can be entered in the PARM parameter of the EXEC statement.

#### SYSPRINT DD (required)

Defines a sequential message data set. The data set can be written to a system output device, a tape volume, or a direct-access device. If the DCB keyword LRECL is specified on the DD statement, it must be from 84 to 137 inclusive. If the BLKSIZE keyword is specified, it must be at least four greater than LRECL. If LRECL is less than 84, the return code is 8, and an error message is issued. If the specified LRECL is greater than 137, the LRECL and BLKSIZE are set to 137 and 141, respectively.

**Note:** If the SYSPRINT DD or a temporary message data set resides on a volume that is being processed by DFSMSdss and a secondary allocation is needed for it, the job may result in an S138 abend. This is because the DADSM EXTEND function attempts to enqueue on the volume's VTOC while DFSMSdss holds the enqueue on that VTOC. To avoid this situation, define the SYSPRINT DD to another volume or use the WORKUNIT or WORKVOL parameters, or both.

#### SYSIN DD (required)

Defines a command data set containing your DFSMSdss commands. It usually resides in the input stream. However, it can be defined as a blocked or unblocked sequential data set or as a member of a partitioned data set. Records must be fixed format, LRECL=80.

#### input DD (optional)

Defines the input (also called the source). The ddname, *input*, is supplied by you and is referred to by your DFSMSdss commands. This DD statement is not required for some operations. Do not specify the BUFNO keyword.

The following example shows an input DD statement that specifies a DASD volume:

//DASD DD UNIT=3380, VOLUME=(PRIVATE, SER=111111), DISP=OLD

See the reference under the INDDNAME, INDYNAM, DDNAME and DYNAM keywords of the various commands (for example, COPY or DUMP) for additional information.

#### output DD (optional)

Defines the output (also called the target). The ddname, *output*, is supplied by you and is referred to by your DFSMSdss commands. This DD statement is not required for some DFSMSdss operations. Do not specify the BUFNO keyword. Code a volume count when a new data set will reside on six or more volumes.

#### Note:

- 1. DISP=MOD is not supported for an output DD statement.
- 2. For dump operations, the output DD statement describes a sequential data set that DFSMSdss dumps the data to. If this dump data set resides on a DASD volume that is being processed by DFSMSdss and a secondary allocation is needed for it, the job may result in a S138

- abend. This is because the DADSM EXTEND function attempts to enqueue on the volume's VTOC while DFSMSdss holds the enqueue on that VTOC.
- 3. For dump operations, the output DD statement can be directed to DUMMY. If you specify DD DUMMY, DFSMSdss does not perform data sets I/O. If you specify DELETE keyword with DD DUMMY, DFSMSdss deletes the input data sets as requested.
- 4. If multiple dumps are done in the same step, each dump command should have an output DD statement that refers to a unique JCL DD statement.
- 5. The output data set must be a standard format sequential data set and cannot use any extended-format features, such as compression.

The following example shows an output DD statement that specifies a tape volume:

```
//TAPE DD UNIT=3480, VOLUME=SER=TAPE01, LABEL=(1, SL),
// DISP=(NEW,CATLG),DSNAME=USER2.DUMP
```

See the reference under the OUTDDNAME and OUTDYNAM keywords of the various commands (for example, COPY or DUMP) for additional information.

#### filter DD (optional)

Defines a data set consisting of cards or card-image records that contains the filtering criteria (INCLUDE, EXCLUDE, and BY) to be used in a data set command. The ddname, filter, is supplied by you and is referred to by your DFSMSdss commands.

#### password DD (optional)

Defines a data set consisting of card-image records that contains data set names and their passwords. The ddname, password, is supplied by you and is referred to by your DFSMSdss commands.

For more information on coding JCL, refer to *z/OS MVS JCL Reference*.

## How to control DFSMSdss through PARM information in the **EXEC** statement

The EXEC statement for DFSMSdss can contain PARM information that is used by the program. You can use the following keyword parameters:

#### ABEND=nnn

nnn is a 3-digit decimal message number (ADRnnnx). If this is specified and this message is to be issued, DFSMSdss performs a user 0001 ABEND dump after issuing the message, the task stops and the return code is set to 8. To get a dump, include a DD statement for SYSABEND, SYSMDUMP, or SYSUDUMP. This keyword is provided for diagnostic purposes only.

#### AMSGCNT=nnnn

The abend message occurrence count that tells DFSMSdss to end abnormally on the nth occurrence of the message specified in ABEND=nnn. nnnn for AMSGCNT can be a number between 1 and 9999. The default is 1 (first occurrence). This keyword is provided for diagnostic purposes only.

#### **DEBUG=FRMSG**

This parameter causes DFSMSdss to issue an informational message during copy or defrag operations for which fast replication methods, such as SnapShot and FlashCopy, cannot be used. The informational message indicates why DFSMSdss could not use fast replication. This keyword is provided for diagnostic purposes only.

#### Guidelines:

- 1. When you specify this parameter, DFSMSdss interprets it as though you have specified the DEBUG(FRMSG(SUMMARIZED)) keyword.
- 2. You can use the DEBUG(FRMSG(MIN | SUM | DTL)) keyword with the COPY and DEFRAG commands. It is used when designating the use of fast replication methods. It is recommended that you convert your DEBUG=FRMSG parameter to this new keyword specification in your JCL jobs.

#### LINECNT=nnnn

**nnnn** is a 1-digit to 4-digit number indicating the number of lines to be printed per page for the SYSPRINT data set. The default is 60. Specify LINECNT=9999 to prevent a page ejection.

#### PAGENO=nnnn

**nnnn** is a 1-digit to 4-digit number indicating the starting page number to be used for the SYSPRINT data set. The default is 1.

#### SDUMP=nnn

nnn is a 3-digit decimal message number (ADRnnnx). If this is specified, DFSMSdss requests an SVC dump after issuing the message, and the task continues processing. The SVC dump is directed to a system defined data set (SYS1.DUMPnn) for later analysis. This keyword is provided for diagnostic purposes only.

#### SIZE=nnnnK

**nnnn** is a 1-digit to 4-digit number indicating the number of KB (1KB equals 1024 bytes) of main storage to be used by DFSMSdss. This amount must be less than or equal to that specified by the REGION keyword. The default value is the region size.

#### SMSGCNT=nnnn

The sdump message occurrence count that tells DFSMSdss to request an SVC DUMP on the nth occurrence of the message specified in SDUMP=nnnn. nnnn for SMSGCNT can be a number between 1 and 9999. The default is 1 (first occurrence). This keyword is provided for diagnostic purposes only.

#### TMPMSGDS=YES | NO

This parameter indicates whether or not a temporary SYSPRINT message data set is to be allocated. When N0, SYSPRINT messages are buffered in an ESA Hiperspace  $^{\text{\tiny TM}}$  and performance is improved. The default is N0.

#### TRACE=YES

When used during DEFRAG or CONSOLIDATE operation, this prints messages that indicate the relocated extents. This is a diagnostic tool.

#### TYPRUN=NORUN

For copy, dump, restore, compress, and release operations, only input data set selection is done without actually processing data sets. Printed output for the run indicates the data sets selected. For a defragmentation operation, the initial volume statistics are printed without actually relocating any extents. For a CONVERTV operation, a full report is produced, but no volumes or data sets are actually converted. For CGCREATED operation, only control card syntax checking is done. The task is not processed.

#### TYPRUN=SCAN

Only control card syntax checking is done. No tasks are processed.

#### USEEXCP=YES NO

Specifies whether the access method used by DFSMSdss for DUMP output, RESTORE input and COPYDUMP operations is to be EXCP. If the backup is to or from tape, the default is NO. If the backup is to or from DASD, the default is YES, unless the backup data set is in the extended format. For COPYDUMP and RESTORE operations that specify USEEXCP=YES, if the backup is from a non-label tape or a standard label tape with a block size of zero in its tape header, the dump data set block size must be specified on the input tape's DD in order for EXCP processing to be used. If the block size is not specified, BSAM processing is used instead.

#### UTILMSG=YES | NO | ERROR

This parameter controls the output of messages from auxiliary programs invoked by DFSMSdss (including ICKDSF, IDCAMS, IEBCOPY, IEBISAM, and IEHMOVE) to the DFSMSdss SYSPRINT output. When YES, informational, warning, and error messages from these auxiliary programs are copied to the DFSMSdss SYSPRINT output. When N0, messages are not copied to the output. When ERROR, messages are copied only if the auxiliary return program returns an error code to DFSMSdss. The default is ERROR.

#### WORKUNIT=workunit

You can supply an esoteric DASD unit name (for example, SYSDA), a generic DASD unit name (for example, 3380), or a specific DASD address. DFSMSdss passes this unit to dynamic allocation when temporary data sets are allocated. When WORKUNIT is specified by itself, the volumes to be processed by DFSMSdss should not fall within the esoteric group passed as the WORKUNIT name. If the esoteric name applies to the volumes to be processed by DFSMSdss, specify WORKVOL.

#### WORKVOL=volser

You can supply a volume serial number on which DFSMSdss should allocate temporary data sets. DFSMSdss passes the volume serial number to dynamic allocation. The volume serial number passed as a WORKVOL should not be the same as any volume being processed by DFSMSdss under the current task.

#### Note:

- 1. WORKUNIT, WORKVOL, or both parameters can be specified when invoking DFSMSdss.
- 2. When DFSMSdss invokes the IDCAMS utility to copy an ICF user catalog, the export data set is allocated as a permanent data set. The permanent data set cannot be placed on the volume specified by WORKUNIT or WORKVOL.
- 3. An esoteric unit name that requests virtual I/O can be used in the WORKUNIT parameter, but when DFSMSdss invokes the IEHMOVE utility during data set copy, the default dynamic allocation unit name is used (SYSALLDA).

#### XABUFF=ABOVE16 | BELOW16

The I/O buffers used by DFSMSdss for COPY, COPYDUMP, DEFRAG, DUMP, PRINT, and RESTORE operations are to be above or below 16 megabytes virtual storage. The default is ABOVE16.

#### ZBUFF64R=YES NO

The I/O buffers that DFSMSdss uses for COPY, COPYDUMP, DEFRAG, DUMP, PRINT, and RESTORE operations can be backed by real storage that is anywhere in 64-bit addressing, or below the 2-gigabyte bar. The ZBUFF64R EXEC parameter allows a user to indicate to DFSMSdss where the I/O buffers should be located.

DFSMSdss obtains I/O buffers that are backed by real storage anywhere in 64-bit addressing when you specify EXEC PARM='ZBUFF64R=YES'. The default is ZBUFF64R=YES, which results in all I/O buffers being obtained such that they can be backed above the 2–gigabyte bar.

DFSMSdss determines whether a tape device used in a job supports buffers above the 2-gigabyte bar, and uses buffers above the 2-gigabyte bar when all tape devices in the job support buffers above the 2-gigabyte bar. If any tape device in a job does not support buffers above the 2 gigabyte bar, DFSMSdss uses buffers below the 2-gigabyte bar for the entire job.

Examples of PARM information are:

```
// EXEC PGM=ADRDSSU,
// PARM='PAGENO=8,LINECNT=57,SIZE=500K,UTILMSG=YES'

// EXEC PGM=ADRDSSU,
// PARM='TYPRUN=SCAN,DEBUG=FRMSG,XABUFF=ABOVE16,UTILMSG=YES'

// EXEC PGM=ADRDSSU,
// PARM='ZBUFF64R=NO,UTILMSG=YES'
```

**Related reading:** For additional information about the PARM parameter of an EXEC statement, see the *z*/*OS MVS JCL Reference*.

**Related reading:** For additional information about the ADRUFO parameter list and the ADRUIXIT exit, see the *z*/*OS DFSMS Installation Exits*.

## **Examples of invoking DFSMSdss with JCL**

The following are some examples of JCL job streams for invoking DFSMSdss.

**Note:** Throughout the examples in this manual, a DASD is presented as UNIT=3380 or UNIT=3390, and a tape device as UNIT=3480. This is only for illustration; you can specify any supported DASD and any supported tape device. Refer to the appropriate system generation manual for the device-type notation to be used in the UNIT parameter of a DD statement.

#### Moving a data set

The following example shows how to move a data set from one DASD volume to another using JCL and a DFSMSdss command. The source data set is deleted and the target data set is cataloged to reflect its new location.

```
//MYJOB JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//DASD1 DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//DASD2 DD UNIT=3390, VOL=(PRIVATE, SER=222222), DISP=OLD
//SYSIN DD *
COPY DATASET(INCLUDE(MYDATSET)) -
LOGINDDNAME(DASD1) OUTDDNAME(DASD2) DELETE CATALOG
/*
```

#### Dumping a data set

Do not use a data set name that DFSMSdss will reference during execution. Otherwise, enqueue contention with the operating system initiator will occur. This example shows how to back up a DASD data set to tape:

```
//MYJOB
          J0B
                 accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD
                 SYSOUT=A
//DASD
                UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
          DD
//TAPE
          DD
                UNIT=3480, VOL=SER=TAPE01,
// LABEL=(1,SL),DISP=(NEW,CATLG),DSNAME=MYDATSET.BACKUP
//SYSIN
          DD
DUMP DATASET(INCLUDE(MYDATSET)) -
     INDDNAME (DASD) OUTDDNAME (TAPE)
```

#### Restoring a data set

Do not use a data set name that DFSMSdss will reference during execution. Otherwise, enqueue contention with the operating system initiator will occur. In this example, the data set (MYDATSET) that has been backed up on tape in the "Dumping a Data Set" example is restored to the original DASD volume on which it resided.

```
//MYJOB
          J0B
                accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD
                SYSOUT=A
//TAPE
          DD
               UNIT=3480, VOL=SER=TAPE01,
// LABEL=(1,SL),DISP=(OLD,KEEP),DSNAME=MYDATSET.BACKUP
               UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//DASD
          DD
//SYSIN
          DD
RESTORE DATASET(INCLUDE(MYDATSET)) -
        INDDNAME(TAPE) OUTDDNAME(DASD) REPLACE
```

# Chapter 16. DFSMSdss filtering—choosing the data sets you want processed

This section is divided into the following subsections:

- "How DFSMSdss filters data sets" describes how DFSMSdss filters data sets by data set name and by data set characteristic.
- "Filtering by data set names" on page 260 explains how to specify fully and partially qualified data set names for filtering. This section includes rules for spelling out qualifiers and examples of qualified data set names.
- "Filtering by data set characteristics" on page 262 lists the data set characteristics on which filtering can be done.
- "Standard catalog search order" on page 267 identifies the standard order in which DFSMSdss searches for a data set name.

See Chapter 24, "Data set attributes," on page 643 for information about DFSMSdss and the way that it determines individual data set attributes.

### How DFSMSdss filters data sets

DFSMSdss filters data sets in the following ways:

- Applying inclusion and exclusion criteria to fully or partially qualified data set names.
  - If you specify inclusion criteria (INCLUDE), DFSMSdss tentatively selects all data sets that fit any of the criteria.
  - If you do not specify inclusion criteria, you must specify EXCLUDE or BY. In this case, DFSMSdss tentatively selects all data sets (equivalent to INCLUDE(\*\*)). For the DEFRAG command, INCLUDE(\*\*) is always implied.
  - If you specify exclusion criteria (EXCLUDE), DFSMSdss surveys the data sets that are selected with the inclusion criteria. It then rejects the data sets that fit any of the new criteria.
- Applying data set characteristics (BY) criteria to the data sets that are tentatively selected with the inclusion and exclusion criteria. DFSMSdss selects only those data sets that satisfy all BY criteria.

DFSMSdss lets you find out which data sets are selected by the filtering process without actually performing the requested operations. You can do this by specifying TYPRUN=NORUN on the JCL EXEC PARM field.

## Virtual storage access method (VSAM) data set considerations

Considerations for VSAM data sets include the following:

- INCLUDE and EXCLUDE filtering is performed on the cluster names of the data sets.
- If you specify the BY criterion DSORG, MULTI, CATLG, or FSIZE, filtering is done at the cluster level. One exception is the DEFRAG command, that filters at the VSAM component level. If you specify other BY criteria, the data components of the selected clusters are further filtered on those BY criteria by using information from the volume table of contents (VTOC). If a data

component is selected, the index component for the cluster is also selected. Again, the one exception is the DEFRAG command, that requires index components to pass all BY criteria.

- DFSMSdss supports the BY criterion EXPDT as it exists in the VTOC only.
- For a physical data set RESTORE, to prevent index components from being restored inadvertently, you must specify the fully qualified name of the cluster.
- For data set print operation, the fully qualified name of the data set to be printed is required. Support is at the component, not the cluster, level.

## Filtering by data set names

A *fully qualified* data set name is one in which all qualifiers are spelled out completely. A *partially qualified* data set name is one in which asterisks (\*) or percent signs (%) are used to represent qualifiers or parts of qualifiers.

## Using an asterisk in partially qualified data set names

The **single asterisk**, \*, is used in place of exactly *one* qualifier. In addition, it can be used to indicate to DFSMSdss that only *part* of a qualifier has been specified. For example, just the first, last, middle, or first and last parts.

When used with other qualifiers, the **double asterisk**, \*\*, indicates either the nonexistence of leading, trailing, or middle qualifiers, or the fact that they play no role in the selection process.

The rules for using asterisks in a qualifier are:

- Two asterisks are the maximum permissible in a qualifier.
- If there are two asterisks in a qualifier, they must be the first and last characters.

Consequently, the following are permissible qualifiers:

```
**
*A*
```

The following are **not** permissible qualifiers:

```
**A*
*A*B*
*A*B
A*B*C
```

## Using a percent sign in partially qualified data set names

The percent sign, %, acts as a place holder for a single character during data set name filtering.

The rules for using % in a qualifier are:

- Each % corresponds to exactly one character.
- % can be specified more than once, consecutively or in any level of the qualifier.
- A % cannot match a null (") or a period ('.').
- Use of a % in filtering does not change any of the other filtering specifications for data set names.

Consequently, specifying I%M.A.%AT%ET matches the data set names IAM.A.DATASET and IBM.A.BATTYET, but not IAM.A.DATASE, IAM.AA.DATASET, IAM.A.ATASET, or IM.A.DATASET.

## Examples of fully and partially qualified data set names

The following are examples of fully and partially qualified data set names.

#### Fully qualified data set names:

#### **USER2LD**

The first and only qualifier is USER2LD.

#### SYS1.UTIL3.LOAD

The first qualifier is SYS1, the second, UTIL3, and the third, LOAD.

#### USER2.PROGRAM1.LIST

The first qualifier is USER2, the second, PROGRAM1, and the third, LIST.

#### Partially qualified data set names using \*\*:

#### \*\*.LOAD

All data sets whose last, or only, qualifier is *LOAD*.

#### SYS1.\*\*

All data sets whose first, or only, qualifier is *SYS1*.

#### USER2.\*\*.LIST

All data sets whose first and last qualifiers are *USER2* and *LIST*, respectively, including *USER2.LIST*.

#### More partially qualified data set names:

- **\*.LOAD** All data sets with two qualifiers whose last qualifier is *LOAD*.
- **SYS1.\*** All data sets with two qualifiers whose first qualifier is *SYS1*.

#### SYS1.\*.LOAD

All data sets with three qualifiers whose first and last qualifiers are *SYS1* and *LOAD*, respectively.

#### SYS1.UT\*.LIST

All data sets with three qualifiers whose first and last qualifiers are *SYS1* and *LIST*, respectively, and whose second qualifier begins with *UT*.

#### \*\*.\*LIB

All data sets whose last, or only, qualifier ends with LIB.

#### \*\*.\*LIB\*

All data sets whose last, or only, qualifier has LIB in it.

#### \*.\*PLI\*.\*

All data sets with three qualifiers whose second qualifier has *PLI* in it.

#### \*.\*.P\*M

All data sets with three qualifiers whose last qualifier begins with P and ends with M.

- \*\* All data sets.
- **%.LIST** All data sets with one character in the first qualifier and *LIST* in the last qualifier.

#### USER%.\*

All data sets with two qualifiers whose first qualifier is *USER* followed by some other character.

\*%\* All data sets whose single qualifier consists of two or more characters.

#### Filtering by Data Set Names

Note: Single quotation marks around a data set name indicates the name is fully qualified. For example, specifying 'USER.%' selects a data set whose first qualifier is USER and whose second qualifier is the character '%'. This data set is selected using the filter USER.\* because the wildcard (\*) matches the character %.

## Relative generation filtering

DFSMSdss allows filtering on relative generations of a generation data group (GDG) data set in the INCLUDE, EXCLUDE, and REBLOCK data set name lists. A GDG is specified as dsn(n) where dsn is a fully or partially qualified base name without the last qualifier (GggggVvv), and n is the relative generation number or \* for all generations.

Guideline: The last qualifier consists of the generation number (Ggggg) and the version number (Vvv).

The following are examples of relative generation filtering:

dsn(0) For the current generation

dsn(-x)

For the xth prior generation

dsn(+x)

For the xth future generation

**dsn(\*)** For all generations.

For logical operations using catalog filtering, you must use one of the following search criteria:


- The fully qualified data set name
- The partially qualified base name with the last qualifier (GggggVvv) not specified (for example, USER1.GDG.\*)
- The above relative generation filtering

Partial qualification of the last qualifier (GggggVvv) is not supported unless a wildcard (\* or %) is specified in the first character of the qualifier. For example, USER1.GDG.\*V01 is valid, but USER1.GDG.G%%10\* is not.

**Note:** Relative generation filtering is not applicable when using the CONVERTV, COPYDUMP, or PRINT functions. These functions do not allow filtering of any kind.

## Filtering by data set characteristics

After DFSMSdss has tentatively selected data sets by applying INCLUDE and EXCLUDE criteria, you can apply BY criteria to further restrict the data sets finally chosen. You can, for example, use BY to select data sets by creation date, storage class, and a wide variety of other criteria. The BY keyword takes this form:



#### Where Represents

schar The selection characteristics:

#### Filtering by Data Set Characteristics

#### Keyword

Criteria

#### **ALLOC**

Allocation type (cylinder, track, block, absolute track, or movable)

#### **CATLG**

Whether the data set is currently cataloged or not (using the standard catalog search order)

#### **CREDT**

Creation date (absolute or relative)

#### **DSCHA**

Whether the data-set-changed flag is on or off

#### **DSORG**

Data set organization (SAM, PAM, PDS, PDSE, BDAM, HFS, EXCP, ISAM, VSAM or zFS)

#### **EXPDT**

Expiration date (absolute or relative). Data sets without expiration dates explicitly assigned to them are considered to have an expiration date of zero. If you wish to exclude these data sets from expiration date processing, you must specifically exclude them in your filtering list, that is, BY EXPDT NE 0000000.

#### **EXTNT**

Number of allocated or used extents for the entire data set on all the volumes on which it resides

**FSIZE** Number of allocated or used tracks for the entire data set on all the volumes on which it resides (data set size)

#### **MULTI**

Whether the data set is singlevolume or multivolume (Single volume data sets that have been allocated but have never been opened and are not cataloged may be selected as multivolume)

#### REFDT

Last-referenced date (absolute or relative)

#### **DATACLAS**

Data class for SMS

#### **MGMTCLAS**

Management class for SMS

#### **STORCLAS**

Storage class for SMS

#### *op* The operator:

#### Operator

Meaning

EQ or =

Equal to

#### **LE or <=**

Less than or equal to

#### LT or <

Less than

### **Filtering by Data Set Characteristics**

GT or >

Greater than

GE or >=

Greater than or equal to

NE or ¬=

Not equal to

An argument that qualifies the selection characteristic (schar). arg

Table 21 summarizes the permissible combinations of schar, op, and arg.

Table 21. BY Keywords

schar	op	arg	Notes
ALLOC	EQ NE	CYL (cylinder allocation) TRK (track allocation) BLK (block length allocation) ABSTR (absolute track allocation) MOV (movable data sets)	If MOV is picked, the data sets to be processed cannot be allocated as any of the following:  • PSU (physical sequential unmovable)  • POU (partitioned organization unmovable)  • DAU (BDAM unmovable)  • ABSTR (absolute tracks)  • ISAM (indexed sequential access method).  COMPRESS command: If MOV is picked, only data sets allocated as POU cannot be compressed.
MULTI	EQ	YES (or 1) NO (or 0)	YES: DFSMSdss processes only multivolume data sets. NO: DFSMSdss processes only singlevolume data sets.  DEFRAG command: If a data set's volume sequence number is greater than one in the VTOC, DFSMSdss assumes it is multivolume. If this sequence number is 1, DFSMSdss assumes it is a single volume data set.
			COMPRESS command: Because DFSMSdss assumes the data set is single volume, you do not need to specify MULTI.  Note: Single volume data sets that have been allocated but have never been opened and are not cataloged may be selected as multivolume.
CATLG	EQ	YES (or 1) NO (or 0)	YES: Only currently cataloged data sets are processed. NO: Only uncataloged data sets are processed.  DUMP command: The CATLG filter is valid only when used with an input volume list (INDD, INDY, LOGINDD, LOGINDY, STORGRP).
			COPY command: The CATLG filter is valid only when used with an input volume list (INDD, INDY, LOGINDD, LOGINDY, STORGRP).  RESTORE command: The target data set is tested to determine if it is
			<ul> <li>cataloged or not.</li> <li>Note:</li> <li>1. Data sets cataloged through JCL are not cataloged until the job step ends. Therefore, when you use the (CATLG,EQ,NO) filter, you should also use a CREDT or REFDT filter. The value used in the CREDT or REFDT filter should be for data sets at least two days old: (CREDT,LE,*,-2) or (REFDT,LE,*,-2).</li> <li>2. A data set is considered uncataloged if it is not cataloged in the standard order of search or if it is cataloged in an unavailable catalog.</li> </ul>

Table 21. BY Keywords (continued)

schar	op	arg	Notes
CREDT EXPDT REFDT	LT GT EQ NE GE LE	[yy]yyddd(,n): 4-digit (or 2-digit) year and 3-digit day, modified by an optional 1-digit to 4-digit positive or negative number of days, n. The year values range from 1900 through 9999. For example, 1998100 (or 98100) is the 100th day of 1998 and 2000001 (or 00001) is the first day of 2000.  *(,n): Current date (run date), modified by an optional 1-digit to 4-digit positive or negative number of days, n. For example, *,-5 is five days before this job is run.  NEVER: Never-expire date (valid only for EXPDT). A never-expire data set has an expiration date in its VTOC entry of 99365, 99366, or 99999.	The preferred form of a date has a 4-digit year (yyyyddd). When you specify a date with a 4-digit year other than a date of all zeros, the smallest valid date before modification is 1900001. When you specify a date with the 2-digit year format (yyddd), a yy of 00 through 49 indicates years 2000 through 2049; a yy of 50 through 99 indicates years 1950 through 1999. You must use the 4-digit year format if you wish to filter on years 1900 through 1949 or on years higher than 2049.  CREDT and EXPDT: For a multivolume data set, the date from its first volume's VTOC is used for checking.  EXPDT: When you specify a date of 99365 or 1999365, you are specifying the last day of 1999. When you specify EXPDT with NEVER 99366, 1999366, 99999, 19999999, or 9999999, you ask DFSMSdss to look for all valid forms of never-expire dates (including 99365 in a data set's VTOC entry). Therefore, BY(EXPDT,EQ,1999365) selects no data sets. DFSMSdss considers the valid forms of never-expire dates as equal to each other and as greater than all other dates. A never-expire date cannot be modified and cannot be specified with the GT operator.  REFDT: For a multivolume data set, the latest date from all its VTOCs is used for checking.  RELEASE and DEFRAG commands: The date in the VTOC of the
			volume being processed is used for filtering both single- and multivolume data sets.
DSCHA	EQ NE	YES (or 1) NO (or 0)	For a multivolume data set, the value used for checking is 1 if any of the indicators from all of its VTOCs is 1. Otherwise, the value is 0.
DSORG	EQ NE	SAM (all sequential data sets, including compressed and striped), PAM (partitioned data sets, including PDS and PDSE), PDS, PDSE, HFS (hierarchical file system data sets), BDAM (all direct access data sets), ISAM (all indexed sequential data sets), VSAM (includes all VSAM data set types), zFS (zFS data sets), EXCP (applies to data sets not allocated as any of the listed organizations and not accessed by using any of the listed access methods)	COMPRESS command: Because DFSMSdss assumes data set organization, you do not need to specify it.  Note: The selective characteristic of DSORG can be specified more than once.
DATACLAS MGMTCLAS STORCLAS	EQ NE	An appropriate SMS class name.	

## **Filtering by Data Set Characteristics**

schar	op	arg	Notes
EXTNT FSIZE	LT GT	nnnnnnn (1-digit to 8-digit decimal number, from 0 to	nnnnnnn is the number of used or allocated extents (EXTNT) or used or allocated tracks (FSIZE).
	EQ NE GE	99999999)	RESTORE command: The data set that was dumped determines the number of used or allocated extents or tracks.
	LE		<ul> <li>DUMP and COPY commands:</li> <li>For non-VSAM data sets: <ul> <li>If ALLDATA or ALLEXCP is specified, FSIZE is equal to the allocated tracks, and EXTNT is equal to the allocated extents.</li> <li>If ALLDATA or ALLEXCP is not specified, FSIZE is equal to the used tracks, and EXTNT is equal to the used extents.</li> <li>Note: A specification of FSIZE,EQ,0 can be used to select PDSE data sets that have no members (that is, have no used directory blocks), and a specification of FSIZE,NE,0 can be used to exclude PDSE data sets that have no members.</li> <li>For VSAM data sets, FSIZE is always equal to the allocated tracks, and EXTNT is always equal to the allocated extents.</li> </ul> </li> <li>Logical data set COPY, DUMP, and RESTORE commands: <ul> <li>FSIZE criteria are applied once for the entire data set on all volume that the data set resides on. For logical processing of HFS files with TYPRUN NORUN, FSIZE equals all of the allocated space. For logical processing of HFS files without TYPRUN NORUN, the used space represents the FSIZE unless ALLDATA was specified.</li> <li>EXTNT criteria are applied to non-VSAM data sets once for the data set on all volumes that the data set resides on.</li> <li>EXTNT criteria are applied to each VSAM data component on all volumes that the VSAM data component resides on. If a VSAM data component is selected by EXTNT filtering, the index component for the cluster is automatically selected.</li> </ul> </li> </ul>
			<ul> <li>Physical data set DUMP and RESTORE commands:</li> <li>FSIZE criteria are applied once for each volume being processed of non-VSAM or VSAM data set. For HFS data sets, FSIZE equates to the allocated space, not the space actually used.</li> <li>EXTNT criteria are applied once for each volume being processed of a non-VSAM data set or VSAM data component. If a VSAM data component residing on a volume is selected by EXTNT filtering, the index component (if any) residing on the same volume for the clust is automatically selected.</li> <li>FSIZE and EXTNT can be used to select certain volumes of a multivolume data set without selecting all of the volumes that the data set resides on.</li> </ul>
			DEFRAG commands:  • For VSAM data sets, EXTNT and FSIZE criteria are applied at the VSAM component level for the volume being processed only. EXTN and FSIZE filtering are performed for both VSAM data and index components; VSAM index components are not automatically selected if the data component for the cluster is selected.  • For non-VSAM data sets, EXTNT and FSIZE criteria are applied for

#### Note:

- 1. When multiple arguments are specified for an NE operation, DFSMSdss selects only those data sets not matching any of the arguments.
- 2. When multiple arguments are specified for an EQ operation, DFSMSdss selects those data sets matching any of the arguments.

the volume being processed only. For HFS data sets, FSIZE equates to

the allocated space, not the space actually used.

3. BY criteria do not apply for the CONVERTV or COPYDUMP commands.

### Some examples of the BY keywords

```
If you code

BY((ALLOC EQ CYL) (CATLG EQ YES))

you receive all cataloged data sets with cylinder allocation.

If you code

BY(FSIZE GE 100)

you receive all data sets whose size is greater than or equal to 100 tracks.
```

If you code
BY(DSORG EQ (PAM,SAM))

DFSMSdss selects all partitioned and sequential data sets.

### Standard catalog search order

When catalogs are searched for a data set name, the standard order of the search is:

- 1. DFSMSdss first searches the catalogs specified with INCAT, if any. If INCAT and ONLYINCAT are specified, the following steps are skipped.
- 2. DFSMSdss searches the user catalog when the data set name meets one of the following criteria:
  - The data set is a qualified name and is the name of a user catalog.
  - The data set name is the same as the alias of a user catalog.
- 3. DFSMSdss searches the master catalog.

#### Broken data set considerations

Broken data sets are data sets that do not comply with defined IBM data set standards. This includes data sets for which catalog entries, VTOC entries, or VSAM volume data set (VVDS) entries are either missing or invalid. DFSMSdss may not properly select broken data sets for processing because DFSMSdss relies on the validity of these structures during filtering.

### **Catalog Search Order**

### Chapter 17. Syntax—DFSMSdss function commands

This topic describes DFSMSdss *function* commands. Function commands specify operations, or "tasks," for DFSMSdss to perform. The following function commands specify such tasks:

- BUILDSA
- CGCREATED
- COMPRESS
- CONSOLIDATE
- CONVERTV
- COPY
- COPYDUMP
- DEFRAG
- DUMP
- PRINT
- RELEASE
- RESTORE

Part 1, "DFSMSdss Storage Administration Guide," on page 1 contains usage notes, including DFSMSdss restrictions.

### What DFSMSdss commands do

DFSMSdss commands can perform a variety of functions.

### Building the stand-alone IPL-able core image

The DFSMSdss BUILDSA command allows you to build the Stand-Alone Services IPL-able core image. The core image is used to IPL Stand-Alone Restore.

### Using DUMP and RESTORE for backup and recovery

DFSMSdss can be used to back up data so that it can be recovered in the event of hardware failure, application failure, or user error. DFSMSdss can back up and recover data sets, entire volumes, or specific tracks. The DFSMSdss DUMP command is used to back up tracks, volumes, and data sets, whereas the RESTORE command is used to recover them. DFSMSdss may be used for the following backup functions:

- Back up data on direct-access storage devices (DASD).
- Restore data from the backup if the original becomes lost, damaged, or inadvertently changed.
- Back up application data for vital records purposes and disaster recovery.

For information about how to back up and restore Linux for System z partitions and volumes, see Chapter 12, "Dumping and restoring Linux for System z partitions and volumes," on page 185.

### Moving data with COPY

You must move data in order to replace storage devices, add storage capacity, and meet storage requirements. DFSMSdss allows you to perform the following data set movements:

· Move data sets from old to new DASD.

#### **Syntax—Function Commands**

- Move data sets between Storage Management Subsystem (SMS) and non-SMS-managed volumes.
- Move data sets off a volume when requiring hardware maintenance.
- Move or copy data sets for other purposes.

The DFSMSdss COPY command performs data set, volume, and track movement.

Data sets may move from one DASD volume to another volume of either like or unlike device types. Where like devices have the same track capacity (3390 Model 2 and 3390 Model 3), unlike devices have different track capacities (3380 Model K and 3390 Model 3).

If you copy a full volume or range of tracks, however, the DASD must be of like device type. The user must specify the source and target volumes. This process permits only one source volume and one target volume.

### Converting to and from Storage Management Subsystem (SMS) with CONVERTV

SMS allows you to match the needs of users' data (like data set organization, size, and format) to the characteristics of storage devices without requiring user knowledge or understanding of the installation's hardware configuration. With SMS, users can both store and retrieve data without awareness of space limitations, device characteristics, and volume serial numbers.

The DFSMSdss CONVERTV command can convert existing volumes to and from SMS management without moving data.

### Managing space with COMPRESS, CONSOLIDATE, DEFRAG, and RELEASE

DFSMSdss provides features which consolidate free space on volumes, compress partitioned data sets, release unused data set space and combine data sets extents.

To help prevent out-of-space abends on new allocations you can use:

- The DFSMSdss COMPRESS command to compress partitioned data sets by consolidating unused space at the end of the data set.
- The DFSMSdss CONSOLIDATE command to combine as many extents of a data set into as few contiguous extents as possible.
- The DFSMSdss DEFRAG command to consolidate free space on a volume.
- The DFSMSdss RELEASE command to free unused space for use by other data sets within sequential, partitioned, and extended-format VSAM data sets.

### Using COPY for partitioned data set (PDS) and partitioned data set extended (PDSE) conversions

The DFSMSdss COPY command can move or copy a PDS, then convert the PDS to a PDSE, and vice versa.

### Copying DFSMSdss-produced dump data with COPYDUMP

The DFSMSdss COPYDUMP command can create a maximum of 255 copies of DFSMSdss-produced dump data.

### Printing for diagnostic purposes with PRINT

DASD data may be printed to SYSPRINT or to a sequential data set, in print format. For data set printing, tracks are printed in a logical sequence reflecting the data set on the volume. It does not reflect the data set within the physical cylinder or head sequence.

The DFSMSdss PRINT command prints the following:

- A single-volume, non-virtual storage access method (non-VSAM) data set.
- A single-volume VSAM data set component.
- All or part of the VTOC.
- · Ranges of tracks.

### **BUILDSA command for DFSMSdss**

Use the BUILDSA command to build the IPL-able core image for the Stand-Alone Services program. With the BUILDSA command you can specify the device (card reader, tape drive, or DASD volume) from which Stand-Alone Services will be IPLed. You can also specify the operator console to be used for Stand-Alone Services.

The BUILDSA function allocates temporary data sets if needed for BUILDSA processing. These data sets are deleted when the BUILDSA operation is complete. System-generated, temporary data set names are used.

The BUILDSA function invokes the linkage editor (or Binder) utility. Specify UTILMSG=YES when you run the BUILDSA function, and keep the output as a debugging reference when you run the Stand-Alone Services program.

The BUILDSA function builds the IPL-able core image under the current operating system, and determines a record size based on whether the IPL is from card, tape, or DASD.


#### Note:

- 1. BUILDSA never allocates a core image data set in the EAS of an EAV.
- 2. The core image sequential data set is allocated with an EATTR value of NO. This will result in the data set being allocated in the track-managed region of a volume regardless of whether it is an EAV.
- 3. The Stand-Alone Services modules reside in target library SYS1.SADRYLIB after they are installed and accepted by System Modification Program (SMP) or System Modification Program Extended (SMP/E). If you name this data set something other than SYS1.SADRYLIB, then substitute that name for SYS1.SADRYLIB in the examples shown later in this section.
- 4. Stand-Alone Services does not support the creation of the core image on an SMS-managed volume.
- 5. To ensure that Stand-Alone Services is available when you run from DASD, do not delete the SYS1.ADR.SAIPLD.V*volser* data set or move it to another volume.
- 6. If you IPL from DASD and later change the volume serial number, you must rerun the BUILDSA function to create a new core image data set with the new volume serial number in the name.
- 7. Consider creating a password or providing other security protection for the SYS1.ADR.SAIPLD.Vvolser data set and for the Stand-Alone Services modules.

#### **BUILDSA Command for DFSMSdss**

8. If you specify TYPRUN=NORUN with the EXEC statement, the BUILDSA task ends without processing input or output.

### **BUILDSA syntax**



### Explanation of BUILDSA command keywords

This section describes the keywords for the BUILDSA command.

#### **ADMINISTRATOR**



ADMINISTRATOR specifies that you are a DFDSS-authorized or DFSMSdss-authorized administrator for the BUILDSA command. If you are not authorized to use the ADMINISTRATOR parameter, the command is ended with an error message. If you are authorized, and you have access authorization to the output data set, you may create an IPL-able core image for the DASD volume. The ADMINISTRATOR parameter does not give you access to the input data sets, or to the output data sets for IPL(TAPE) or IPL(CARD).

To use the ADMINISTRATOR parameter, all of the following must be true:

- FACILITY class is active.
- Applicable FACILITY-class profile is defined.
- You have READ access to that profile.

For more details, see "Understanding BUILDSA command authorization levels" on page 528.

#### INDDNAME



INDDNAME specifies the DD card in the JCL that identifies the partitioned data set that contains the information that is needed to build the STAND-ALONE Services core image. This is the target library (SYS1.SADRYLIB) where the Stand-Alone Services modules are placed after the SMP or SMP/E install is complete.

ddname1 specifies the name of the DD statement that identifies a volume whose partitioned data set contains the input information.

#### **IPL**



IPL specifies the type of device from which Stand-Alone Services is to be IPLed. The system then creates the appropriate loader for the specified device type. If you do not specify the IPL parameter, the system creates a core image suitable for IPLing from a card reader (or a tape drive).

CARD specifies that the core image is to be used for IPLing from a card reader. As a result, the core image is created with BLKSIZE=80 and LRECL=80, and is placed in the data set specified by the OUTDD parameter. You can use this core image to IPL from a card reader (or a tape drive). If you specify CARD, you must also specify the OUTDDNAME parameter. Create the output data set with DSORG=PS, RECFM=F, BLKSIZE=80 and LRECL=80.

TAPE specifies that the core image is to be used for IPLing from a tape drive. As a result, the tape is created with a blocksize optimized for tape. IBM recommends that you specify TAPE when IPLing from a tape drive. If you specify TAPE, you must also specify the OUTDDNAME parameter. Create the output data set with DSORG=PS, RECFM=U, BLKSIZE=32760, and LRECL=32760.

Note that you cannot use an encrypted tape as the source for an IPL. If you attempt to do so, DFSMSdss fails the BUILDSA command.

**DASD** specifies that the core image is to be used for IPLing from a DASD volume. As a result, the core image is created with a record size optimized for DASD. If you specify DASD, you must also specify the OUTDYNAM parameter. The core image is placed in data set SYS1.ADR.SAIPLD.V*volser*, which is allocated by Stand-Alone Services in the volume specified on the OUTDYNAM parameter (that is, the volume from which the Stand-Alone Services program is to be IPLed). This core image can only be used to IPL from the DASD volume specified in the OUTDYNAM parameter.

Additionally, the BUILDSA command invokes the ICKDSF REFORMAT command to place the IPLTEXT and bootstrap records on this volume. The BUILDSA command provides ICKDSF with IPLTEXT necessary to IPL the Stand-Alone Services core image.

**Note:** Stand-Alone Services does not support the creation of the core image from an SMS-managed volume.

#### **OPERCNSL**



OPERCNSL specifies the device address to be used as the operator console when running Stand-Alone Services.

#### **BUILDSA Command for DFSMSdss**

*ccuu* specifies that Stand-Alone Services attempt to use the device address as the operator console instead of using the device that generates the first interrupt. Specify a valid device that exists in the configuration where the Stand-Alone Services program will be executed. You can specify a 3-digit or 4-digit address.

SERV specifies that the ES/9000 service console be used as the Stand-Alone Services operator console instead of a unit address.

When OPERCNSL is not specified, Stand-Alone Services loads a wait-state, and then waits for the operator console to generate an interrupt. Limited verification of this parameter is performed during processing of the BUILDSA command. For more information about the predefined console, see "Running stand-alone services with a predefined console" on page 513.

#### OUTDDNAME



OUTDDNAME specifies the output location for the IPL-able core image.

ddname2 specifies the DD card in the JCL where the IPL-able core image is placed when IPL(TAPE) or IPL(CARD) is specified.

When IPL(TAPE) is specified, it becomes the physical sequential data set where the core image (including bootstrap) is placed to IPL from a tape drive.

When IPL(CARD) is specified, it becomes the physical sequential data set where the core image (including bootstrap) is placed to IPL from a card reader. If this is a DASD data set, you can then punch it to cards or use it in a VM virtual card reader for IPL.

Specify either OUTDDNAME or OUTDYNAM, not both. When OUTDDNAME is specified, IPL(CARD) is the default. You can specify the IPL(CARD) parameter or the IPL(TAPE) parameter.

#### **OUTDYNAM**



OUTDYNAM specifies the output volume serial number for the DASD volume where the IPL-able core image is placed when IPL(DASD) is specified.

volser specifies the name of the DASD volume from which the Stand-Alone Services program will be IPLed.

The IPL bootstrap and IPLTEXT (needed to read in the core image) are placed on this volume. Additionally, Stand-Alone Services allocates data set SYS1.ADR.SAIPLD.Vvolser on this volume and places the core image into this data set. If the SYS1.ADR.SAIPLD.Vvolser data set already exists, Stand-Alone Services deletes and reallocates it.

Specify either OUTDDNAME or OUTDYNAM, not both. When OUTDYNAM is specified, IPL(DASD) must also be specified.

### **BUILDSA** command examples

### Example 1: core image using the default parameters

In this example, the IPL parameter is not specified, so the default (CARD) is used. Stand-Alone Services is created with BLKSIZE=80, LRECL=80, a bootstrap, and is placed in a data set on volume 339001. This core image can be used to IPL from a tape or a card reader. You can either punch the Stand-Alone Services program to a card reader or use IEBGENER to copy the Stand-Alone Services program to tape. The OPERCNSL parameter is not specified; after Stand-Alone Services is IPLed, it loads a wait-state and then waits for the first interrupt to define the operator console.

**Note:** The DCB parameters must be coded as shown.

```
//BUILDSA JOB accounting information, REGION= nnnnK
//STEP1
           EXEC PGM=ADRDSSU, PARM='UTILMSG=YES'
//SAMODS DD DSN=SYS1.SADRYLIB,DISP=SHR
//CARDDD DD DSN=ADRSA.IPLC,UNIT=3390,
           DISP=(NEW, KEEP), VOL=SER=339001,
//
           SPACE=(TRK, (40,5)),
//
           DCB=(DSORG=PS, RECFM=F, BLKSIZE=80, LRECL=80)
//SYSPRINT DD SYSOUT=A
//SYSIN
           DD *
 BUILDSA -
           INDD(SAMODS) -
           OUTDD (CARDDD)
```

The following example copies the Stand-Alone Services core image (created in Example 1) to tape.

**Note:** The DCB parameters must be coded as shown.

```
//COPYSA JOB accounting information
//STEP1 EXEC PGM=IEBGENER
//SYSPRINT DD SYSOUT=A
//SYSUT1 DD DSN=ADRSA.IPLC,DISP=SHR,VOL=SER=339001,UNIT=3390,
// DCB=(RECFM=F,BLKSIZE=80,LRECL=80)
//SYSUT2 DD DSN=DSSSA,DISP=(,KEEP),VOL=SER=T11002,LABEL=(,NL),
// DCB=(RECFM=F,BLKSIZE=80,LRECL=80),
/// UNIT=3480
//SYSIN DD DUMMY
/*
```

#### Example 2: core image for IPL from tape

In this example, Stand-Alone Services is created for IPLing in stand-alone mode from a tape. The core image is then placed on an unlabeled tape. The OPERCNSL option is not specified; after Stand-Alone Services is IPLed, it loads a wait-state and then waits for the first interrupt to define the operator console.

Note: The DCB parameters must be coded as shown.

```
//BUILDSA JOB accounting information, REGION= nnnnK
//STEP1
           EXEC PGM=ADRDSSU, PARM='UTILMSG=YES'
//SAMODS
           DD DSN=SYS1.SADRYLIB,DISP=SHR
//TAPEDD
          DD DSN=ADRSA.IPLT,UNIT=3480,LABEL=(,NL),
              DISP=(NEW, KEEP), VOL=SER=TAPE01,
              DCB=(DSORG=PS, RECFM=U, BLKSIZE=32760, LRECL=32760)
//SYSPRINT DD SYSOUT=A
//SYSIN
          DD *
 BUILDSA -
           INDD(SAMODS) -
           OUTDD(TAPEDD) -
           IPL(TAPE)
```

### **Example 3: core image for IPL from DASD**

In this example, the core image is created for IPLing in stand-alone mode from the DASD with volume label IPLVOL. The core image, the IPL bootstrap, and IPLTEXT are all placed on volume IPLVOL in data set SYS1.ADR.SAIPLD.VIPLVOL. The OPERCNSL option is not specified; after Stand-Alone Services is IPLed, it loads a wait-state and then waits for the first interrupt to define the operator console.

# Example 4: core image for IPL from DASD with OPERCNSL option

In this example, the core image is created for IPLing in stand-alone mode from the DASD with volume label IPLVOL. The core image, the IPL bootstrap, and IPLTEXT are all placed on volume IPLVOL in data set SYS1.ADR.SAIPLD.VIPLVOL. The OPERCNSL customization option is specified for the operator console definition; after Stand-Alone Services is IPLed, it attempts to use the device at address 0009 as the operator console instead of waiting for the first interrupt.

#### **CGCREATED** command for DFSMSdss

The CGCREATED command signals that a FlashCopy Consistency Group has been formed or aborted. I/O activity can resume on the "frozen" FlashCopy source volumes previously established by specifying FCCGFREEZE on the COPY command.

#### **CGCREATED Command for DFSMSdss**

The CGCREATED operation is processed at logical subsystem (LSS) level. It thaws all the volumes currently in "frozen for consistency grouping" state in the LSS that received the command. When a "thaw" command is received by an LSS that does not have any frozen volumes in a FlashCopy Consistency Group, the command is accepted, but no actual processing takes place.

The freeze and thaw operations require the specified devices support the FlashCopy Consistency Group function. Appropriate LIC level is required on the ESS Model 800, the DS8000<sup>®</sup>, or the DS6000<sup>TM</sup>.

The CGCREATED command is restricted by RACF FACILITY-Class profile 'STGADMIN.ADR.CGCREATE'.


For additional information about creating consistent copies with FlashCopy Consistency Group, refer to "Backing up volumes with FlashCopy consistency group" on page 135.

For additional information about FlashCopy Consistency Group, refer to *z/OS DFSMS Advanced Copy Services* and the IBM TotalStorage ESS User's Guide.


For additional information about RACF authorization, refer to Chapter 5, "Protecting DFSMSdss functions," on page 27.

For additional information about RACF FACILITY class profiles, refer to *z/OS Security Server RACF Security Administrator's Guide*.

### **CGCREATED** syntax



#### A: Optional keywords::



### **Explanation of CGCREATED command keywords**

This section describes the keywords for the CGCREATED command.

#### **ACCESSVOLUME**

volser Specifies the volume serial number of a CKD volume.

ACCESSVOLUME specifies one or more CKD access volumes to be used for a z/OS host to communicate with the storage facility and to direct the "Consistency Group Created" command to the logical subsystems where the access volumes reside. The volumes must be mounted and online. You can specify up to 255 volumes. You cannot specify a nonspecific volume serial number using an asterisk (\*).

#### **CGCREATED Command for DFSMSdss**

ACCESSVOLUME is a required keyword on the CGCREATED command. Because the CGCREATED command is processed at LSS level, only one volume needs to be specified for each LSS containing frozen volumes in the FlashCopy Consistency Group.

If the specified access volume does not reside in an LSS with Consistency Group timer enabled or if the storage facility does not support FlashCopy Consistency Group, the CGCREATED command will fail for the volume.

#### **FCCGVERIFY**

Specifies the volume serial number of the FlashCopy Consistency Group verification volume.

FCCGVERIFYFRZSTATE specifies one ore more volume serial numbers of the verification volumes that DFSMSdss will use to validate the state of the FlashCopy Consistency Group before thawing all the volumes. This will help you determine if the copies of the group of volumes are consistent. An error message is issued if the frozen state cannot be verified. Regardless of the verification result, DFSMSdss will proceed to thaw all the volumes in the designated logical subsystems.

For the verification volume, IBM recommends that you select the first source volume that was copied with FCCGFREEZE in the group. When the logical subsystems have different Consistency Group timer values, select the volume residing in the LSS with the smallest Consistency Group timer value, or select one volume from each LSS.

#### COMPRESS command for DFSMSdss

The COMPRESS command compresses partitioned data sets on a specified volume. Compressing (degassing) removes unused space between members in a partitioned data set. Depending on the filtering criteria that you specify, you can compress either all or some of the partitioned data sets. This command is useful for compressing system partitioned data sets before you apply maintenance (to avoid certain space-related abends).

Restriction: You must not compress data sets that contain DFSMSdss or IEBCOPY executable code.


The actual PDS compression is done on the existing volume using the IEBCOPY utility. To prevent loss of data if the system or IEBCOPY abnormally ends during the processing, back up volumes or data sets that meet the filtering criteria before you use the COMPRESS command.

The COMPRESS command cannot process partitioned data sets that:


- Are unmovable
- Have no directory

### **COMPRESS** syntax





### A: Additional Keywords with the COMPRESS command:



## **Explanation of COMPRESS command keywords**

This section describes the keywords for the COMPRESS command.

#### **ADMINISTRATOR**



ADMINISTRATOR allows you to act as a DFSMSdss-authorized storage administrator for the COMPRESS command. DFSMSdss-initiated access checking to data sets and catalogs is bypassed. If you are not authorized to use the ADMINISTRATOR keyword, the command ends with an error message.

To use the ADMINISTRATOR keyword, all of the following conditions must be true:

#### **COMPRESS Command for DFSMSdss**

- FACILITY class is active.
- The applicable FACILITY-class profile is defined.
- You have READ access to that profile.

For more details, see "ADMINISTRATOR keyword" on page 541.

#### BY



BY specifies that the data sets selected up to this point, by the processing of the INCLUDE and EXCLUDE keywords, are to be further filtered. To select the data set, all BY criteria must be met. See "Filtering by data set characteristics" on page 262 for a full discussion of schar, op, and arg. See the separate discussions of the INCLUDE and EXCLUDE keywords for information on how these keywords are specified.

Rule: You must use FILTERDD when you have more than 255 entries in the INCLUDE, EXCLUDE, or BY list keywords.

#### DDNAME



ddn Specifies the name of the DD statement that identifies a volume whose partitioned data sets, if selected, are to be compressed. To assure correct processing, each of the DD statements corresponding to a DDNAME (ddn) must identify only one volume serial number.

For additional information about storage requirements when processing multiple volumes, see the "Storage requirements" on page 11.

#### **DYNALLOC**




DYNALLOC specifies dynamic allocation, instead of enqueue, to serialize the use of selected partitioned data sets. This allows cross-system serialization in a JES3/MVS environment.

#### Consider:

- The serialization is of value only when the dynamic allocation/JES3 interface is not disabled.
- Run time increases when DYNALLOC is used to serialize data sets (as opposed to enqueue) because overhead is involved in dynamic allocation and serialization across multiple processors.

#### **DYNAM**



DYNAM specifies a dynamically allocated volume whose partitioned data sets, if selected, are to be compressed. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*). Consider using DYNAM instead of DD statements to allocate DASD volumes. This does not appreciably increase run time and permits easier coding of JCL and command input.

volser Specifies the volume serial number of a DASD volume to be processed.

*unit* Specifies the device type of a DASD volume to be processed. This parameter is optional.

For additional information regarding storage requirements when processing multiple volumes, see the "Storage requirements" on page 11.


#### **EXCLUDE**



dsn Specifies the name of a data set to be excluded from the data sets selected by the INCLUDE keyword. Either a fully or a partially qualified data set name can be used. See the separate discussions of the INCLUDE and BY keywords for information on how they are specified.

**Rule:** You must use FILTERDD when you have more than 255 entries in the INCLUDE, EXCLUDE, or BY list keywords.

#### **FILTERDD**



ddn Specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set that contains the filtering criteria to use. This is in the form of card-image records, in DFSMSdss command syntax, that contain the INCLUDE, EXCLUDE, and BY keywords that complete the syntax of the COMPRESS command.

**Rule:** You must use FILTERDD when you have more than 255 entries in the INCLUDE, EXCLUDE, or BY list keywords.

#### **COMPRESS Command for DFSMSdss**


#### **INCLUDE**



dsn Specifies the name of a data set eligible to be compressed. Either a fully or a partially qualified data set name can be used. See "Filtering by data set names" on page 260. If INCLUDE is omitted (but EXCLUDE or BY is specified) or if INCLUDE(\*\*) is specified, all partitioned data sets are eligible to be selected for compressing. See the separate discussions of EXCLUDE or BY for information on how these keywords are specified.

Rule: You must use FILTERDD when you have more than 255 entries in the INCLUDE, EXCLUDE, or BY list keywords.

#### **PASSWORD**



PASSWORD specifies the passwords DFSMSdss uses for selected password-protected data sets. (Password checking is bypassed for data sets that are protected by the resource access control facility (RACF).) This must be specified only if:

- You do not have the required RACF DASDVOL or RACF DATASET access.
- The installation authorization exit does not bypass the checks.

Note: You should specify the passwords for all data sets that do not have RACF protection but do have password protection. During processing, a utility invoked by DFSMSdss may have to prompt the operator for a password. You can control authorization checking by using the installation authorization exit.


ddn Specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set that contains data set names and their passwords. This data set must contain card-image records in DFSMSdss command syntax format.

dsn/pswd

dsn is a fully qualified data set name. pswd is its password. If no password follows the slash (/), *dsn* is treated as though it were *ddn*.

Printing of actual data set passwords specified in your input command stream is suppressed in the SYSPRINT output.

#### WAIT



#### **COMPRESS Command for DFSMSdss**

WAIT specifies to DFSMSdss the length of a wait in seconds and the number of retries to obtain control of a data set.

numsecs

Is a decimal number (0–255) that specifies the interval, in seconds, between retries.

numretries

Is a decimal number (0–99) that specifies the number of times an attempt to gain control of a data set can be retried.

The default for *numsecs,numretries* is WAIT(2,2), which specifies two retries at 2-second intervals. If you do not want to wait for a data set, specify 0 for either numsecs or numretries.

**Note:** The WAIT keyword does not control wait/retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is 3 seconds and the default retry count is 30. This results in a total wait time of 90 seconds.

For information about controlling the wait/retry attempts for system resources, see the "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

### **Example of compress operations**

The following example compresses a selected partitioned data set.

Compress partitioned data sets on volume 338000 if:

- They are not system data sets (EXCLUDE(SYS1.\*\*)), and
- They have not been updated (DSCHA EQ 0) since the last time they were backed up (dumped). This ensures that the data set can be recovered if the system fails while the compress operation is running.

### **CONSOLIDATE** command for DFSMSdss

When you enter the CONSOLIDATE command, DFSMSdss performs extent reduction by combining multiple extents of a data set into as few extents as possible given the contiguous free space on a volume. You can specify which data sets are to be included and excluded from this processing.


The amount of time needed for a CONSOLIDATE operation to complete depends on the size of the volume and the number of multiple extent data sets to be processed. In general, larger volumes and data sets with many extents take longer to complete. You can use the MAXTIME keyword to control the amount of time that the CONSOLIDATE operation is allowed to run. For more information, see "MAXTIME" on page 291.

#### **CONSOLIDATE Command for DFSMSdss**


Attention: Canceling the CONSOLIDATE command is strongly discouraged, because doing so can damage data in numerous and unpredictable ways. Before entering this command, consider how long the CONSOLIDATE operation will take by evaluating the size of the volume and the number of data sets with multiple extents to be processed.

### **CONSOLIDATE** command syntax


The syntax of the CONSOLIDATE command is:




#### A: Additional Keywords with CONSOLIDATE:



#### **B: Optional Keywords with CONSOLIDATE:**



#### **CONSOLIDATE Command for DFSMSdss**



### **Explanation of CONSOLIDATE command keywords**

This section describes the keywords for the CONSOLIDATE command.

#### **ADMINISTRATOR**



The ADMINISTRATOR keyword allows you to act as a DFSMSdss authorized storage administrator for the CONSOLIDATE command. For administrators, DFSMSdss bypasses access checking for data sets and catalogs.

To use the ADMINISTRATOR keyword, all of the following must be true:

- The RACF FACILITY class is active
- The applicable FACILITY class profile is defined
- You have READ access to that profile.

If you are not authorized to use the ADMINISTRATOR keyword, the command ends with an error message.

For more information, see "ADMINISTRATOR keyword" on page 541.

#### **CONSOLIDATE Command**

#### BY



The BY keyword specifies additional filtering criteria for the data sets specified on the INCLUDE and EXCLUDE keywords. To be selected, a data set must satisfy this criteria.

For information about BY filtering, see "Filtering by data set characteristics" on page 262.

Note: You must use FILTERDD when you specify more than 255 entries on the INCLUDE, EXCLUDE, or BY keywords.

#### CANCELERROR



The CANCELERROR keyword specifies that the CONSOLIDATE operation is to be ended if any of the following errors occur:

- · Permanent read error, such as a data check. Processing of the data set ends and the CONSOLIDATE operation is ended.
- · Write error, such as an incorrect track format. Processing of the data set ends and the CONSOLIDATE operation continues with the next data set.

If you omit the CANCELERROR keyword, and CONSOLIDATE processing encounters a permanent read error, the track in error is not copied and processing continues with the next data set.

The CANCELERROR keyword has no effect with the following types of DASD volume errors:

- Equipment check
- Command reject
- Intervention required
- · Busout parity.

For information about handling errors for incorrect tracks, see Chapter 10, "Diagnosing problems in DFSMSdss operations," on page 167.

#### DATASET




The DATASET keyword specifies the data sets to be consolidated.

For a description of the data set filtering process, see Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259.

**Note:** Using the DATASET keyword requires that you also specify the FILTERDD, INCLUDE, EXCLUDE, or BY keywords.

#### **DEBUG**



You can use the DEBUG keyword as a diagnostic tool. Specify DEBUG with one of the following sub-keywords:

#### **TRACE**

Specifies that DFSMSdss is to print messages that identify the relocated extents.

#### **FRMSG**

Specifies that DFSMSdss is to issue messages that explain why you cannot use fast replication or Preserve Mirror during a CONSOLIDATE operation. For Preserve Mirror operations, the DEBUG(FRMSG) keyword might not have an effect if the FlashCopy target is not a PPRC Primary device. Specify DEBUG(FRMSG) with an additional sub-keyword, as follows:

#### FRMSG(MINIMAL)

Specifies that DFSMSdss is to issue a message with a minimal level of information.

#### FRMSG(SUMMARIZED)

Specifies that DFSMSdss is to issue a message with summarized information. When applicable, summarized information regarding ineligible volumes is provided in the message text.

#### FRMSG(DETAILED)

Specifies that DFSMSdss is to issue a message with detailed information. When applicable, detailed information regarding ineligible volumes is provided in the message text.

#### Note:

- 1. If you specify FASTREPLICATION(REQUIRED) without specifying the DEBUG keyword, DFSMSdss issues an informational message whenever a fast replication method cannot be used.
- 2. The FRMSG sub-keyword overrides the DEBUG=FRMSG parameter specified on the JCL EXEC statement.

#### **DYNALLOC**



The DYNALLOC keyword requests that dynamic allocation, rather than enqueuing, be used as the serialization method for relocating data set extents. Use DYNALOC when you require cross-system serialization in a JES3 environment.

#### **CONSOLIDATE Command**

#### Note:

- 1. Serialization is of value only for dynamic allocation or when the JES3 interface is enabled.
- 2. Using the DYNALLOC keyword to serialize data set access (as opposed to enqueuing) will increase run-time because of the additional processing involved in dynamic allocation and performing serialization across multiple processors.
- 3. If a data set passes INCLUDE/EXCLUDE filtering, and is migrated before BY filtering, and you specify the DYNALLOC keyword, dynamic allocation causes the data set to be recalled. DFSMSdss waits for the recall processing to complete. If the data set is recalled to a different volume, DFSMSdss issues a message to indicate that the VTOC entry was not found.
- 4. For an HFS source data set, CONSOLIDATE processing ignores the DYNALLOC keyword, and, instead, attempts to obtain a SYSZDSN enqueue for the data set. If the enqueue attempt fails, DFSMSdss attempts to quiesce the data set.

#### **EXCLUDE**




The EXCLUDE keyword specifies one or more data sets (*dsn*) to be excluded from processing by the INCLUDE keyword. You can specify fully or partially qualified data set names.

For information about the INCLUDE and BY keywords, see "INCLUDE" on page 290 and "BY" on page 286.

**Note:** You must use FILTERDD when you specify more than 255 entries on the INCLUDE, EXCLUDE, or BY keywords.

#### **FASTREPLICATION**



The FASTREPLICATION keyword specifies whether the use of fast replication is required, preferred, or not desired for the CONSOLIDATE operation. This keyword applies to fast replication methods, such as FlashCopy and SnapShot.

#### **REQUIRED**

Specifies that fast replication must be used. If fast replication cannot be used, DFSMSdss stops processing the current data set, and continues with subsequent data sets. If you do not specify the DEBUG keyword, DFSMSdss issues summarized information to indicate why you cannot use fast replication.

#### **PREFERRED**


This is the default. The PREFERRED keyword specifies that the use of fast

replication is preferred. If fast replication cannot be used, DFSMSdss completes the CONSOLIDATE operation using traditional data movement methods.

#### **NONE**

Specifies that fast replication should not be used. DFSMSdss completes the CONSOLIDATE operation using traditional data movement methods.

#### **FCTOPPRCPRIMARY**



The FCTOPPRCPRIMARY keyword specifies that if FlashCopy is used to perform the CONSOLIDATE operation, a Peer-to-Peer Remote Copy (PPRC) primary volume can become a FlashCopy target volume. Use the following sub-keywords to specify whether the device pair is allowed to go to duplex pending state if the target volume of the FlashCopy operation is a metro mirror primary device:

#### **PRESMIRREQ**

specifies that if the target volume is a Metro Mirror primary device, the pair must not go into a duplex pending state as the result of a FlashCopy operations.

#### **PRESMIRPREF**

specifies that if the target volume is a Metro Mirror primary device, it would be preferable that the pair does not go into a duplex pending state as the result of a FlashCopy operation. However, if a Preserve Mirror operation cannot be accomplished, the FlashCopy operation is still to be performed.

#### **PRESMIRNONE**

specifies that Preserve Mirror operation is not to be done, even if all of the configuration requirements for a Preserve Mirror operation are met. If the target specified is a Metro Mirror primary device, the pair is to go into a duplex pending state while the secondary device is updated with the tracks to be copied. PRESMIRNONE is the default if you specify FCTOPPRCPrimary without a subkeyword.

**Attention:** When you specify FCTOPPRCPrimary or

FCTOPPRCPrimary(PRESMIRNONE), the FlashCopy operation causes a PPRC primary volume to become a FlashCopy target volume. A Metro Mirror or Global Copy pair currently in full duplex state, goes into a duplex pending state when the FlashCopy relationship is established. When Metro Mirror or Global Copy completes the copy operation, the Metro Mirror or Global Copy pair goes to full duplex state. To prevent Metro Mirror or Global Copy pairs from going to duplex pending state during FlashCopy operation, you must specify FCTOPPRCPrimary(PRESMIRREQ).

#### Note:

1. Using FCTOPPRCPRIMARY might require RACF authorization.

#### **CONSOLIDATE Command**

- 2. When FlashCopy is not used to perform the CONSOLIDATE operation, the FCTOPPRCPRIMARY keyword is ignored.
- 3. If you do not specify FCTOPPRCPRIMARY, or your storage subsystem does not support this capability, a PPRC primary volume cannot become a FlashCopy target volume.
- 4. When you use FCTOPPRCPRIMARY, the FlashCopy operation causes a PPRC primary volume to become a FlashCopy target volume. The PPRC-SYNC volume pair currently in full duplex state changes to a duplex pending state when the FlashCopy relationship is established. When PPRC completes the copy operation, the PPRC-SYNC volume pair changes to full duplex state.

For more information about IBM Remote Pair FlashCopy, Metro Mirror, also known as synchronous Peer-to-Peer Remote Copy (PPRC), and other copy services functions, see *z/OS DFSMS Advanced Copy Services*.

#### **FILTERDD**



The FILTERDD keyword specifies the name of the DD statement that identifies the sequential data set, or member of a partitioned data set, that contains the filtering criteria to be used (the INCLUDE, EXCLUDE, and BY keywords). This data set must contain card-image records in DFSMSdss command syntax format.

Note: You must use FILTERDD when you specify more than 255 entries on the INCLUDE, EXCLUDE, or BY keywords.

#### **FORCECP**



The FORCECP keyword specifies that checkpoint data sets on SMS-managed volumes can be processed. Checkpoint indicators are removed from the resulting consolidated data set.

Specifies the number of days (0-255) that must elapse since the last referenced date before the data set can be processed.

#### INCLUDE



The INCLUDE keyword specifies one or more data sets that are eligible to be consolidated. You can use either fully or partially qualified data set names. If you specify INCLUDE(\*\*) or omit INCLUDE, but specify EXCLUDE or BY, all data sets are eligible to be selected for processing.

#### **Restrictions:**

 You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

 DFSMSdss does not support INCLUDE filtering of non-VSAM data sets using an alias.

For more information, see "Filtering by data set names" on page 260.

#### **MAXTIME**




Specifies the maximum time, in minutes, for the CONSOLIDATE operation to complete. MAXTIME is checked after each data set is processed. When the MAXTIME value is reached, the CONSOLIDATE operation ends.

nummins

Specifies the maximum number of minutes (0-9999 in decimal) that a CONSOLIDATE operation can run. A value of 0 is ignored.

**Note:** The elapsed time of the CONSOLIDATE operation might be slightly longer than the MAXTIME value because the value is checked after each data set is processed.

#### **PASSWORD**



The PASSWORD keyword specifies the passwords that DFSMSdss is to use for password-protected data sets. (Password checking is bypassed for RACF-protected data sets.)

This keyword is required only when either of the following is true:

- You do not have the required RACF DASDVOL or RACF data set access
- The installation authorization exit does not bypass the checks.

ddn Specifies the name of the DD statement that identifies the sequential data set, or member of a partitioned data set, that contains data set names and their passwords. This data set must contain card-image records in DFSMSdss command syntax format.

dsn/pswd

dsn is a fully qualified data set name, pswd is the data set password. If no password follows the slash (/), dsn is treated as if it were ddn.

#### Note:

- Specify passwords for all data sets that do not have RACF protection, but do have password protection. During processing, a utility invoked by DFSMSdss might prompt the system operator to supply a password. You can control authorization checking through the installation authorization exit.
- 2. Do not request password prompting for VSAM data sets.
- 3. Catalog passwords are not supported. Instead, it is recommended that you use RACF or another access control facility to secure your catalogs.

#### **CONSOLIDATE Command**


- 4. The SYSPRINT output does not show the data set passwords that are specified in the input command stream.
- 5. When you use a system utility to perform the CONSOLIDATE operation, you must supply the password for each password-protected data set selected, or have the proper RACF data set access authority.

#### **PHYSINDDNAME**



The PHYSINDDNAME keyword specifies the name of the DD statement (ddn) that identifies the input volume to be processed. Specify only one volume per CONSOLIDATE operation.

#### **PHYSINDYNAM**



The PHYSINDYNAM keyword specifies dynamic allocation for the volume to be processed.

volser Specifies the volume serial number of a DASD volume to be processed.

unit Specifies the device type of a DASD volume to be processed. This parameter is optional.

#### Note:

- 1. The volume must be mounted and online.
- 2. Do not specify a non-specific volume serial number, such as an asterisk (\*).
- 3. Specify only one volume for CONSOLIDATE processing.
- 4. Consider using PHYSINDYNAM instead of PHYSINDDNAME to allocate DASD volumes. Doing so does not appreciably increase run-time and might simplify your coding of JCL and command input.


#### **PROCESS**



The PROCESS keyword specifies that DFSMSdss is to allow data sets with a high-level qualifier of SYS1 to be consolidated.

- 1. SYS1.VVDS and SYS1.VTOCIX data sets are not processed.
- 2. To use PROCESS(SYS1), you might require RACF authorization.

#### WAIT



The WAIT keyword specifies the maximum wait time, and the number of attempts permitted, for a CONSOLIDATE operation to obtain control of a data set.

#### numsecs

Specifies a decimal number (0-255) that designates the interval, in seconds, to wait before attempting another pass through the list of selected data sets.

#### numretries

Specifies a decimal number (0-99) that designates the number of attempts permitted to obtain control of a data set.

The default for *numsecs*, *numretries* is (2,2), which specifies two retries at a two-second intervals. To avoid waiting for a resource, specify zero (0) for either *numsecs* or *numretries*.

The WAIT keyword does not control wait or retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is three seconds and the default retry count is 30. This results in a total wait time of 90 seconds.

For information about controlling the wait or retry attempts for system resources, see "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

#### WRITECHECK



The WRITECHECK keyword specifies that the data set being processed is to be verified for successful completion.

#### Note:

- The WRITECHECK keyword is not supported for extended-format sequential data sets.
- 2. This keyword increases the overall elapsed time of the CONSOLIDATE operation.

### **Example of a CONSOLIDATE operation**

This example shows a CONSOLIDATE operation. All eligible data sets on the volume identified by the DASD DD statement are to be filtered using the specified INCLUDE and EXCLUDE criteria. Data sets that satisfy this filtering criteria are processed.

```
//J0B1
                 accounting information, REGION=nnnnK
//STEP1
           EXEC PGM=ADRDSSU
//SYSPRINT DD
                 SYSOUT=A
//DASD
           DD
                 UNIT=3390, VOL=(PRIVATE, SER=111111), DISP=OLD
//SYSIN
           DD
  CONSOLIDATE DATASET(INCLUDE(**) -
     EXCLUDE(USER2.**.LIST,*.LOAD)) -
     PHYSINDDNAME (DASD)
```

#### CONVERTV command for DFSMSdss

The CONVERTV command is used to convert existing volumes to and from SMS management without data movement. The CONVERTV command performs three functions:


- Locks volumes that are ready for conversion to prevent new data set allocations (PREPARE keyword).
- Examines volumes identified by SMS to determine if they can be converted to SMS management (TEST keyword). No conversion is actually performed, but DFSMSdss identif any data sets that cannot be converted to SMS management and why they cannot be converted.
- Performs conversion of volumes into or out of SMS management. Any conditions that prevent conversion are identified.

Guideline: Proper RACF security authorization might be required.


For additional information about RACF security authorization, see the Chapter 5, "Protecting DFSMSdss functions," on page 27.

### CONVERTV command syntax

The syntax of the CONVERTV command is:




#### A: The syntax of optional keywords with CONVERTV SMS is::



### **Explanation of CONVERTV command keywords**

This section describes the keywords for the CONVERTV command.

#### **CATALOG**



CATALOG specifies that if a data set's catalog entry is not found in the standard order of search, the data set is to be cataloged during the conversion.

If the CATALOG keyword has not been specified, and a data set's catalog entry is not found in the standard order of search, the data set is not converted.

#### **INCAT**

Specifies input catalogs that are not in the standard search order. This allows non-VSAM data sets cataloged outside the standard order of search to be processed.

catname

Specifies a fully qualified catalog name.

If CATALOG is specified without INCAT, a single volume, non-VSAM data set cataloged outside the standard order of search might be cataloged in more than one place.

#### **DDNAME**



DDNAME specifies a volume that you want converted. Use this keyword to designate the list of volumes that need conversion. Use this keyword when you do not use the DYNAM keyword.

ddn Specifies the name of the DD statement that identifies a volume to be processed. Up to 255 DDNAMEs can be specified.

#### **CONVERTV Command**

#### **DEBUG**



DEBUG(SMSMSG) instructs DFSMSdss to display ACS WRITE statements to the job output.

#### DYNAM



DYNAM specifies the volume that you want to process must be dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number by using an asterisk (\*). Use this keyword to designate the list of volumes that you need to convert. Use the DYNAM keyword when you do not specify the DDNAME keyword.

Consider using DYNAM instead of DD statements to allocate DASD volumes. This does not noticeably increase run time and presents easier coding of JCL and command input.

volser Specifies the volume serial number of a DASD volume to be processed. Up to 255 volumes can be specified.

unit Specifies the device type of a DASD volume to be processed. This parameter is optional.

#### **FORCECP**



FORCECP specifies that checkpointed data sets resident on the SMS volume can be converted to non-SMS management. Checkpoint indications are removed from the data set during conversion.

days Specifies the number of days that must have elapsed since the last referenced date before the data set can be converted. It is a one-to-three-digit number in the range of zero to 255.

#### INCAT

See "CATALOG" on page 295.

#### **NONSMS**



NONSMS specifies that a volume and all of the data sets on that volume be converted from SMS management to non-SMS management.

#### **PREPARE**



PREPARE specifies that a volume is to be prepared for SMS without conversion of data sets. This prevents the volume from changing prior to performing the full SMS conversion. After the PREPARE is requested, the volume is placed in initial status and you cannot allocate new data sets. However, you can delete existing data sets.

The NONSMS keyword must be specified to return the volume to non-SMS management.


#### **REDETERMINE**



REDETERMINE specifies that the SMS class information is to be reset for data sets previously converted to SMS management whose SMS management class or SMS storage class do not match those returned by the current ACS routines. REDETERMINE allows management class and storage class to be reset, but does not update the data class.

If REDETERMINE is used with the TEST keyword, a report is produced specifying all data sets eligible for conversion, including those already converted.

#### SELECTMULTI



SELECTMULTI specifies how cataloged multivolume data sets are to be selected during conversion to or from SMS management. The volume list is the list of volumes supplied by the DDNAME or DYNAM keyword.


- ALL Specifies that DFSMSdss *not process* a multivolume data set unless all of the volumes that contain a part of the non-VSAM data set or VSAM base cluster are in the volume list specified by DDNAME or DYNAM. ALL is the default for non-SMS processing.
- **ANY** Specifies that DFSMSdss process a multivolume data set when any part of the non-VSAM data set or VSAM base cluster is on a volume in the volume list specified by DDNAME or DYNAM.
- FIRST Specifies that DFSMSdss process a multivolume data set only when the DDNAME or DYNAM volume list includes the volume that contains the first part of the non-VSAM data set or the primary data component of the base cluster for a VSAM sphere. FIRST is the default for SMS processing.

#### **SMS**



SMS specifies that a volume and all of the data sets on that volume are to be converted to SMS management. SMS is the default when the SMS, NONSMS, or PREPARE keyword is not specified.

#### **TEST**



TEST specifies that DFSMSdss is to verify that a volume and its data sets are eligible for conversion or for preparation. The TEST keyword functions just as if TYPRUN=NORUN had been specified on the JCL EXEC PARM field. DFSMS must be active to use this function.

**Note:** It is also possible to use TEST to verify that the ACS algorithms would process correctly because the resulting report indicates the classes associated with the various data sets on the volume.

### **Examples of CONVERTV operations**

The following are examples of the CONVERTV command.

# Example 1: using the CONVERTV command to simulate conversion

```
//JOB1 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//SYSIN DD *

CONVERTV SMS -
    DYNAM((VOL001,3380),(VOL002,3380),(VOL003)) -
    TEST
/*
```

The preceding example uses the TEST keyword to simulate conversion. The TEST keyword produces a report that indicates whether the three volumes (VOL001, VOL002, and VOL003) can be converted to SMS management.

#### Example 2: using the CONVERTV command to convert to SMS

```
//J0B1
           J0B
                 accounting information, REGION=nnnnK
//STEP1
           EXEC PGM=ADRDSSU
//SYSPRINT DD
                 SYSOUT=*
//DVOL1
                 UNIT=SYSDA, VOL=SER=338001, DISP=OLD
           DD
//DVOL2
           DD
                 UNIT=SYSDA, VOL=SER=338002, DISP=OLD
//SYSIN
           DD
 CONVERTY -
     DDNAME(DVOL1, DVOL2) -
     INCAT(SYS1.ICFCAT.V338002) -
     SELECTMULTI(FIRST) -
     CATALOG
```

The non-SMS-managed volume 338002 and the SMS-managed volume (in INITIAL state) 338001 are converted to SMS. The volume 338001 has been placed in the initial state by the storage administrator. Regardless of where the data sets reside, all multivolume data sets whose first extent is on volume 338001 or 338002 are processed. In addition, there are some data sets on volume 338002 cataloged in the user catalog SYS1.ICFCAT.V338002. These data sets are uncataloged from the user catalog and cataloged in the standard order of search. The INCAT keyword provides access to the user catalog.

#### Example 3: using the CONVERTV command to convert from SMS

```
//JOB1 JOB accounting information,nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SYSIN DD *

CONVERTV -
DYNAM(338003) -
NONSMS
/*
```

This example converts a volume to non-SMS-managed.

### **COPY Command for DFSMSdss**

The DFSMSdss COPY command performs data set movement, volume movement, and track movement from one DASD volume to another.

You can copy data sets to another volume of either like or unlike device types. Like devices have the same track capacity (3390 Model 2 and 3390 Model 3), while unlike devices have different track capacities (3380 Model K and 3390 Model 3).

However, the DASD must be of *like* device type if you copy a full volume, range of tracks, or physically copy a data set. The user must specify the source volumes and the target volumes. DFSMSdss only allows one source volume and one target volume.

DFSMSdss offers two ways to process COPY commands as follows:

• Logical processing is data set-oriented, which means that it operates against data sets and volumes independently of physical device format.

#### **COPY Command for DFSMSdss**

 Physical processing can operate against data sets, volumes, and tracks, but is oriented toward moving data at the track-image level. The processing method is determined by the keywords specified on the command.

Integrated catalog facility catalogs should not have a high-level qualifier of SYSCTLG because this causes DFSMSdss to treat them as control volumes.

For more information about using the COPY command, see "Backup with concurrent copy" on page 40 and "Moving data sets with concurrent copy" on page 107.


### Special Considerations for COPY


The following special considerations may apply when you perform a COPY operation:

- · The logical and physical data set COPY function supports hierarchical file system (HFS) data sets and zFS data sets. There is no support for copying individual files within an HFS or zFS.
- The COPY function is not supported for SAM compressed extended-format data sets being copied to a non-SMS-managed target.
- The COPY FULL or COPY TRACK commands might invoke ICKDSF to rebuild the VTOC INDEX data set for a target volume. Therefore, users of these commands require the appropriate authority for ICKDSF.
- When you perform a logical or physical COPY operation of a VSAM compressed data set, the target data set allocation must be consistent with the source data set allocation as follows:
  - If the source is an extended-format VSAM KSDS, then the target must be an extended-format VSAM KSDS.
  - If the source is a compressed VSAM KSDS, then the target must be a compressed VSAM KSDS.
  - If the source is an alternate index for an extended-format KSDS, then the target must be an alternate index for an extended-format KSDS.
  - The target control interval size must be equal to the source.
- If you copy a data set that has an F8/F9 DSCB pair to a volume that does not support F8/F9 DSCBs, the attributes in the F9 DSCB are lost. To retain these extended attributes, the target volumes of the COPY, either SMS or nonSMS, must support F8/F9 DSCBs.


Target data set allocation differs between a physical data set and logical data set copy of non-VSAM data sets. Logical data set copy allocates target data sets according to the amount of used space in the source data set, thereby freeing unused space. Physical data set copy preserves the original size of the source data set. To force unused space to be kept during logical data set copy, the ALLDATA or ALLEXCP keyword must be specified.

### COPY DATASET Command Syntax for Logical Data Set







### A: Additional Keywords Used for Logical Data Sets:




### **B: Optional Keywords Used for Logical Data Sets:**



#### **COPY Command**






### **Notes:**


- Do not use the FASTREPlication (REQuired) keyword with the CONCURRENT(ANYPREF | ANYREQ | VIRTUALPREF | VIRTUALREQ | CACHEPREF | CACHEREQ) keyword.
- 2 Do not use the FASTREPlication (NONE) keyword with the FCNOCOPY or FCTOPPRCPrimary keywords.

# **COPY DATASET Command Syntax for Physical Data Set**








# A: Additional Keywords Used for Physical Data Sets:



# **B: Optional Keywords Used for Physical Data Sets:**








# **Notes:**


- Do not use the FASTREPlication (REQuired) keyword with the 1 CONCURRENT(ANYPREF | ANYREQ | VIRTUALPREF | VIRTUALREQ | CACHEPREF | CACHEREQ) keyword.
- Do not use the FASTREPlication (NONE) keyword with the FCNOCOPY or 2 FCTOPPRCPrimary keywords.


# **COPY FULL and COPY TRACKS Syntax**







# C: Optional Keywords with COPY FULL:









#### Notes:

- 1 Do not use the FASTREPLICATION (NONE) keyword with the FCFULLVOLUMERELATION, FCNOCOPY, FCSETGTOK, or FCTOPPRCPRIMARY keywords.
- 2 For COPY TRACKS operations, the FCCGFREEZE, FCINCREMENTAL, and FCINCREMENTALLAST keywords require that the CPVOLUME keyword be specified, too. For more information, see the keyword descriptions.

# **Explanation of COPY Command Keywords**

This section describes the keywords for the COPY command.

#### **ADMINISTRATOR**



The ADMINISTRATOR keyword allows you to act as a DFSMSdss authorized storage administrator for the COPY command. For administrators, DFSMSdss bypasses access checking for data sets and catalogs.

To use the ADMINISTRATOR keyword, all of the following conditions must be true:

- FACILITY class is active.
- Applicable FACILITY-class profile is defined.
- You have READ access to that profile.

If you are not authorized to use the ADMINISTRATOR keyword, the command ends with an error message.

For more details, see "ADMINISTRATOR keyword" on page 541.

# **ALLDATA**



ALLDATA applies to full, logical and physical data set copy operations.

dsn Specifies the fully qualified name of a data set whose data set organization is physical sequential (PS), physical sequential undefined (PSU), partitioned organization (PO), partitioned organization undefined (POU), or null.

Specify ALLDATA(dsn) or ALLDATA(\*) if the data set is not empty, or ALLEXCP if the data set is empty, for the following conditions (this applies to *like* targets only):

- The data set has data beyond the last-used block pointer in the data set's VTOC entry.
- The data set has a null data set organization.
- The data set is the first or intermediate volume of a multivolume data set and has a null data set organization.

JES2/JES3 data sets can have the characteristics specified above, as can CICS journal data sets.

The data set is processed as follows:

- For a full-volume copy, all of the allocated space for the source data set is copied to the target volume.
- For a physical data set copy, all of the allocated space for the part of a data set that resides on the input volume will be copied to the target volume.
- For a data set copy, the function of ALLDATA is dependent upon certain data set characteristics, device characteristics, and other DFSMSdss keywords specified. See Table 22 on page 370 and Table 23 on page 371 for more information.

# \* (asterisk)

Specifies all data sets whose data set organization is PS, PSU, PO, POU, or null and are not empty (the last used block pointer in the data set's VTOC entry is not zero). The data sets are processed as follows:

- For a full-volume copy, all of the allocated space for the source data set is copied to the target volume.
- For a physical data set copy, the allocated space for the piece of a data set that resides on the input volume will be copied to the target volume.
- For a data set copy, the function of this parameter is dependent upon certain data set characteristics, device characteristics, and other DFSMSdss keywords specified. See Table 22 on page 370 and Table 23 on page 371 for more information.

### Note:

1. When you specify ALLDATA or ALLEXCP for a sequential extended format data set during a logical copy operation DFSMSdss does not retain data beyond

### **COPY Command**

- the last used block pointer. Also, DFSMSdss allocates the same amount of space for the target data set as the source data set.
- 2. When you specify ALLDATA for a PDSE data set during a logical copy operation, DFSMSdss does not retain the data that resides in the allocated but unused space. DFSMSdss allocates the same amount of space for the target data set as the source data set.

DFSMSdss determines the amount of space allocated or used for the data set by counting how many tracks have been allocated or used by the data set. For this reason, the allocated space for the target data set may occupy more tracks than the source when going to a different device type.

**Attention:** Because the unused portion of the data set may or may not be copied, care should be used when specifying the ALLDATA keyword with DELETE. For example, if a data set contains records past the last used block pointer in the data set's VTOC entry that you wish to preserve and you perform a data set copy with ALLDATA and DELETE to an unlike device, these records are not copied to the target, but the source will be deleted upon successful completion of the copy.

# **ALLEXCP**



ALLEXCP specifies all data sets whose data set organization is PS, PSU, PO, POU, or null and are empty (the last used block pointer in the data set's VTOC entry is zero). The data sets are processed as follows:

- For a full-volume copy, all of the allocated space for the source data set are copied to the target volume.
- For a physical data set copy operation, the allocated space for the piece of an empty data set on the input volume will be copied to the target volume. If there is no allocated space, but there is an entry on the VTOC, no tracks will be processed and an entry for the data set will be created in the VTOC of the target volume.
- For a data set copy, the function of this keyword is dependent upon certain data set characteristics, device characteristics, and other DFSMSdss keywords specified. See Table 22 on page 370 and Table 23 on page 371 for more information.

Attention: Because all of the allocated space may or may not be copied, use care in specifying the ALLEXCP keyword with DELETE. For example, if a data set contains records that you wish to preserve, but the last block pointer in the data set's VTOC entry is zero and you perform a data set copy with ALLEXCP and DELETE to an unlike device, these records are not copied to the target, but the source will be deleted upon successful completion of the copy.

### **AUTORELBLOCKADDRESS**



AUTORELBLOCKADDRESS specifies that direct access data sets be automatically processed by relative block address rather than by track-track-record (TTR). The data sets must be accessed with an optional services code (OPTCD) setting. This setting indicates the data sets are organized by relative block address.

#### Note:

- 1. If any such data set is actually organized by TTR, the data set might become unusable.
- 2. The TTRADDRESS keyword takes precedence over the AUTORELBLOCKADDRESS keyword. Refer to the RELBLOCKADDRESS and TTRADDRESS keywords for more information.
- 3. AUTORELBLOCKADDRESS is ignored for direct access data sets with variable-spanned record formats or standard user labels.

For more information about the OPTCD, see *z/OS DFSMS Macro Instructions for Data Sets*.

### BY



BY specifies that the data sets selected up to this point, by the processing of the INCLUDE and EXCLUDE keywords, are to be filtered further. To select the data set, *all* BY criteria must be met. See "Filtering by data set characteristics" on page 262 for a full discussion of *schar*, *op*, *arg*, and for more information about BY filtering.

**Note:** You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

### **BYPASSACS**



BYPASSACS specifies that the automatic class selection (ACS) routines are not invoked to determine the target data set class names. To specify BYPASSACS, RACF authorization may be required.

dsn Specifies a fully or partially qualified data set name.

If a data set is being renamed, the old name must be specified.

For more information about RACF authorization, see Chapter 5, "Protecting DFSMSdss functions," on page 27.

For information about the assignment of class names using the COPY command, see "Assignment of class names by using the RESTORE and COPY commands" on page 494.

For more information about data set names, see "Filtering by data set names" on page 260.

### CANCELERROR



CANCELERROR specifies that the copy task be ended for a permanent read error, or that the copy of a data set is ended for a write error.

- Permanent read error, such as a data check: If CANCELERROR is specified, the copy task is ended. If this keyword is not specified, the track in error is not copied and the copy continues. Only the data set receiving the error is ended, and the DFSMSdss copy function continues to
- Write error, such as an invalid track format:

process any subsequent data sets.

For data set copy, processing of the data set ends and the target data set is deleted. The copy operation continues with the next data set. For full volume and tracks copy, processing for the volume ends. Subsequent tracks are not processed.

DFSMSdss allows you to change this default operation. A patch byte is provided to allow you to change the default handling of invalid tracks created during COPY processing.

During copy operations in which a utility performs the copy, DFSMSdss ignores this keyword. CANCELERROR has no effect on the following types of errors on a DASD volume:

- Equipment check
- Command reject
- Intervention required
- Busout parity

This keyword may be used in conjunction with CHECKVTOC to specify whether or not the operation is to continue in the event of terminating VTOC errors found during VTOC checking. Refer to CHECKVTOC keyword.

For more information about the handling of invalid tracks, see Chapter 10, "Diagnosing problems in DFSMSdss operations," on page 167.

### **CATALOG**



CATALOG specifies that on a data set copy operation, DFSMSdss is to catalog data sets that it allocates. For a logical copy operation, CATALOG instructs DFSMSdss to catalog data sets that it allocates. For a physical copy operation, CATALOG instructs DFSMSdss to catalog the non-VSAM single volume data sets that it allocates. An IDCAMS DEFINE RECATALOG must be used to catalog the VSAM data sets after the physical copy. If the CATALOG keyword is not specified, single volume non-VSAM target data sets will be uncataloged as well.

#### **CATALOG**

catalogs the target data set as determined by the standard catalog search order. This is the default for VSAM, multivolume data sets, and SMS-managed data sets.

#### Note:

- If the CATALOG keyword was specified, but the RENAMEUNCONDITIONAL or UNCATALOG keywords were not specified, an ADR385E message will be issued because two data sets with the same name cannot be cataloged in the standard order of search at the same time.
- 2. The CATALOG keyword is ignored for preallocated target data sets.

### **RECATALOG**(*newcatname*)

catalogs the target data set in the *newcatname* catalog. If you do not specify the *RECATALOG(newcatname)* keyword, single volume non-VSAM target data sets remain uncataloged as well.

# **RECATALOG(\*)**

catalogs the target data set in the same catalog that points to the source data set. If the source data set was not cataloged, the new data set is not cataloged either. After DFSMSdss determines the catalog status of the data set and is changed by other means outside of DFSMSdss, the original catalog status is used. If you do not specify the *RECATALOG(\*)* keyword, single volume non-VSAM target data sets remain uncataloged as well.

#### Note:

- 1. Be careful when using the RECATALOG(*newcatname*) keyword because the target data set may be cataloged outside of the standard order of search.
- 2. The CATALOG or RECATALOG operation fails if the target data set is already cataloged in the same catalog and DELETE, RENAMEU, or UNCATALOG is not specified. The RECATALOG keyword is ignored for SMS-managed targets.
- 3. An alternate index (AIX) is always cataloged in the same catalog as its associated base cluster. If the base cluster is recataloged, the AIX is recataloged.
- 4. If you omit the CATALOG or RECATALOG keyword for a single volume, non-VSAM, non-SMS-managed data set, the target data set is uncataloged.
- 5. The CATALOG and RECATALOG keywords are ignored for preallocated data sets.
- 6. If the RECATALOG(newcatname) or RECATALOG(\*) keyword is specified, but RENAMEUNCONDITIONAL or UNCATALOG is not specified, message ADR385E will be issued if the newcatname catalog is in the standard order of search since two data sets with the same name cannot be cataloged in the standard order of search.

## **CHECKVTOC**



CHECKVTOC specifies that a VTOC analysis of the source volume be performed during copy processing. In the event of terminating VTOC errors found during analysis, operation continues unless the CANcelerror keyword is specified. CHECKVTOC is ignored if CPVOLUME is also specified.

# CICSVRBACKUP



CICSVRBACKUP specifies that DFSMSdss create backups for use by CICSVR for a data set copy operation. DFSMSdss notifies the CICSVR server address space when a CICSVR backup is made for a VSAM base cluster. This enables CICSVR to manage backups that are made by DFSMSdss.

CICSVR provides DFSMSdss with a new name for each VSAM base cluster that is to be copied when CICSVRBACKUP is specified. DFSMSdss uses the CICSVR-generated new name instead of the one that is specified in the RENAMEUNCONDITIONAL keyword.


#### Note:

- 1. CICSVRBACKUP is intended to be used with CICSVR. The minimum required CICSVR release is Version 3 Release 1. To use CICSVRBACKUP, the CICSVR server address space must be active.
- 2. CICSVRBACKUP applies to COPY DATASET for logical data set processing
- 3. CICSVR manages VSAM base clusters that are backed up using the DFSMSdss COPY command. DFSMSdss COPY fails the processing of alternate indexes when you specify the CICSVRBACKUP keyword. Because CICSVR removes reusable alternate indexes (AIX) from the upgrade set prior to recovery and rebuilds the reusable AIXs after recovery, you need not copy the alternate indexes. DFSMSdss ignores the CICSVRBACKUP keyword when copying non-VSAM data sets.
- 4. CICSVRBACKUP cannot be specified with the SPHERE or DELETE keyword.
- 5. You must specify the RENAMEUNCONDITIONAL keyword when you specify the CICSVRBACKUP keyword. The use of RENAMEU must follow the DFSMSdss syntax rules. However, be aware that DFSMSdss uses the CICSVR-generated new name instead of the name that you specify.

Recommendation: To avoid confusion or frustration, you can specify the RENAMEU keyword as RENAMEU((\*\*,CICSVR.\*\*)).

For more information about CICSVR-generated new name, its naming convention, and required RENAMEU specifications, see CICSVR Implementation Guide.

### CONCURRENT



The CONCURRENT keyword specifies that the data is to be processed with concurrent copy except when CONCURRENT(STANDARD | NO) is specified. You can specify one of the following optional sub-keywords to indicate the type of concurrent copy to be used and whether DFSMSdss can use standard I/O when concurrent copy could not be used or has failed.

#### ANYPREFERRED or PREFERRED

Specifies that data is to be processed with concurrent copy. Virtual concurrent copy is attempted first, if the storage subsystem on which the data resides is capable of it and working-space data sets have been defined. Otherwise, cache-based concurrent copy is attempted if the storage subsystem is capable of it. If neither type of concurrent copy is possible or both fail, the data is processed with standard I/O. PREFERRED is the default if you specify the CONCURRENT keyword without a sub-keyword.

## ANYREQUIRED or REQUIRED

Specifies that data is to be processed with concurrent copy. Virtual concurrent copy is attempted first, if the storage subsystem on which the data resides is capable of it and working-space data sets have been defined. Otherwise, cache-based concurrent copy is attempted, if the storage subsystem is capable of it. If neither type of concurrent copy is possible or both fail, the data is not processed.

# **CACHEPREFERRED**

Specifies that data is to be processed with cache-based concurrent copy. If cache-based concurrent copy cannot be used or fails, the data is processed with standard I/O. DFSMSdss does not attempt to use virtual concurrent copy.

# **CACHEREQUIRED**

Specifies that data is to be processed with cache-based concurrent copy. If cache-based concurrent copy cannot be used or fails, the data is not processed. DFSMSdss does not attempt to use virtual concurrent copy or standard I/O.

#### STANDARD or NONE

Specifies that data is to be processed with standard I/O as if the CONCURRENT keyword was not specified.

# **VIRTUALPREFERRED**

Specifies that data is to be processed with virtual concurrent copy. If

virtual concurrent copy cannot be used or fails, the data is processed with standard I/O. DFSMSdss does not attempt to use cache-based concurrent copy.

### **VIRTUALREQUIRED**

Specifies that data is to be processed with virtual concurrent copy. If virtual concurrent copy cannot be used or fails, the data is not processed. DFSMSdss does not attempt to use cache-based concurrent copy or standard I/O.

For a logical data set copy operation, you can also specify the NOTIFYCONCURRENT keyword, as follows:

#### **NOTIFYCONCURRENT**

Specifies that DFSMSdss is to issue an informational message for every data set that is successfully included in the concurrent copy operation. If you do not specify NOTIFYCONCURRENT, DFSMSdss issues messages only for data sets that are not successfully included in the concurrent copy operation.


### Note:

- 1. Do not specify NOTIFYCONCURRENT with CONCURRENT(STANDARD NONE).
- 2. You cannot use the CONCURRENT keyword with the DELETE, UNCATALOG, because after the concurrent copy operation starts, the original data might still be updated.
- 3. You cannot use the concurrent copy option with FASTREPLICATION(REQUIRED) keyword.
- 4. The use of concurrent copy and virtual concurrent copy with the DFSMSdss COPY command is controlled by the RACF FACILITY class profile, STGADMIN.ADR.COPY.CNCURRNT.
- 5. Cache-based and virtual concurrent copy operations are not affected if you specify the FASTREPLICATION(PREFERRED) keyword for the COPY command. If you specify both FASTREPLICATION(PREFERRED) and CONCURRENT keywords, DFSMSdss attempts to use fastreplication first.
- 6. Cache-based and virtual concurrent copy operations are not affected by RACF FACILITY class profile STGADMIN.ADR.COPY.FLASHCPY.

For help with determining concurrent copy storage requirements, see "Concurrent copy storage requirements" on page 56.

For more information about virtual concurrent copy and working space data sets, see "Performance considerations" on page 55 and z/OS DFSMS Advanced Copy Services.

# **CONVERT**



### **CONVERT**(*PDSE*(*dsn*))

Specifies that the PDSs that are listed in the *dsn* be converted to PDSE

### **CONVERT**(PDS(dsn))

Specifies that the PDSEs that are listed in the *dsn* be converted to PDS

#### Note:

1. When a PDSE version 2 is converted to a PDS all PDSE version attributes are lost, including member generations.

# **COPYVOLID**



COPYVOLID specifies that the volume serial number (VOLID) from the input DASD volume is to be copied to the output DASD volume. This applies to full copy operations and to tracks copy operations if track 0 (zero) is copied.

## Note:

- 1. DFSMSdss requires the COPYVOLID keyword for a full-volume copy operation of an SMS-managed input volume—unless you specify the DUMPCONDITIONING keyword.
- 2. When the volume serial number is changed by using a COPYVOLID keyword, profiles are not built for the RACF-protected data sets on the target volume or for the RACF DASDVOL for the RACF-protected DASD volume. When the volume serial number on a DASD volume is changed, the operator is notified. The operating system then initiates a demount of the volume.
- 3. Exercise caution using COPYVOLID in a multiple task job step when two or more of the tasks are using the same output volume. If the output volume is made unavailable by the first task, all succeeding tasks that use the same output volume fail.
- 4. COPYVOLID cannot be performed if there are permanent I/O errors or if CANCELERROR is specified. If TOLERATE(IOERROR) is honored, however, COPYVOLID is performed.
- 5. You cannot use the COPYVOLID keyword with the DUMPCONDITIONING keyword.

# **CPVOLUME**



CPVOLUME specifies that the input and output volumes are VM-format volumes and that the OS-compatible VTOCs must begin on track zero, record five. You must specify the track range to be copied with the TRACKS keyword, as the OS-compatible VTOCs do not describe the extents of any data on the volume. You must also specify the ADMINISTRATOR keyword with CPVOLUME because DFSMSdss cannot check access authorization for VM data.


### **DATASET**



DATASET specifies a data set copy operation using filtering. See Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259 for an explanation of the filtering process used. Unless ALLDATA or ALLEXCP is specified, only *used tracks* are copied for sequential and partitioned data sets and for data sets with a data set organization that is null (for example, JES2/JES3 data sets). If the free space map in the VTOC is invalid, all tracks for the data set are copied.

**Note:** Either the FILTERDD, INCLUDE, EXCLUDE, or BY keyword must be specified when data set is selected.

# **DEBUG**



You can use DEBUG as a diagnostic tool. When you specify the FRMSG subkeyword, DFSMSdss issues messages that explain why you cannot use fast replication or Preserve Mirror operation during COPY processing. The DEBUG(FRMSG) keyword overrides the DEBUG=FRMSG parameter that is specified in the JCL EXEC statement. For Preserve Mirror operations, the DEBUG(FRMSG) keyword might not have an effect if the FlashCopy target is not a PPRC Primary device.

Specify DEBUG(SMSMSG) to instruct DFSMSdss to display ACS WRITE statements to the job output.

Specify DEBUG(FRMSG) with one of the following sub-keywords:

### FRMSG(MINIMAL)

Specifies that DFSMSdss is to issue a message with a minimal level of information. The following are examples of messages that are issued when you use this keyword:

### **Example 1:** Data set copy

```
ADR948I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR DATA SET TEST.SRC.KSDS1 BECAUSE THE TARGET DEVICES DO NOT PROVIDE COMPATIBLE DATA SET FAST REPLICATION FUNCTIONS
```

### **Example 2:** Data set copy

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED
FOR DATA SET TEST.SRC.KSDS1, RETURN CODE 3
```

Return code 3 indicates that one or more source devices are not eligible for fast replication at this time.

### Example 3: Data set copy

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED
FOR DATA SET TEST.SRC.KSDS1, RETURN CODE 15
```

Return code 15 indicates that for the SMS allocation, target volumes that would allow fast replication to be used could not be selected.

### **Example 4:** Full volume or tracks copy

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR VOLUME SRCV01, RETURN CODE 1
```

Return code 1 indicates that the source device is not capable of fast replication.

**Guideline:** DFSMSdss suppresses SMS allocation messages regarding fast replication during a data set copy operation when you specify the DEBUG(FRMSG(MINIMAL)) keyword.

# FRMSG(SUMMARIZED)

Specifies that DFSMSdss is to issue an informational message with summary information. When applicable, summary information regarding ineligible volumes is provided in the message text. The following examples show the messages that are issued when you use this keyword:

### **Example 1:** Data set copy

```
ADR948I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED
FOR DATA SET TEST.SRC.KSDS1 BECAUSE THE TARGET DEVICES DO NOT PROVIDE
COMPATIBLE DATA SET FAST REPLICATION FUNCTIONS
2 VOLUMES SUPPORT DATA SET FLASHCOPY
1 VOLUME SUPPORTS SNAPSHOT
3 VOLUMES DO NOT SUPPORT ANY TYPE OF DATA SET FAST REPLICATION
```

### Example 2: Data set copy

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR DATA SET
TEST.SRC.KSDS1, RETURN CODE 3
     1 VOLUME WAS REJECTED FOR QFRVOLS REASON CODE 7 - VERSION 1 FC RELATION
       EXISTS
     2 VOLUMES WERE REJECTED FOR QFRVOLS REASON CODE 8 - MAX ESS FC
        RELATIONS
      1 VOLUME WAS REJECTED FOR QFRVOLS VOLUME REASON CODE CA - BOUNDARY
       EXCEPTION
```

### **Example 3:** Data set copy, target data set is non-SMS-managed

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR
DATA SET TEST.SRC.KSDS1, RETURN CODE 14
    1 VOLUME WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 7 - VERSION 1 FC
      RELATION EXISTS
    2 VOLUMES WERE REJECTED FOR QFRVOLS VOLUME REASON CODE 8 - MAX ESS
      FC RELATIONS
    2 VOLUMES WERE REJECTED FOR QFRVOLS VOLUME REASON CODE C9 - FLASHCOPY
      NOT SUPPORTED
    1 VOLUME WAS REJECTED FOR DFSMSDSS REASON CODE 1 - INSUFFICIENT SPACE
    1 VOLUME WAS REJECTED FOR DFSMSDSS REASON CODE 2 - NO FREE DSCB
      IN THE VTOC
    2 VOLUMES WERE REJECTED FOR DFSMSDSS REASON CODE 3 - VOLUME IS SMS
      MANAGED
    1 VOLUME WAS REJECTED FOR DFSMSDSS REASON CODE 4 - LSPACE MACRO FAILED
       WHILE CALCULATING FREE SPACE
    1 VOLUME WAS REJECTED FOR DFSMSDSS REASON CODE 8 - DADSM FAILURE
       OCCURRED WHILE ALLOCATING THE DATA SET ON THE VOLUME
```

# Example 4: Data set copy, target data set is SMS-managed Data set copy, target data set is non-SMS-managed

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR
DATA SET TEST.SRC.KSDS1, RETURN CODE 15
IGD17330I DATA SET TEST2.TGT.KSDS1 WAS ALLOCATED ON VOLUME(S) WHICH ARE
          NOT ELIGIBLE FOR FAST REPLICATION. PREFERRED FAST REPLICATION
          WAS SPECIFIED BY CALLER
IGD17290I THERE WERE 3 CANDIDATE STORAGE GROUPS OF WHICH THE FIRST 3
         WERE ELIGIBLE FOR VOLUME SELECTION. THE CANDIDATE STORAGE
         GROUPS WERE: SG1, SG2, SG3
IGD17267I THE FOLLOWING 1 CANDIDATE STORAGE GROUPS WERE INELIGIBLE FOR
          PREFERRED FAST REPLICATION BECAUSE THEY DID NOT HAVE A SUFFICIENT
          NUMBER (2) OF ELIGIBLE FAST REPLICATION VOLUMES: SG3
IGD17268I 2 VOLUMES WERE NOT USED FOR FAST REPLICATION BECAUSE THE SMS VOLUME
         STATUS WAS DISABLED
IGD17268I 2 VOLUMES WERE NOT USED FOR FAST REPLICATION BECAUSE THEY WERE
         NOT ONLINE
IGD17268I 6 VOLUMES WERE NOT USED FOR FAST REPLICATION BECAUSE OF FLASHCOPY
         NOT SUPPORTED - ANTRQST QFRVOLS VOLUME RSN(201)
IGD17268I 2 VOLUMES WERE NOT USED FOR FAST REPLICATION BECAUSE OF BOUNDARY
          EXCEPTION - ANTRQST QFRVOLS VOLUME RSN(202)
IGD17268I 2 VOLUMES WERE NOT USED FOR FAST REPLICATION BECAUSE OF XRC SRC
         CURRENTLY ACTIVE - ANTRQST QFRVOLS VOLUME RSN(5)
IGD17268I 1 FR-ELIGIBLE VOLUMES WERE NOT USED FOR FAST REPLICATION BECAUSE
         STORAGE GROUP HAS INSUFFICIENT FAST REPLICATION VOLUMES
IGD17268I 4 FR-ELIGIBLE VOLUMES WERE NOT USED FOR FAST REPLICATION BECAUSE
         THEY DID NOT HAVE SUFFICIENT SPACE
IGD17269I 2 NON-FR VOLUMES WERE REJECTED BECAUSE THE SMS VOLUME STATUS WAS
         DISABLED
IGD17269I 2 VOLUMES WERE REJECTED BECAUSE THEY WERE NOT ONLINE
IGD17269I 1 VOLUMES WERE REJECTED BECAUSE OF A DADSM FAILURE
IGD17269I 5 VOLUMES WERE REJECTED BECAUSE THEY DID NOT HAVE SUFFICIENT
         SPACE
```

# Example 5: Full volume or tracks copy

```
ADR947I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR VOLUME SRCV01 BECAUSE
THE SOURCE AND TARGET DEVICES DO NOT PROVIDE COMPATIBLE FAST REPLICATION FUNCTIONS
VOLUME SRCV01 SUPPORTS DATA SET FLASHCOPY
VOLUME TGTV01 SUPPORTS SNAPSHOT
```

In examples 4 and 5, DEBUG(FRMSG(SUM)) and DEBUG(FRMAG(DTL)) result in the same level of informational message being issued.

#### Note:

- 1. DFSMSdss supplies fast replication ineligible reasons at the summarized level when summary information is applicable.
- 2. Specifying SUMMARIZED causes DFSMSdss to issue SMS allocation messages regarding fast replication in a data set copy operation when the target data set is SMS-managed.
- 3. When the FASTREPLICATION(REQUIRED) keyword is specified and the DEBUG(FRMSG(MIN | SUM | DTL)) keyword is not specified, DFSMSdss still issues an informational message when a fast replication method cannot be used. It is as though the DEBUG(FRMSG(SUMMARIZED)) keyword had been specified.

#### FRMSG(DETAILED)

Specifies that DFSMSdss is to issue a message with detailed information When applicable, detailed information regarding ineligible volumes is provided in the message text. The following examples show the messages that are issued when you specify this keyword:

# Eample 1: Data set copy

```
ADR948I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR
DATA SET TEST.SRC.KSDS1 BECAUSE THE SOURCE DEVICES DO NOT PROVIDE COMPATIBLE
DATA SET FAST REPLICATION FUNCTIONS
VOLUME SRCV01 SUPPORTS DATA SET FLASHCOPY
VOLUME SRCV02 SUPPORTS DATA SET FLASHCOPY
VOLUME SRCV03 DOES NOT SUPPORT ANY TYPE OF DATA SET FAST REPLICATION
VOLUME SRCV14 SUPPORTS SNAPSHOT
VOLUME SRCV25 DOES NOT SUPPORT ANY TYPE OF DATA SET FAST REPLICATION
VOLUME SRCV26 DOES NOT SUPPORT ANY TYPE OF DATA SET FAST REPLICATION
```

### **Example 2:** Data set copy

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR
DATA SET TEST.SRC.KSDS1, RETURN CODE 3

VOLUME SRCV01 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 7 - VERSION

1 FC RELATION EXISTS

VOLUME SRCV02 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 8 - MAX ESS

FC RELATIONS

VOLUME SRCV03 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 8 - MAX ESS

FC RELATIONS

VOLUME SRCV04 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE CA - BOUNDARY

EXCEPTION
```

Example 3: Data set copy, target data set is non-SMS-managed

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR
DATA SET TEST.SRC.KSDK1, RETURN CODE 14
    VOLUME TGTV01 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 7 - VERSION 1
                   FC RELATION EXISTS
    VOLUME TGTV02 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 8 - MAX ESS
                   FC RELATIONS
     VOLUME TGTV03 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 8 - MAX ESS
                   FC RELATIONS
     VOLUME TGTV04 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE C9 - FLASHCOPY
                   NOT SUPPORTED
     VOLUME TGTV05 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE C9 - FLASHCOPY
                   NOT SUPPORTED
     VOLUME TGTV21 WAS REJECTED FOR DFSMSDSS REASON CODE 1 - INSUFFICIENT
                   SPACE
     VOLUME TGTV22 WAS REJECTED FOR DFSMSDSS REASON CODE 2 - NO FREE DSCB IN THE VTOC
     VOLUME TGTS01 WAS REJECTED FOR DFSMSDSS REASON CODE 3 - VOLUME IS
                   SMS MANAGED
    VOLUME TGTS02 WAS REJECTED FOR DFSMSDSS REASON CODE 3 - VOLUME IS
                   SMS MANAGED
     VOLUME TGTS23 WAS REJECTED FOR DFSMSDSS REASON CODE 4 - LSPACE MACRO
                   FAILED WHILE CALCULATING FREE SPACE
     VOLUME TGTS24 WAS REJECTED FOR DFSMSDSS REASON CODE 8 - DADSM FAILURE
                   OCCURRED WHILE ALLOCATING THE DATA SET ON THE VOLUME
```

# **Example 4:** Full volume or tracks copy

```
ADR947I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR
VOLUME SRCV01 BECAUSE THE SOURCE AND TARGET DEVICES DO NOT PROVIDE
COMPATIBLE FAST REPLICATION FUNCTIONS
    VOLUME SRCV01 SUPPORTS DATA SET FLASHCOPY
    VOLUME TGTV01 SUPPORTS SNAPSHOT
```

#### Note:

- 1. DFSMSdss supplies fast replication ineligible reasons at the individual volume level when detailed information is applicable.
- 2. Specifying DETAILED causes DFSMSdss to issue SMS allocation messages regarding fast replication in a data set copy operation when the target data set is SMS-managed. For an SMS allocation, DFSMSdss supplies the same level of information as if you had specified DEBUG(FRMSG(SUMmarized)).
- 3. For a non-SMS allocation during a data set copy operation, DFSMSdss supplies fast replication ineligible reasons at the individual volume level.

### DELETE



DELETE specifies that for a data set copy DFSMSdss deletes VSAM and non-VSAM data sets from the source volume after a successful copy. This moves, in effect, a data set from one volume to another. The data sets are scratched and uncataloged.

### Note:

1. Specify DELETE when you are copying cataloged data sets. If you do not specify DELETE when you are copying cataloged data sets, the target data set must either be cataloged in a different catalog (using the RECATALOG keyword) or renamed (using the RENAMEU keyword).

- 2. If you copy a data set with DFM attributes to a non-SMS-managed target, the new data set will not have the DFM attributes.
- 3. Unexpired source data sets are deleted only if you also specify PURGE.
- 4. Even if PROCESS (SYS1) is specified, SYS1.VVDS and SYS1.VTOCIX data sets cannot be copied and deleted.
- 5. Do not specify SHARE if you specify DELETE.
- 6. If DFSMSdss encounters a damaged PDS during logical data set copy, it displays messages indicating the nature and relative location of the problem. In order to maintain complete data integrity, DFSMSdss does not delete the source data set. The copy of the data set fails, and the target is deleted. In order to copy and delete a damaged PDS, use the NOPACKING keyword.
- 7. Do not specify DELETE with CONCURRENT, because after the concurrent copy operation has begun, the original data can still be updated.
- 8. Do not specify DELETE with CICSVRBACKUP.
- 9. Specify DELETE to preserve aliases that are associated with non-VSAM data sets. The following criteria must be met for this to work:
  - RENAMEU cannot be specified at the same time.
  - The data set must be SMS-managed and remain SMS-managed during the copy operation.
- 10. For physical data set copy processing, only a single-volume non-VSAM data set may be deleted from a volume that is not a dump conditioned volume. If the DELETE keyword is specified and the input volume specified on the PHYSINDD keyword is a dump conditioned volume, then the DELETE keyword will be ignored while processing all data sets from that volume. If the DELETE keyword is specified and the target data set is single volume and the target volume is SMS managed and the target is not preallocated, the target data set will be cataloged.
- 11. If the data set being processed is a generation data set (GDS), an exclusive enqueue on the GDG BASE is required in addition to the exclusive enqueue on the GDS.

For more information about copying non-VSAM data sets that have aliases, see "Moving data sets with special requirements" on page 114.

# **DUMPCONDITIONING**



DUMPCONDITIONING specifies that you want to create a copy of the source volume for backup purposes rather than for the applications to use the target volume.

When you specify DUMPCONDITIONING, the volume serial number of the target volume does not change, and the target volume remains online after the copy. The VVDS and VTOC index names on the target volume will not change to match the target volume serial number. They will continue to match the source volume serial number. This volume is a "dump conditioned volume."

#### Note:

1. Do not use the DUMPCONDITIONING keyword with the COPYVOLID keyword.

- 2. DUMPCONDITIONING applies to TRACKS COPY operations only if the tracks selected for copying include the VTOC. Otherwise, DFSMSdss ignores DUMPCONDITIONING.
- 3. You may not be able to access data on the target volume after a DUMPCONDITIONING COPY operation. This is because the VVDS and VTOC index names do not match the target volser. Use the resulting target volume for either of the following operations: as the source volume for a FULL volume DUMP operation or the source of another FULL volume DUMPCONDITIONING COPY operation.
- 4. You must specify the DUMPCONDITIONING keyword to perform a FULL volume COPY operation of a dump conditioned volume.
- 5. If a conditioned volume is copied back using DUMPCONDITIONING, conditioning is not performed on the original source volume. Instead, DFSMSdss recognizes that it is copying from the target of a previous conditioned-backup and recovers the original source volume.

# **DYNALLOC**



DYNALLOC specifies dynamic allocation, instead of enqueue, to serialize the use of data sets. The data sets whose extents are to be relocated are serialized throughout the copy operation. This allows cross-system serialization in a JES3/MVS environment.

#### Note:

- 1. Serialization is of value only when you use the dynamic allocation or the JES3 interface is not disabled.
- 2. Run time increases when you use the DYNALLOC keyword to serialize data sets (as opposed to enqueue) because overhead is involved in dynamic allocation and serialization across multiple processors.
- 3. If a data set passes INCLUDE/EXCLUDE filtering and is migrated before BY filtering and the DYNALLOC keyword is used, the dynamic allocation causes the data set to be recalled. DFSMSdss waits for the recall processing to complete. If the data set is recalled to a different volume, a message indicates that the VTOC entry was not found.
- 4. For an HFS source data set, DFSMSdss ignores DYNALLOC and attempts to get a SYSZDSN enqueue. If the enqueue attempt fails, DFSMSdss attempts to quiesce the HFS data set.
- 5. For a physical data set copy operation, the DYNALLOC keyword will be ignored for the source data set when that data set resides on a dump conditioned volume.

# **EXCLUDE**




dsn Specifies the name of a data set to be excluded from the data sets selected by the INCLUDE keyword. Either a fully or a partially qualified data set

name can be used. See the separate discussions of INCLUDE and BY for information about how these keywords are specified.

**Note:** You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

## **FASTREPLICATION**



FASTREPLICATION specifies whether the use of fast replication is preferred, required, or not desired. This keyword applies to fast replication methods such as FlashCopy and SnapShot. It does not affect concurrent copy or virtual concurrent copy processing.

PREFERRED specifies that you want to use a fast replication method, if possible. If fast replication cannot be used, DFSMSdss completes the operation using traditional data movement methods. PREFERRED is the default (unless changed to NONE by the installation).

REQUIRED specifies that fast replication must be used. For full volume or tracks COPY operations, DFSMSdss fails the operation if fast replication cannot be used. For a data set COPY operation, DFSMSdss stops processing the current data set if fast replication cannot be used. However, DFSMSdss continues processing the rest of the data sets using fast replication. When the DEBUG(FRMSG(MIN | SUM | DTL)) keyword is not specified, DFSMSdss still issues summarized information regarding why a fast replication method cannot be used as though DEBUG(FRMSG(SUMMARIZED)) had been specified. The DEBUG(FRMSG(MIN | SUM | DTL)) keyword determines the amount of information provided for why you cannot use a fast replication method.

NONE specifies that fast replication should not be used. DFSMSdss does not attempt to use fast replication and completes the operation using traditional data movement methods.

#### Note:

- 1. Do not use the FASTREPlication (REQuired) keyword with the CONCURRENT(ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ) keyword.
- 2. Do not use the FASTREPlication (NONE) keyword with the FCNOCOPY keyword.
- 3. Use VOLCOUNT(ANY) together with FASTREPlication (REQuired) or FASTREPlication (PREFerred) when copying VSAM data sets and the following conditions are all true:
  - The data set is single volume
  - The smallest allocation quantity is less than 1 cylinder
  - The primary allocation is less than the secondary allocation.

# **FCCGFREEZE**



FCCGFREEZE specifies that the source volume is to be part of a FlashCopy Consistency Group. Subsequent I/O activity to the FlashCopy source volume will be held until the CGCREATED (thaw) command is processed on the logical subsystem (LSS) where the volume resides or when the FlashCopy Consistency Group timer expires.

#### Note:

- 1. Do not specify FCCGFREEZE with any of the following keywords:
  - CONCURRENT(ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ)
  - DATASET
  - FASTREPLICATION(PREFERRED | NONE)
  - FCNOCOPYTOCOPY
- 2. DFSMSdss supports FlashCopy Consistency Group at a volume level. When you specify FCCGFREEZE with TRACKS, you must also specify the CPVOLUME keyword. FCCGFREEZE is supported with the TRACKS keyword only for full volume copy of VM-format volumes with OS-compatible VTOCs.
- 3. When FCCGFREEZE is specified, it indicates FlashCopy Version 2 must be used to copy the data. If FlashCopy V2 cannot be used, the copy operation will
- 4. The FCCGCREEZE option requires the specified devices support the FlashCopy Consistency Group function.
- 5. Because I/O activity is held on source volumes that are frozen, it is recommended not to include system volumes that are required to run the current COPY command (or subsequent COPY commands) needed to form a FlashCopy Consistency Group. Examples of such system volumes include spool, page, and volumes containing checkpoint data sets, catalogs, and RACF databases.

# **FCFASTREVERSERESTORE**



FCFASTREVERSERESTORE specifies that the use of fast reverse restore is required. Fast reverse restore gives the option to restore a FlashCopy source from its FlashCopy target without having to wait for completion of the background copy operation.

A FlashCopy relationship must exist between the source and the target and must be a single FlashCopy relationship that covers the entire volume (from track 0 through the last track on the volume). The relationship can be an incremental FlashCopy relationship.

The existence of a FlashCopy relationship will be verified. If a relationship does not exist between the source and the target, the fast reverse restore request will fail. Verification can be bypassed using ADRUFO, however, it will be difficult to determine the cause of a request failure.

The contents of the source volume, which is the original target of a FlashCopy operation, are unpredictable after the fast reverse restore operation is complete and should not be used.

#### Note:

- 1. Do not specify FCFASTREVERSERESTORE with any of the following keywords:
  - FCTOPPRCPRIMARY (PRESMIRPREF | PRESMIRREQ)
  - FASTREPLICATION (PREFERRED | NONE)
  - CONCURRENT, FCFREEZE, FCINCREMENTAL, FCINCREMENTALLAST, FCINCRVERIFY, FCNOCOPYTOCOPY, FCWAIT
- 2. The source and target device capacity must be the same.
- 3. If the target volume specified is the source volume of other FlashCopy relationships, then those copies must be withdrawn prior to using FCFASTREVERSERESTORE. Otherwise the request will fail.
- 4. ADRUFO can be configured to retry a failed FlashCopy recovery without the use of fast reverse restore. If the subsequent attempt is successful, a new FlashCopy relationship between the specified source and target volumes will be created.

### **FCFULLVOLUMERELATION**



FCFULLVOLUMERELATION specifies that a single FlashCopy relationship will be created that covers the entire volume (from track 0 through the last track on the volume). This means the entire volume will be copied, including free space. If FCFULLVOLUMERELATION is not specified, free space is not copied.

#### Note:

- 1. Do not specify FCFULLVOLUMERELATION with any of the following keywords:
  - FASTREPLICATION (NONE)
- 2. If FlashCopy cannot be used to move the data, the FCFULLVOLUMERELATION keyword will be ignored.
- 3. If the FCFASTREVERSERESTORE keyword is specified, the FCFULLVOLUMERELATION keyword does not need to be specified.

FCINCREMENTAL specifies that DFSMSdss establishes a full volume Incremental FlashCopy relationship from the specified source volume (in the INDD/INDYNAM keyword) to the specified target volume (in the OUTDD/OUTDYNAM keyword). The full volume FlashCopy relationship remains in effect after the initial copy has completed and subsequent changes to the source and target volumes are tracked so that a future FlashCopy operation is performed to only copy incremental changes.

When FCINCREMENTAL is specified and no Incremental FlashCopy relationship currently exists between the volume pair, the storage subsystem initiates background copy of the entire source volume to the target volume.

When FCINCREMENTAL is specified and an Incremental FlashCopy relationship already exists between the volume pair, the storage subsystem only copies the changed data in the specified direction which can be the same as the existing (original) or the reverse of the existing FlashCopy direction. When no updates have been made to the existing target since the last Incremental FlashCopy, the reverse of FlashCopy direction can be used to restore the original source volume back to the previous point-in-time copy state. The new source volume is designated by the INDD/INDYNAM keyword and the new target is designated by the OUTDD/OUTDYNAM keyword on the copy command.

**Attention:** DFSMSdss does not inhibit writes to the FlashCopy source or target volumes. If you plan to use the Incremental FlashCopy target volume as a backup, you must ensure that the target volume is not updated inadvertently.

### Note:

- 1. Do not specify the FCINCREMENTAL keyword with any of the following keywords:
  - DATASET
  - FCINCRMENTALLAST
  - CONCURRENT(ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ)
  - FASTREPLICATION(PREFERRED | NONE)
  - FCNOCOPY
  - FCNOCOPYTOCOPY
- 2. Incremental FlashCopy is supported at a volume level. It is not supported for data set FlashCopy.
- 3. Incremental FlashCopy Version 2 supports up to the maximum number of full volume flashcopies allowed for a source, which is 12. The initial Incremental FlashCopy support, known as Incremental FlashCopy Version 1, allows only 1 full volume FlashCopy to be incremental. A Version 1 Incremental FlashCopy relationship can coexist with Version 2 Incremental FlashCopy relationships.

- 4. When you specify FCINCREMENTAL with TRACKS, you must also specify the CPVOLUME keyword. FCINCREMENTAL is supported with the TRACKS keyword only for full volume copy of VM-format volumes with OS-compatible VTOCs.
- 5. The benefit of Incremental FlashCopy is to minimize the amount of data transfer needed when a FlashCopy pair is refreshed. There is no saving in data transfer when the no-background copy option is chosen. Therefore, DFSMSdss does not allow FCINCREMENTAL and FCNOCOPY to be specified together.
- 6. When you specify DUMPCONDITIONING with FCINCREMENTAL, the volume serial number of the target volume does not change, and the target volume remains online after the copy. A subsequent incremental copy can be made without additional procedure.
- 7. When you specify COPYVOLID with FCINCREMENTAL, the volume serial number of the target volume is changed to match the source's and the target volume is varied offline. Prior to performing a subsequent incremental copy using DFSMSdss, the offline volume's volume serial number must be changed by using a utility such as ICKDSF and the volume must be varied online. Although you can specify FCINCREMENTAL with COPYVOLID, IBM recommends you use FCINCREMENTAL with DUMPCONDITIONING.
- 8. The PURGE keyword may be required on subsequent incremental copies.
- 9. When FCINCREMENTAL is specified, it requires that the storage facility has the Change Recording feature enabled. The Incremental FlashCopy request fails if the storage facility does not support Change Recording.
- 10. The Incremental FlashCopy direction can only be reversed when the previous physical background copy has completed. If the background copy is still in progress, the new Incremental FlashCopy attempt fails. You can instruct DFSMSdss to wait for background copy to complete by specifying the FCWAIT keyword. See the FCWAIT keyword description for more information.
- 11. FCINCREMENTAL specifies that the full volume FlashCopy relationship remains in effect (persists) after the background copy has completed and subsequent changes to the source and target volumes are tracked. You can specify the INCREMENTALLAST keyword instead of FCINCREMENTAL If you want DFSMSdss to initiate FlashCopy of the final increment, stop tracking the changes, and have the relationship ended when background copy has completed.

# **FCINCREMENTALLAST**

See "FCINCREMENTAL" in "FCINCREMENTAL" on page 330 for syntax diagram.

FCINCREMENTALLAST specifies that DFSMSdss establishes FlashCopy of the final increment from the specified source volume (in the INDD/INDYNAM keyword) to the specified target volume (in the OUTDD/OUTDYNAM keyword), stops change recording, and have the FlashCopy relationship ended when the background copy has completed.

When FCINCREMENTALLAST is specified and no Incremental FlashCopy relationship currently exists between the volume pair, DFSMSdss will establish a non-incremental FlashCopy of the entire source volume to the target volume. The FlashCopy relationship will end when the background copy has completed.

When FCINCREMENTALLAST is specified and an Incremental FlashCopy relationship already exists between the volume pair, the storage subsystem will

only copy the changed data in the specified direction which can be the same as the existing (original) or the reverse of the existing FlashCopy direction. When no updates were made to the existing target since the previous Incremental FlashCopy, the reverse of FlashCopy direction can be used to restore the original source back to the previous point-in-time copy state. The new source volume is designated by the INDD/INDYNAM keyword and the new target is designated by the OUTDD/OUTDYNAM keyword on the copy command.

See the INCREMENTAL keyword description for more information about Incremental FlashCopy.

#### Note:

- 1. Do not specify the FCINCREMENTALLAST keyword with any of the following keywords:
  - DATASET
  - FCINCRMENTAL
  - CONCURRENT (ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ)
  - FASTREPLICATION(PREFERRED | NONE)
  - FCNOCOPY
  - FCNOCOPYTOCOPY
- 2. When you specify FCINCREMENTALLAST with TRACKS, you must also specify the CPVOLUME keyword. FCINCREMENTALLAST is supported with the TRACKS keyword only for full volume copy of VM-format volumes with OS-compatible VTOCs.
- 3. When FCINCREMENTALLAST is specified, it requires that the storage facility has the Change Recording feature enabled. The Incremental FlashCopy request will fail if the storage facility does not support Change Recording.
- 4. The Incremental FlashCopy direction can only be reversed when the previous physical background copy has completed. If the background copy is still in progress, the new Incremental FlashCopy attempt will fail. You can instruct DFSMSdss to wait for background copy to complete by specifying the FCWAIT keyword. See the FCWAIT keyword description for more information.
- 5. If you want the full volume Incremental FlashCopy relationship to remain in effect (persists) after the copy has completed and subsequent changes to the source and target volumes to be tracked, specify the FCINCREMENTAL keyword.

### **FCINCRVERIFY**

See "FCINCREMENTAL" on page 330 for Syntax diagram.

### **NOREVERSE**

Specifies that the new FlashCopy direction is the same as the existing (original) FlashCopy direction.

#### REVERSE

Specifies that the new FlashCopy direction is the reverse of the existing (original) FlashCopy direction.

FCINCRVERIFY specifies that DFSMSdss should verify the new and the existing Incremental FlashCopy direction before copying incremental changes. The new source volume is designated by the INDD/INDYNAM keyword and the new target is designated by the OUTDD/OUTDYNAM keyword on the copy command. If the new and the existing FlashCopy directions match what the user expected -the same or reversed -- DFSMSdss will proceed to copy the incremental changes in

the specified (new) direction. If the new and the existing FlashCopy directions do not match what the user expected, DFSMSdss will fail the copy task without copying the new increment.

When FCINCRVERIFY is specified and no Incremental FlashCopy relationship currently exists, DFSMSdss will fail the copy task without establishing a new FlashCopy relationship.

When FCINCRVERIFY is specified and an Incremental FlashCopy relationship exists between the specified volume pair, DFSMSdss will verify the FlashCopy directions before proceeding.

**Note:** When FCINCRVERIFY is specified, either the FCINCREMENTAL or the FCINCREMENTALLAST keyword must also be specified.

# **FCNOCOPY**



FCNOCOPY specifies that if FlashCopy is used to perform the copy operation, then the ESS subsystem does not perform a physical copy of the data. If FCNOCOPY is not specified and FlashCopy is used to perform the operation, then the ESS subsystem performs a physical copy of the data in order to release the subsystem resources that are used to maintain the FlashCopy relationship (a virtual copy of the data).

When FlashCopy is not used to perform the copy operation, the FCNOCOPY keyword is ignored.

#### Note:

- 1. Do not specify the FCNOCOPY keyword with the FASTREPLICATION(NONE) keyword.
- 2. If FCNOCOPY is not specified and the ESS subsystem performs the physical copy, the DFSMSdss copy operation will not be delayed. However, performing the physical copy uses subsystem resources, which can impact the performance of other I/O operations that are issued to the ESS.
- 3. Be aware that if you use the FCNOCOPY keyword, you must withdraw the FlashCopy relationship in which the copy is no longer needed in order to free up the subsystem resources that maintain the FlashCopy relationship. You can withdraw the FlashCopy relationship by performing one of the following options:
  - Initiate a dump of the target of the copy and specify the FCWITHDRAW keyword on the DUMP command.
  - Initiate the TSO FCWITHDR command.

# **FCNOCOPYTOCOPY**



FCNOCOPYTOCOPY specifies that DFSMSdss initiate background copy between the specified source and any target with existing FlashCopy no-background copy (NOCOPY) relationships associated with that source. As a result, the remaining unchanged source tracks will be written to the target. When the physical background copy completes, the FlashCopy relationship will end unless the relationship is persistent.

If there are not any existing FlashCopy no-background copy relationships associated with the specified source, no operations will be performed as a result of this COPY command. No messages will be issued if there are not any existing relationships to be converted.

#### Note:

- 1. Do not specify the FCNOCOPYTOCOPY keyword with any of the following keywords:
  - DELETE
  - FASTREPLICATION(REQUIRED | PREFERRED | NONE)
  - FCCGFREEZE
  - FCINCREMENTAL | FCINCREMENTALLAST
  - FCNOCOPY
- 2. FCNOCOPYTOCOPY operation does not create a new copy of the source data.
- 3. FCNOCOPYTOCOPY operation initiates background copy of any NOCOPY FlashCopy relationships in which the specified source is participating. If output data sets, tracks (OUTTRACKS), or volumes (OUTDDNAME/OUTDYNAM) are specified, they are ignored.
- 4. The source extent ranges specified or determined by DFSMSdss in the FCNOCOPYTOCOPY conversion request might not match the existing FlashCopy relationships. Any existing no-background copy FlashCopy relationships with extent ranges intersecting the source tracks specified in the conversion request will have the entire relationship converted. For example, if FlashCopy no-background copy relationships were established for 2 extents: tracks 1 through 50 and tracks 70 through 100, a subsequent COPY FCNOCOPYTOCOPY issued for an extent range of tracks 30 through 90 would result in background copy being initiated for tracks 1 through 50 and 70 through 100. Tracks 51 through 69 would be ignored.
- 5. The existing FlashCopy relationships may have been established with the no-background copy option by a previous DFSMSdss copy job with the FCNOCOPY option, TSO FCESTABL command with MODE(NOCOPY), or other programs. The FCNOCOPYTOCOPY option will convert any existing FlashCopy no-background copy relationships regardless of which program established the NOCOPY relationships.

### **FCSETGTOK**



FCSETGTOK specifies that when FlashCopy is used to perform a full volume copy operation, the target volume can be a space efficient volume. This type of FlashCopy relationship is called a *space efficient FlashCopy*. You can use space efficient FlashCopy for a full-volume copy operation only; that is, a COPY FULL operation or a COPY TRACKS command that specifies a full volume.

Observe the following considerations:

- If you specify FCSETGTOK with COPY FULL, and the target is a space efficient
  volume, DFSMSdss attempts to establish a full-volume FlashCopy relationship
  without excluding free space, which results in one FlashCopy relationship for
  the entire volume. If FlashCopy cannot be used, DFSMSdss issues an error
  message and the copy operation fails. DFSMSdss does not attempt to use
  another method of data movement.
- To use FCSETGTOK with COPY TRACKS, your command must specify one track range (an extent) that includes the entire volume (tracks 0 through *n*). Otherwise, the FCSETGTOK keyword has no effect on the copy operation.

When you specify the FCSETGTOK keyword, you must also specify the following sub-keyword to indicate what action DFSMSdss is to take if space on the repository volume is exhausted during the FlashCopy relationship:

#### **FAILRELATION**

This sub-keyword, abbreviated as FAIL, specifies that if space on the repository volume is exhausted during the FlashCopy relationship, DFSMSdss is to place the relationship in a failed state and mark the target copy as not valid. During the failed state, DFSMSdss continues to allow read and write operations to the source volume, but does not copy the updated tracks to the target volume. DFSMSdss fails any read or write requests for the target volume.

To clear this condition for the target volume, you must initialize the target volume through the ICKDSF INIT command. Doing so causes the FlashCopy relationship to be withdrawn and the space on the space efficient volume to be released.

Using FCSETGTOK might require RACF authorization. If your installation has defined the RACF FACILITY class profile, STGADMIN.ADR.COPY.FCSETGT, your user ID requires READ access to the profile. For more information, see "Protecting the usage of DFSMSdss" on page 533.

DFSMSdss ignores the FCSETGTOK keyword for COPY operations in which:

- FlashCopy is not used to perform the copy operation
- The target volume is not a space efficient volume
- Less than a full volume is to be copied, for example, a COPY DATASET operation.

**Example:** In the following example, a full volume copy and dump is requested. Based on the FCSETGTOK setting, if space on the repository volume is exhausted during the FlashCopy relationship, DFSMSdss continues to allow read and write operations to the source volume, **VOL00A**, but does not copy the updated tracks to the target volume **VOL00B**:

```
COPY FULL INDYNAM(VOL00A) OUTDYNAM(VOL00B) DUMPCONDITIONING - ADMIN PURGE FCNOCOPY FCSETGTOK(FAIL)
```

DUMP FULL INDYNAM(VOLOOB) OUTDD(TAPEO1) FCWITHDRAW

#### Note:

1. Space efficient FlashCopy is intended for full volume copies that are short term in nature, such as those that are to be backed up to tape. Space efficient FlashCopy might also be appropriate for longer term copies, if the source and target volumes are not frequently updated.


- 2. For a FlashCopy request, you must also specify the FCNOCOPY keyword when the intended target is a space efficient volume. Otherwise, your request will fail.
- 3. Do not specify FCSETGTOK with the FASTREPLICATION(NONE) keyword.

For more information about space efficient FlashCopy, see z/OS DFSMS Advanced Copy Services.

For information about RACF protection for DFSMSdss functions and keywords, see Chapter 5, "Protecting DFSMSdss functions," on page 27.

For more information about RACF FACILITY class profiles, see "Protecting DFSMSdss functions with RACF FACILITY class profiles" on page 29.

# **FCTOPPRCPrimary**



FCTOPPRCPrimary specifies that if FlashCopy is used to perform the copy operation, a Peer-toPeer Remote Copy (PPRC) primary volume is allowed to become a FlashCopy target volume. Use the following sub-keywords to specify whether the device pair is allowed to go to duplex pending state if the target volume of the FlashCopy operation is a metro mirror primary device:

### **PRESMIRREQ**

specifies that if the target volume is a Metro Mirror primary device, the pair must not go into a duplex pending state as the result of a FlashCopy operations.

#### **PRESMIRPREF**

specifies that if the target volume is a Metro Mirror primary device, it would be preferable that the pair does not go into a duplex pending state as the result of a FlashCopy operation. However, if a Preserve Mirror operation cannot be accomplished, the FlashCopy operation is still to be performed.

### **PRESMIRNONE**

specifies that Preserve Mirror operation is not to be done, even if all of the configuration requirements for a Preserve Mirror operation are met. If the target specified is a Metro Mirror primary device, the pair is to go into a duplex pending state while the secondary device is updated with the tracks to be copied. PRESMIRNONE is the default if you specify FCTOPPRCPrimary without a subkeyword.

Attention: When you specify FCTOPPRCPrimary or FCTOPPRCPrimary(PRESMIRNONE), the FlashCopy operation causes a PPRC primary volume to become a FlashCopy target volume. A Metro Mirror or Global Copy pair currently in full duplex state, goes into a duplex pending state when the FlashCopy relationship is established. When Metro Mirror or Global Copy

completes the copy operation, the Metro Mirror or Global Copy pair goes to full duplex state. To prevent Metro Mirror or Global Copy pairs from going to duplex pending state during FlashCopy operation, you must specify FCTOPPRCPrimary(PRESMIRREQ).

#### Note:


- 1. Using FCTOPPRCPRIMARY might require RACF authorization.
- 2. Do not specify the FCTOPPRCPrimary keyword with the PRESMIRPREF and PRESMIRREQ subkeywords, if you specify the FCSETGTOK keyword with FAILRELATION.
- **3**. Do not specify the FCTOPPRCPrimary keyword with the FASTREPLICATION(NONE) keyword.
- 4. When FlashCopy is not used to perform the copy operation, the FCTOPPRCPrimary keyword is ignored.
- 5. When FCTOPPRCPrimary is not specified or if the capability is not supported by the ESS, a PPRC primary volume is not eligible to become a FlashCopy target volume.

For more information about RACF authorization, see *z/OS DFSMSdss Storage Administration*.

For more information about RACF FACILITY class profiles, see *z/OS Security Server RACF Security Administrator's Guide*.

For more information about PPRC, Metro Mirror, Global Copy, and Global Mirror, see *z/OS DFSMS Advanced Copy Services*.

### **FCWAIT**



### numsecs

Specifies a decimal number (0-255) that designates the time, in seconds, to wait before checking for physical background copy completion.

#### numretries

Specifies a decimal number (0-99) that designates the maximum number of additional queries to make on physical background copy completion.

FCWAIT specifies to DFSMSdss the length of the wait in seconds, and the number of additional queries on FlashCopy background copy completion. The combination of retry interval and maximum number of retries (numsecs times numretries) designated in the FCWAIT keyword specifies the maximum length of time for DFSMSdss to wait for an existing physical background copy to complete before either initiating FlashCopy Establish or failing the COPY FULL or COPY TRACKS operation.

When FCWAIT(numsecs,numretries) is specified, DFSMSdss will check for existing background copy completion before initiating a FlashCopy attempt. If no background copy is currently in progress from the COPY source to the target, DFSMSdss will establish FlashCopy immediately. If background copy is in progress, DFSMSdss will recheck at the specified interval until the designated


number of retries has been reached. If background copy remains in progress when the maximum wait time has been reached, DFSMSdss will fail the COPY FULL or COPY TRACKS operation.

The default for numsecs, numretries is (0,0). In other words, when FCWAIT is not specified, or when either numsecs or numretries is 0, DFSMSdss will attempt to establish FlashCopy without waiting for active background copy to end.

### Note:

- 1. The FCWAIT keyword is ignored when neither the FCINCREMENTAL nor the FCINCREMENTALLAST keyword is also specified.
- 2. The FCWAIT keyword is ignored when Incremental FlashCopy direction is not being reversed.
- 3. The FCWAIT keyword is ignored if FlashCopy cannot be attempted.

### **FILTERDD**



ddn Specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set that contains the filtering criteria to use. This is in the form of card-image records, in DFSMSdss command syntax, that contain the INCLUDE, EXCLUDE, and BY keywords that complete the RELEASE command syntax.

Note: You must use FILTERDD when you have more than 255 entries in the INCLUDE, EXCLUDE, or BY list of subkeywords.

# **FORCE**



FORCE specifies that DFSMSdss copy one or more unmovable data sets to a like or unlike device type. Unmovable data sets are those allocated as absolute track (ABSTR) or as unmovable (PSU, POU, DAU, or ISU). The allocation attribute, unmovable or ABSTR, is carried over to the output volume.

When copying to like devices, DFSMSdss copies the data sets to the same track locations on the target volume. In this case, FORCE is not required if the target volume uses an indexed VTOC, and the space where the unmovable data set is to reside is available. If any of these conditions is not true, DFSMSdss does not copy any unmovable data sets unless FORCE is specified. In this case, DFSMSdss places the unmovable data sets in any available location.

You must specify FORCE when copying unmovable data sets to unlike devices. DFSMSdss places the unmovable data sets in any available location.

Restriction: Use the EXCLUDE keyword (with the FORCE keyword) to designate data sets that have CCHHR (cylinder, cylinder, head, head, record) location-dependent data. This prevents DFSMSdss from moving the location-dependent data sets.

## **FORCECP**



FORCECP specifies that checkpoint data sets resident on the SMS volume or volumes can be copied. Checkpoint indicators are removed from the target data set.

days Specifies a decimal number in the range of zero to 255, and specifies the number of days that must have elapsed since the last referenced date before the data set can be copied.

#### **FREESPACE**



FREESPACE specifies free space values for DFSMSdss-allocated target VSAM data sets. If this keyword is omitted, the control interval and control area free space are the same as the source data set.

- CI Specifies the percentage of free space to be kept in each control interval during allocation of the data set.
- CA Specifies the percentage of free space to be kept in each control area during allocation of the data set. When omitted, the control area free space is the same as the source data set.

#### **FULL**



FULL specifies that an entire DASD volume is to be copied. This is the default. Unallocated tracks are not copied. Unless specified by ALLDATA or ALLEXCP, only the used (rather than allocated) tracks are copied for sequential data sets, partitioned data sets, and for data sets with unknown data set organization (for example, JES2/JES3 data sets with a data set organization that is null). If the VTOC has errors, all tracks are copied. Used tracks consist of the tracks from the beginning of the data set to the last-used track (as indicated by the last used block pointer in the data set's VTOC entry).

**Note:** You cannot specify the SHARE or TOL(ENQF) keywords for FULL operations.

### **INCAT**



INCAT(catname) specifies that DFSMSdss search the user catalogs specified by the INCAT(catname) keyword, then follow the standard search order to locate data sets. INCAT(catname) allows you to identify specific source catalogs. You might need RACF authorization to use the INCAT keyword.

catname

Specifies a fully qualified catalog name.

#### **ONLYINCAT**

Specifies that DFSMSdss only searches catalogs that are specified in the INCAT catalog name list.

DFSMSdss does not process an SMS-managed data set that is cataloged outside the standard order of search, even if it is cataloged in one of the catalogs that is specified with the INCAT keyword. Ensure that the SMS-managed data sets are cataloged under standard catalog search order.

## INCLUDE



dsn Specifies the name of a data set eligible to be copied. Either a fully or a partially qualified data set name can be used. See "Filtering by data set names" on page 260. If INCLUDE is omitted (but EXCLUDE or BY is specified) or INCLUDE(\*\*) is specified, all data sets are eligible to be selected for copying.

You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

DFSMSdss does not support INCLUDE filtering of non-VSAM data sets using an alias.

### INDDNAME



ddn Specifies the name of the DD statement that identifies a volume processed during FULL or TRACKS copy. For a data set copy operation, you can specify multiple names (that is, multiple volumes), separated by commas. For single-volume data sets, each of the DD statements corresponding to a DDNAME (ddn) must identify only one volume serial number.

Note: If no input volumes are specified for a data set copy operation, DFSMSdss selects from all data sets cataloged in the catalogs accessible through the standard search order. If either INDDNAME or INDYNAM is specified, DFSMSdss still uses the standard catalog search order, but it selects data sets only from the specified volumes. For multivolume data sets, use LOGINDDNAME or LOGINDYNAM with SELECTMULTI.


When DFSMSdss invokes IEHMOVE to copy multivolume non-VSAM data sets, IEHMOVE requires that the first DD statement in the job stream must identify all input volumes. DFSMSdss requires separate DD statements for the input volumes. To accommodate both requirements, you must code your JCL as follows:

```
//INDD1 DD UNIT=(SYSDA,2),VOL=SER=(VOL1,VOL2),DISP=SHR
//INDD2 DD UNIT=SYSDA,VOL=SER=VOL2,DISP=SHR
```

and code your DFSMSdss control statement:

```
COPY LOGINDD(INDD1, INDD2) ...
```

#### **INDYNAM**




The INDYNAM keyword specifies the input volumes that are to be dynamically allocated and copied. The volume must be both mounted and online. You cannot specify a nonspecific volume serial number by using an asterisk (\*). Only one volume is allowed for a FULL or tracks COPY. Data set copy operations allow multiple volumes. To ease JCL coding and command input without appreciably increasing run time, use the INDYNAM keyword instead of data definition statements to allocate DASD volumes.

volser Specifies the volume serial number of a DASD volume that will be copied.

*unit* Specifies the device type of a DASD volume that will be copied. This parameter is optional.

### LOGINDDNAME




LOGINDDNAME specifies that data sets be selected from the specified volume or volumes (which you can also do by specifying INDDNAME or INDYNAM) and also allows you to specify SELECTMULTI (which cannot be done with INDDNAME or INDYNAM).

ddn Specifies the name of the DD statement that identifies a volume that contains the data sets to be copied. For single-volume data sets, each of the DD statements corresponding to a DDNAME (ddn) must identify only one volume serial number.

For more information, refer to "Notes for LOGINDDNAME, LOGINDYNAM and STORGRP keywords" on page 343.

Refer to the description of SELECTMULTI in "LOGINDYNAM."

## **LOGINDYNAM**



LOGINDYNAM specifies that the volumes that contain the data sets to be copied are dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*).

volser Specifies the volume serial number of a DASD volume to be copied.

*unit* Specifies the device type of a DASD volume to be copied. This parameter is optional.

#### **SELECTMULTI**

Specifies the method for determining how cataloged multivolume data sets are to be selected during a logical data set copy operation. SELECTMULTI is accepted only when logical volume filtering is specified with the following keywords:

- LOGINDDNAME
- LOGINDYNAM
- STORGRP

If logical volume filtering is not used, the specification of SELECTMULTI is not accepted.

- **ALL** Specifies that DFSMSdss *not copy* a multivolume data set unless the following criteria is met:
  - The volume list created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword lists all the volumes that contain a part of the data set.
  - The volume list created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword lists all the volumes that contain a part of the VSAM cluster.

ALL is the default.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you only need to list all parts of the base cluster in the volume list.
- Do not specify SPHERE and you must list all parts of the base cluster and the associated alternate indexes in the volume list.

ANY Specifies that DFSMSdss copy a multivolume data set when any part of the data set or VSAM cluster is on a volume in the volume list created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you only need to list any part of the base cluster in the volume list.
- Do not specify SPHERE and you must list any part of the base cluster and the associated alternate indexes in the volume list.

FIRST Specifies that DFSMSdss copy a multivolume data set only when

the volume list includes the volume that contains the first part of the data set. The volume list is created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you only need to list the volume containing the first extent of the data component in the volume list.
- Do not specify SPHERE and you must list the following in the volume list:
  - The volume containing the first extent of the data component for the base cluster.
  - The volume containing the first extent of the data component for the associated alternate indexes

## Notes for LOGINDDNAME, LOGINDYNAM and STORGRP keywords:

#### Note:

- 1. If the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword is not specified, DFSMSdss selects from all data sets that are cataloged in the catalogs that are accessible through the standard search order.
- 2. If the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword is specified, DFSMSdss still uses the standard catalog search order, but it selects data sets only from the specified volumes.
- 3. You must specify the SELECTMULTI keyword to copy a multivolume data set that has extents on volumes which are not identified with the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword.

#### **MAKEMULTI**



MAKEMULTI allows DFSMSdss to convert single volume data sets into multivolume data sets. The default is not to convert single volume data sets into multivolume data sets.

This keyword applies only to SMS-managed target data sets. Only single volume, non-VSAM data sets are eligible to be changed into multivolume data sets.


SMS-managed target data sets are given a volume count (VOLCOUNT) that is either:

- The number of SMS output volumes specified in the COPY command, if output volumes are specified through OUTDDNAME or OUTDYNAM
- The number of volumes in the target storage group or 59, whichever is less.

A data set's volume count is the maximum number of volumes to which the data set may extend. At any one time, there may be a mixture of primary volumes (volumes on which space is allocated for the data set) and candidate volumes (volumes on which space may be allocated at a future time). The total sum of the primary volumes and candidate volumes is the data set's volume count.

Note: When MAKEMULTI is specified and VOLCOUNT is also specified with an option other than VOLCOUNT(\*), the VOLCOUNT option overrides MAKEMULTI.

## **MENTITY**



MENTITY specifies, for RACF-protected data sets, an entity (modeldsn) and, optionally, the serial number of the volume containing that entity (volser). These keywords are used to define the data sets to RACF. Specification of MVOLSER is optional for one of the following:


- When the model entity (MENTITY) is cataloged in an integrated catalog facility catalog.
- When a non-VSAM data set is cataloged in the standard catalog search order.

When MVOLSER is specified for a VSAM model entity, volser must be the volume serial number of the catalog in which the model entity is cataloged. If these keywords are not specified, DFSMSdss defines the data set to RACF by modeling the target profile after the source data set, if the source is discretely protected. Target data sets (preallocated or nonpreallocated) are RACF-protected only if the corresponding source data sets were so protected. If a source data set is protected with a generic profile, RACF generic profile checking must be activated prior to invoking the copy function.

Restriction: You cannot specify the MVOLSER(volser) keyword by itself. It can only be specified in conjunction with the MENTITY(*modeldsn*) keyword.

For more information about data security and data set profile considerations, see Chapter 20, "Data security and authorization checking," on page 531.

## MGMTCLAS



MGMTCLAS specifies the user-desired management class that replaces the source management class as input to the ACS routines. You must have the proper RACF authority for the management class specified. The keyword itself does not require RACF authorization.

NULLMGMTCLAS/NMC specifies that the input to the ACS routines is a null management class rather than the source data set's management class.

MGMTCLAS and NULLMGMTCLAS are mutually exclusive; you cannot specify these keywords together.

Note:

- 1. All SMS-managed data sets specified in the BYPASSACS keyword are assigned the specified management class because the ACS routines are not invoked. Non-SMS-managed data sets do not have a management class.
- 2. See "Assignment of class names by using the RESTORE and COPY commands" on page 494 for information about the assignment of class names using the copy function.
- 3. If DFSMSdss physical data set copy is used to copy the parts of a multivolume data set, the BYPASSACS(dsn) keyword is specified, and a different management class is specified on the MGMTCLAS keyword on each invocation of DFSMSdss, the user will be unable to recatalog the multivolume data set because of the mismatching management classes of the pieces. DFSMSdss is unable to determine at the time of copying a part of the data set, whether or not the management class specified conflicts with one specified on a previous invocation of DFSMSdss. If the BYPASSACS(dsn) keyword is not specified, the correct management class should be chosen by the ACS routines.

## **NOPACKING**



NOPACKING specifies that DFSMSdss is to allocate the target data set only to the same or like device types as the source data set is allocated on and that DFSMSdss is to use track level I/O to perform data movement. This results in an exact track-for-track image of the source data set on the target volume.

dsn Specifies the fully or partially qualified names of a PDS to be processed.

NOPACKing is only valid with a PDS. If REBLOCK is specified, REBLOCK is ignored for the data set. If the data set is specified with CONVERT(PDSE()), NOPACKing is ignored for the data set.

A PDS copied or restored by using NOPACKing is not be compressed during data movement.

NOPACKing can be used for a damaged PDS that is currently usable by an application but would be made unusable by compression or other rearrangement of the physical layout of the data.

## NOTIFYCONCURRENT

See "CONCURRENT" on page 402.

## **NULLMGMTCLAS**

See "MGMTCLAS" on page 344.

#### NULLSTORCLAS

See "STORCLAS" on page 355.

#### **ONLYINCAT**

See "INCAT" on page 339.


### **OUTDDNAME**



ddn Specifies the name of the DD statement that identifies the output DASD volume. To assure correct processing, each of the DD statements corresponding to a DDNAME (ddn) must identify only one volume serial number. The volume serial number specified must be a valid DASD device; DD DUMMY is not supported. Only one volume is allowed for a full, tracks, or physical data set copy operations; one or more volumes are allowed for a logical data set copy operation. Multiple names in a data set copy must be separated by commas.

See the Note under OUTDYNAM for additional information.

## **OUTDYNAM**



OUTDYNAM specifies that the output DASD volume is to be dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*). Only one volume is allowed for a full, tracks or physical data set copy operation; one or more volumes are allowed for logical data set copy.


Specifies the volume serial number of the volume. volser

unit Specifies the device type of the volume. This parameter is optional.

### Notes for OUTDDNAME and OUTDYNAM Keywords:


- 1. DFSMSdss now distinguishes between non-SMS and SMS volumes specified in the OUTDDNAME or OUTDYNAM keywords. For non-SMS allocations, only the volumes that are non-SMS are considered for allocation. Similarly, only SMS volumes are considered for SMS allocations.
- 2. The above distinction is also used when determining the volume count for a multivolume allocation. Where volume count is determined from the number of specified volumes, only those volumes eligible for the type of allocation being done are counted. If there are no volumes that match the type of allocation (SMS volumes for SMS allocation, or non-SMS volumes for non-SMS allocation), processing proceeds with a null volume list.

## **OUTTRACKS**



OUTTRACKS specifies, for a tracks copy operation, the cylinder (cc) and head number (hh) on the output volume to which the tracks from the input volume are to be copied. If you do not specify OUTTRACKS operation, the tracks are copied to the same place on the output volume where they were on the input volume. The number of (cc,hh) combinations specified in the OUTTRACKS keyword must be the same as the number of (c1,h1,c2,h2) combinations specified in the TRACKS keyword.

### **PASSWORD**



PASSWORD specifies the passwords that DFSMSdss is to use for password-protected data sets. (Password checking is bypassed for RACF-protected data sets.) This keyword is required only when:

- You do not have the required RACF DASDVOL or RACF data set access.
- The installation authorization exit does not bypass the checks.
- You do not want to be prompted for the password for VSAM data sets.

**Note:** You should specify the passwords for all data sets that do not have RACF protection but do have password protection. During processing, a utility invoked by DFSMSdss may have to prompt the operator for a password. You can control authorization checking by using the installation authorization exit.

Catalog passwords are not supported to facilitate disaster recovery operations, application data transfers, and data set migration. Catalog protection via an access control facility, such as RACF, is the preferred method of protection.

Passwords for a tracks copy operation are required only for the data sets on which the requested ranges fall.

ddn Specifies the name of the DD statement that identifies the sequential data set, or member of a partitioned data set, that contains data set names and their passwords. This data set must contain card-image records in DFSMSdss command syntax format.


#### dsn/pswd

*dsn* is a fully qualified data set name. *pswd* is its password. If no password follows the slash (/), *dsn* is treated as though it were *ddn*.

Printing of actual data set passwords specified in the input command stream is suppressed in the SYSPRINT output.

When a system utility is being used to perform the DFSMSdss copy operation, the user must supply the password for each password-protected data set selected or have the proper RACF data set access authority.

## PERCENTUTILIZED



PERCENTUTILIZED specifies that DFSMSdss must stop allocating data sets to the target volumes when the allocated space reaches n percent of the total space on the target volume. The default value is 100. Specify more than one n if you have more than one target volume (for instance, a volume for overflow). If there are more target volumes than you have values in this keyword, the last value is used for the remaining target volumes. This keyword is used as a guide only and might not be precise for all situations.

If the output volume is an extended address volume and DFSMSdss is allocating non-VSAM or unsupported VSAM data sets, PERCENTUTILIZED specifies that DFSMSdss must stop allocating data sets to the target volumes when the allocated space reaches n percent of the track-managed space on the target volume.

#### Note:

- 1. PERCENTUTILIZED is ignored when the target data set is preallocated or if you do not specify an output volume.
- 2. PERCENTUTILIZED is not supported in an SMS environment.


#### PHYSINDD



PHYSINDD may be specified to request that DFSMSdss perform a physical copy. It specifies a ddname that describes an input volume to be used for the copy operation. Only one ddname may be specified. The device described by the ddname must be the same type as the output device specified on the OUTDD or OUTDYNAM keyword.

PHYSINDD may be abbreviated to PIDD.


#### **PHYSINDYNAM**



The PHYSINDYNAM keyword specifies the input volume that is to be dynamically allocated to a physical copy or dump operation. A nonspecific volume serial number cannot be specified by using an asterisk (\*). Only one volume may be specified for a FULL, TRACKS, or DATASET COPY. The device described by the volser must be the same type as the output device specified on the OUTDD or OUTDYNAM keyword.

PHYSINDYNAM may be abbreviated to PIDY.

### **PROCESS**



SYS1 specifies that DFSMSdss is to allow data sets with a high-level qualifier of SYS1 to be copied to a preallocated target and that SYS1 data sets can be deleted and uncataloged. SYS1.VVDS and SYS1.VTOCIX data sets cannot be copied, deleted, or uncataloged. To specify PROCESS(SYS1), RACF authorization may be required.

## **UNDEFinedsorg**

PROCESS also specifies that DFSMSdss allow data sets with undefined data set organizations to be copied to an unlike target with a larger capacity. Refer to Table 22 on page 370 and Table 23 on page 371 for the action taken by DFSMSdss.

**Note:** Even though the data is being copied to a device with a larger track capacity, the data may not fit on the output device. For example, if the source device is a 3380, and the output device is a 3390 and the data set's block size is less than 277 bytes, a track on the target cannot contain as much data as a track on the source and the message ADR366W (Invalid Track Format) is issued.

For more information about RACF authorization, see Chapter 5, "Protecting DFSMSdss functions," on page 27.

## **PURGE**




PURGE specifies that unexpired data sets, which reside on the target volume, can be overlaid for a full or track copy operation. If you do not specify PURGE and unexpired data sets exist on the target volume, the copy operation fails.

For data set copy operations, PURGE specifies that unexpired source data sets can be deleted after they have been successfully copied. PURGE is only valid with the DELETE keyword.

**Note:** You must specify PURGE for a full volume copy operation if the VVDS name on the target volume does not match the target volume serial number (*volser*). This procedure applies to volumes that are created by using full volume copy in conjunction with one of the following conditions:

- When DUMPCONDITIONING is specified
- When you do not specify COPYVOLID or DUMPCONDITIONING

#### READIOPACING



READIOPACING specifies the pacing (that is, I/O delay) to be used for DFSMSdss DASD read channel programs. You can use this keyword to allow more time for other applications to complete I/O processing. DFSMSdss waits the specified time before issuing each channel program that reads from DASD.

Specifies the amount of time in milliseconds. The maximum delay that can be specified is 999 milliseconds.

#### Note:

- 1. If READIOPACING is not specified, there is no I/O delay.
- 2. The additional wait time does not apply to error recovery channel programs.
- 3. READIOPACING does not apply to concurrent copy I/O.

#### REBLOCK



REBLOCK specifies that DFSMSdss is to reblock one or more of the selected sequential or partitioned data sets.

Specifies the fully or partially qualified names of a sequential or partitioned data set to be copied and reblocked.

The REBLOCK keyword is ignored for:

- · Unmovable data sets
- Data sets with record format of U (except for partitioned load modules)
- Data sets with a record format of V, VS, VBS, or F
- Partitioned data sets with note lists (except for partitioned load modules)
- Partitioned data sets that are also specified in the NOPACKING keyword
- Compressed data sets in zEDC format.

Additionally, both the installation options exit and the installation reblock exit can override the specification of the REBLOCK keyword. The installation options exit can specify that no data set is to be reblocked. The installation reblock exit can specify whether a given data set is to be reblocked.

Some sequential and partitioned data sets have an attribute indicated in the VTOC making them capable of being reblocked. These data sets may be automatically reblocked by DFSMSdss independent of the REBLOCK keyword.


When copying partitioned load modules to an unlike device, DFSMSdss uses IEBCOPY with COPYMOD specified. This may result in a reblocked data set. When copying to a like device, IEBCOPY with COPY specified is used.

DFSMSdss uses DASD calculation services to determine the optimal block size for the target. The reblocking method used, DFSMSdss or DASD calculation services, is presented to the installation reblock exit.

## **RECATALOG**

See "CATALOG" on page 314.


## **RELBLOCKADDRESS**



RELBLOCKADDRESS identifies the direct data sets (BDAM) whose names match the fully or partially qualified names specified (*dsn*). These direct data sets are organized by relative block address instead of TTR and are to be copied block by block. DFSMSdss updates the block reference count (the relative position of the physical record as stored on its track) of dummy records. This keyword applies only to direct data sets with fixed record formats and without standard user labels.

**Restriction:** If the data set is actually organized by TTR, the data set might become unusable.

## RENAMEUNCONDITIONAL



RENAMEUNCONDITIONAL specifies that the data set must be copied with the new name, regardless of whether the data set exists on DASD with the old name. If the data set exists on the target volume with the new name and the REPLACEUNCONDITIONAL keyword is not specified, an error message is issued, and the data set is not copied.

- pfx Specifies the prefix used to replace the first-level qualifier of the data set name. It is optional, but if specified, must be the first parameter in the list of subkeywords. The prefix is used only if the (on,nn) parameters are not specified or the old name filters do not match the data set name.
- on Specifies the old name to be used as a filtering criterion to check if it matches the data set name.
- nn Specifies the new name to be used to derive the new data set name when the data set name matches the corresponding old name filtering criterion.

The syntax rules for pfx (prefix), on (old name), and nn (new name) are the same as in the RENAME keyword in a restore operation.

#### Note:

- 1. If the RENAMEU keyword is specified in conjunction with the REPLACE keyword, only one of the keywords take effect for any particular data set. The RENAMEU keyword takes precedence over the REPLACE keyword. If a source data set name matches the RENAMEU criteria, then rename processing will be performed and replace processing will not be performed. If a preallocated target data set exists with the new name as chosen by the rename criteria, then the copy fails even if the REPLACE keyword was specified. If you want to replace a preallocated target with the new name, specify the REPLACEUNCONDITIONAL keyword. If a source data set name does not match the rename criteria and a preallocated target data set with the source name exists, the preallocated target data set is replaced.
- 2. If CICSVRBACKUP is also specified, DFSMSdss uses the CICSVR-generated new name instead of the new name that you specified. See "CICSVRBACKUP" on page 316 for more information.
- 3. You can have up to 255 entries using RENAMEUNCONDITIONAL. You cannot go beyond this limit by trying to use FILTERDD. FILTERDD can not be used with RENAMEUNCONDITIONAL.
- 4. RENAMEUNCONDITIONAL is not supported for VSAM Alternate Index (AIX) data sets during a physical data set restore.

For more information about renaming, see "RENAME" on page 478.

## **REPLACE**



REPLACE specifies that DFSMSdss is to search the target volumes for usable preallocated data sets. If a usable preallocated target data set is found, it is replaced with the source data set. If no preallocated target is found, DFSMSdss attempts to allocate a data set.

DFSMSdss searches for preallocated data sets as follows:

- For SMS-managed data sets, DFSMSdss first searches in the standard order of search for a catalog entry for the data set.
- For VSAM data sets that are not SMS-managed, DFSMSdss searches the output volumes for preallocated data sets. If no output volumes are specified, DFSMSdss searches for a catalog entry for the data set.
- · For Non-VSAM data sets that are not SMS-managed, DFSMSdss searches the output volumes for preallocated data sets. If no output volumes are specified, DFSMSdss searches for a catalog entry for the data set.
- If no preallocated target is found, DFSMSdss attempts to allocate a data set. DFSMSdss invokes the ACS routines to determine if the data set should be SMS managed. If it should be SMS managed, then allocation is done according to the SMS constructs. If the data set should not be SMS managed, the output volumes specified are used. If allocation is successful, the data set is copied.

#### Note:

1. If REPLACE is specified with the COPY command:

- The SMS constructs already associated with the preallocated target data set remain the same
- The CA Reclaim attribute already associated with the preallocated target data set remains the same.
- 2. CATALOG and RECATALOG are ignored for preallocated data sets.
- 3. If the source data set is an extended-addressable VSAM data set, then the target must also be an extended-addressable VSAM data set.
- 4. The target data set name must match the source data set name. REPLACEUnconditional must be specified to replace a target data set that has a name matching the rename criteria.
- 5. The REPLACE and REPLACEUnconditional keywords can not be specified together.
- 6. If the RENAMEU keyword is specified in conjunction with the REPLACE keyword, only one of the keywords take effect for any particular data set. The RENAMEU keyword takes precedence over the REPLACE keyword. If a source data set name matches the RENAMEU criteria, then rename processing will be performed and replace processing will not be performed. If a preallocated target data set exists with the new name as chosen by the rename criteria, then the copy fails even if the REPLACE keyword was specified. If you want to replace a preallocated target with the new name, specify the REPLACEUNCONDITIONAL keyword. If a source data set name does not match the rename criteria and a preallocated target data set with the source name exists, the preallocated target data set is replaced.
- 7. If the source data set is a large format sequential data set, but the preallocated target is not a large format sequential data set, the preallocated target data set will be used and turned into a large format sequential data set as long as it has enough allocated space for the source data set.

## REPLACEUNCONDITIONAL



REPLACEUNCONDITIONAL specifies that DFSMSdss is to search the target volumes for usable preallocated data sets. If a usable preallocated target data set is found, it IS replaced. When used with the RENAMEUnconditional keyword, usable preallocated data sets with the new name are replaced. When used without the RENAMEUnconditional keyword, usable preallocated data sets with the same name as the source data set are replaced. If no preallocated target is found, DFSMSdss attempts to allocate a data set. The REPLACE and REPLACEUnconditional keywords can not be specified together.

See the REPLACE keyword description for information about how target volume selection is performed.

#### Note:

- 1. If REPLACEUNCONDITIONAL is specified with the COPY command:
  - The SMS constructs already associated with the preallocated target data set remain the same. If the preallocated target data set is scratched and reallocated, the SMS constructs used are those returned by the ACS routines for the source data set name.

- · The CA Reclaim attribute already associated with the preallocated target data set remain the same.
- 2. CATALOG and RECATALOG are ignored for preallocated data sets.
- 3. If the source data set is an extended-addressable VSAM data set, then the target must also be an extended-addressable VSAM data set.
- 4. If the source is a large format sequential data set, but the preallocated new name target is not a large format sequential data set, the preallocated target will be used and turned into a large format sequential data set as long as it has enough allocated space for the source data set. If the preallocated new name target does not have enough allocated space, it will be scratched and reallocated as a large format sequential data set with enough space for the source data set. If the name of the preallocated target is the same as the source data set, then see the REPLACE keyword.

## SELECTMULTI

Refer to the description of SELECTMULTI in "LOGINDYNAM" on page 341.

## SHARE



SHARE specifies that DFSMSdss is to share the data sets to be copied for read access with other programs.

SHARE and FULL are mutually exclusive; you cannot specify these keywords together.

Do not specify DELETE if you specify SHARE. You must have exclusive control over data sets that are to be deleted; SHARE does not require such exclusive control.

Note: Unlike the RESTORE command, the COPY command honors the SHARE keyword for VSAM data sets. However, the SHARE keyword is only honored for VSAM data sets that were defined with share options other than (1,3) or (1,4).

Specifying the SHARE keyword does not cause DFSMSdss to honor the share options that are defined for VSAM data sets. For VSAM data sets that are defined with share options other than (1,3) or (1,4), specifying the SHARE keyword allows other programs to obtain read access. It does not, however, allow write access to the data sets while they are being copied. For VSAM data sets that are defined with share options (1,3) or (1,4), neither read access nor write access by other programs is allowed while the data set is being copied.

## **SPHERE**




SPHERE specifies that, for any VSAM cluster copied, all associated AIX clusters and paths are to be copied. Individual names of sphere components do not need to be specified. Only the base cluster name is required. If output volumes are specified, the volumes on which the AIX clusters reside do not need to be specified.

#### **Restrictions:**

- If the sphere is specified but the base cluster name is not, DFSMSdss processes only those components of the sphere whose names are specified.
- Do not specify the SPHERE keyword with the CICSVRBACKUP keyword.

#### **STORCLAS**



STORCLAS specifies the storage class that you want to replace (the source storage class) as input to the ACS routines. You must have the proper RACF authorization for the specified storage class. The keyword itself does not require authorization.

NULLSTORCLAS/NSC specifies that the input to the ACS routines is to be a null storage class rather than the source data set's storage class.

STORCLAS and NULLSTORCLAS are mutually exclusive; you cannot specify both keywords simultaneously. See "Assignment of class names by using the RESTORE and COPY commands" on page 494 for information about assigning class names using the copy function.

**Note:** If BYPASSACS(dsn) is specified, all data sets that pass the BYPASSACS selection criteria are guaranteed the specified storage class. The combination of NULLSTORCLAS and BYPASSACS(dsn) forces the selected data sets to be non-SMS-managed.

#### **STORGRP**




STORGRP specifies that all of the online volumes in the storage group be dynamically allocated. If a volume in the storage group is not online, that volume is not used for processing. Up to 255 storage group names may be specified. Specifying STORGRP with a storage group name is equivalent to specifying LOGINDYNAM with all the online volumes in the storage group included in the list.

You can specify the STORGRP keyword with the SELECTMULTI keyword, but STORGRP is mutually exclusive with the INDDname, INDYnam, LOGINDDname and LOGINDYnam keywords.

For more information, refer to "Notes for LOGINDDNAME, LOGINDYNAM and STORGRP keywords" on page 343.

See "LOGINDYNAM" on page 341 for a description of the SELECTMULTI keyword.

## **TGTALLOC**



TGTALLOC specifies how DFSMSdss is to allocate the target data set.

**BLK** by blocks

CYL by cylinders

TRK by tracks


#### SOURCE/SRC

with the same space allocation type as that of the source data set

#### Note:

- 1. If the TGTALLOC keyword is omitted, the target allocation defaults to SOURCE.
- 2. If SRC is specified and if the source data set is allocated by track or if TRK is specified, then the final VSAM allocation might be different from the requested one because of VSAM allocation rules.
- 3. If BLK is specified for VSAM data sets, TRK is used instead. The final VSAM allocation might be different from the requested one because of VSAM allocation rules.

## **TGTGDS**



TGTGDS specifies in what status, during a data set operation, that DFSMSdss is to place nonpreallocated SMS-managed GDG data sets:

#### **DEFERRED**

Specifies that the target data set is to be assigned the DEFERRED status.

#### **ACTIVE**

Specifies that the target data set is to be assigned the ACTIVE status, for example, rolled into the GDG base.

### **ROLLEDOFF**

Specifies that the target data set is to be assigned the rolled-off status.

#### SOURCE/SRC

Specifies that the target data set is to be assigned the same status as that of the source data set.

#### Note:

- If DELETE is specified without RENAMEUNCONDITIONAL and the source data set is an SMS-managed generation data set on a non-DFSMSdss dump conditioned volume, the TGTGDS keyword is ignored and the source GDS status is copied to the target.
- 2. If DELETE is specified without RENAMEUNCONDITIONAL and the source data set is an SMS-managed generation data set on a DFSMSdss dump conditioned volume, the DELETE keyword is ignored and the TGTGDS keyword will be honored.
- 3. The requested target status of generation data sets must not violate generation data group rules.

For more information about the default status when TGTGDS is not specified, see "Restoring GDG data sets" on page 90.

## **TOLERATE**



TOLERATE specifies that DFSMSdss tolerates certain error conditions. For a copy operation (except of a user catalog or loadlib) in which a utility performs the copy, this keyword is ignored.

## **ENQFailure**

specifies that source and target data sets are to be processed even though shared or exclusive access fails.

#### Note:

- 1. Unlike PDS data sets, PDSE data sets that are open for update cannot be copied even if TOL(ENQF) is specified.
- 2. If you must copy a PDSE data set and it must be open for update, convert the PDSE back to PDS and then copy the PDS data set with TOL(ENQF).
- 3. For a logical data set COPY command, TOL(ENQF) is ignored for HFS source data sets.

#### **IOERROR**

specifies that if the input volume can be opened, DFSMSdss is to continue copying even though permanent input errors (busout parity and equipment checks only) occur. DFSMSdss ends after 100 errors when this keyword is specified. The default ends on permanent input errors. On a data set copy in which a utility performs the copy, DFSMSdss ignores this keyword.


### Note:

1. TOL(IOERror) is ignored if CANcelerror is specified.

- 2. You cannot use the TOLERATE(ENQF) keyword when performing a logical copy operation with VSAM extended-format data sets.
- **3**. You cannot use the TOLERATE(ENQF) keyword with a COPY FULL or COPY TRACKS operation.

For more information about using the TOL(ENQF) keyword, see Chapter 21, "Data integrity—serialization," on page 561.

## **TRACKS**



TRACKS specifies ranges of tracks to be copied (that is, a tracks copy).

- *c1,h1* Specifies the cylinder and head number of the beginning of the range. Specify hexadecimal numbers as X'c1' or X'h1'.
- c2,h2 Specifies the cylinder and head number of the end of the range. Specify hexadecimal numbers as X'c2' or X'h2'. The c2 must be greater than or equal to c1. If c2 equals c1, h2 must be greater than or equal to h1.

You can enter X'FFFFFFF' (or 268435455) as the high cylinder value. This causes DFSMSdss to choose the high cylinder value to be the end of the volume.

DFSMSdss verifies that the range is within the limits of the device. If you do not specify all four values for a range, DFSMSdss provides the missing values unless the omitted value causes a syntax error. No intervening values can be omitted. For example:

## Specified

Results

**None** Syntax error

*c*1 c1,0,*c*1,maximum head number

*c1,h1* c1,h1,c1,maximum head number

c1.h1.c2

c1,h1,c2,maximum head number

*c*1,,*c*2 Syntax error

*,h1* Syntax error

c1,h1,X'FFFFFFF'

c1,h1,maximum cylinder number for the volume, maximum head number

**Restriction:** You cannot use the TRACKS keyword with the TOL(ENQF) keyword.

For more information about using the TRACKS keyword, see "Physical processing" on page 18.

## **TTRADDRESS**



TTRADDRESS identifies the direct access data sets whose names match the fully or partially qualified names specified (dsn). These data sets are organized by TTR rather than by relative block addressing and are to be processed track by track. The target device track capacity must be equal to or greater than the source.

**Guideline:** The TTRADDRESS keyword takes precedence over the AUTORELBLOCKADDRESS keyword processing for the specified data sets (*dsn*).


## **UNCATALOG**



UNCATALOG specifies that DFSMSdss is to uncatalog but not scratch successfully copied non-VSAM data sets that are currently cataloged on the source volume. Any non-SMS, non-VSAM data set that has a high-level qualifier of SYS1 cannot be uncataloged unless PROCESS(SYS1) is specified. UNCATALOG is ignored for VSAM data sets and SMS-managed non-VSAM data sets. UNCATALOG will also be ignored when processing data sets that reside on a DFSMSdss dump conditioned volume.

**Note:** Do not specify UNCATALOG with CONCURRENT, because after the concurrent copy operation has begun, the original data can still be updated.

## **VOLCOUNT**



VOLCOUNT specifies the method DFSMSdss uses to determine the number of volumes (volume count) for allocating the SMS target data set for a copy operation of VSAM or non-VSAM data sets.

#### \* (asterisk)

Specifies that DFSMSdss determine the volume count for allocation according to the following conditions:

- If the source data set is a single-volume data set, allocate one volume.
- The source data set is a multivolume data set, and one of the following conditions is present:
  - The OUTDDNAME or OUTDYNAM does not specify a list of volumes.

- There are no SMS volumes in the list

DFSMSdss allocates the same number of volumes that were in the multivolume source data set.

The source data set is a multivolume data set. It has an associated volume list (you specified the OUTDDNAME or OUTDYNAM keyword). DFSMSdss designates the volume count as the number of SMS volumes in the list.

DFSMSdss does not adjust the final number of candidate volumes after the allocation is complete.

The \* (asterisk) is the default for this keyword.

SRC Specifies that DFSMSdss rely on the source volume count to determine the number of volumes to allocate for the target data set as follows:

- If no output volume list is specified, DFSMSdss allocates the same number of volumes that the source data set had.
- If a volume list is specified through OUTDDNAME or OUTDYNAM, the volumes in the list that are SMS-managed must be in the same storage group, and the allocation must be directed to that storage group.

DFSMSdss does not adjust the final number of candidate volumes after the allocation is complete.

**N**(*nn*) *nn* represents the number of volumes to be used for SMS data set allocation. Any value between 0 and 59 may be specified with the following conditions:

- If *nn* is not zero and a volume list is specified through OUTDDNAME or OUTDYNAM, DFSMSdss allocates either the number of SMS volumes in the volume list or nn, whichever is less.
- If *nn* is zero and a volume list is specified through OUTDDNAME or OUTDYNAM, DFSMSdss allocates either the number of SMS volumes in the volume list or the number of volumes that were allocated for the source data set, whichever is less.
- If a volume list is specified through OUTDDNAME or OUTDYNAM and there are no SMS volumes in the list, or there is no volume list, DFSMSdss allocates either the number of volumes used by the source data set or *nn*, whichever is *more*.

DFSMSdss does not adjust the final number of candidate volumes after the allocation is complete.

ANY Specifies that DFSMSdss use a maximum volume count to allocate the SMS target data set as follows:

- DFSMSdss initially sets a volume count of 59 for the allocation.
- If the data set is allocated on more volumes than were used to allocate the source data set, DFSMSdss reduces the number of volumes used to the number of primary volumes needed to satisfy the allocation.
- If the data set is allocated on the same number or fewer volumes than were used to allocate the source data set. DFSMSdss reduces the number of volumes used to the number of volumes used for allocation of the source data set.

Note:

- 1. VOLCOUNT does not convert any of the following data sets to multivolume: PDS or PDSE data sets, single-volume data sets whose organization is undefined, or empty non-VSAM, single-volume data sets.
- 2. VOLCOUNT does not change the number of volumes for keyrange KSDS data sets.
- 3. Guaranteed space is not honored when VOLCOUNT(ANY) is used.
- 4. VOLCOUNT(ANY) does not support keyed VSAM data sets that have an imbedded index. If VOLCOUNT(ANY) is specified and a data set has an imbedded index, the data set is processed as if VOLCOUNT(\*) were specified.
- 5. VOLCOUNT(ANY) does not support any type of striped data set (physical, sequential, extended, or VSAM). If VOLCOUNT(ANY) is specified and a data set is striped, the data set is processed as if VOLCOUNT(\*) were specified.
- 6. When you specify VOLCOUNT(ANY), the &ANYVOL and &ALLVOL read-only variables are not available to the storage group ACS routine.
- 7. For nonguaranteed-space, striped VSAM data sets: The minimum number of volumes that DFSMSdss allocates is determined by the number of stripes, which is based on the STORCLAS sustained data rate (SDR). DFSMSdss does not consider the number of volumes in the output volume list or any of the VOLCOUNT specifications. If there are not enough enabled volumes in the STORGRP to support the SDR, DFSMSdss reduces the number of stripes. If there are excess volumes specified, those volumes become nonspecific (\*) candidates.
- 8. For guaranteed-space, striped VSAM data sets: DFSMSdss allocates the number of volumes that are specified in the output list, regardless of the SDR. (To be striped, the SDR must be greater than zero.) The VOLCOUNT rules described above apply.

You can override VOLCOUNT keyword settings with the options installation exit routine.

For more information about overriding VOLCOUNT keyword settings, see *z/OS DFSMS Installation Exits*.

## WAIT



WAIT Specifies to DFSMSdss the length of the wait in seconds, and the number of passes to be made through the list of selected data sets to obtain control of a data set for the COPY DATASET command.

#### numsecs

Specifies a decimal number (0–255) that designates the interval, in seconds, to wait before attempting another pass through the entire list of selected data sets.

### numretries

Specifies a decimal number (0–99) that designates the number of passes to make through the list of selected data sets in an attempt to obtain control of a data set.

The default for numsecs, numretries is (2,2), which specifies two retries at 2-second intervals. If you do not want to wait for a resource, specify 0 for either numsecs or numretries.

For a data set copy operation the WAIT keyword has a different meaning when: (1) data sets are being serialized, (2) multiple data sets are being processed, and (3) WAIT(0,0) is not specified. In this case, DFSMSdss makes multiple passes through the list of data sets. On each pass, DFSMSdss processes the data sets that (1) can be serialized without waiting for the resource and (2) were not processed before. At the end of a pass, if none of the data sets can be processed without waiting for a resource, then, in the next pass, at the first occurrence of a data set that was not processed, a WAIT is issued. That data set and the remainder of the list are processed if possible.

The above procedure is repeated until all data sets are processed or the WAIT limits are reached. For example, if WAIT(3,10) is specified and five data sets are left to be processed, up to ten passes are made. On each pass, an unprocessed data set is waited upon for 3 seconds. Thus, only a 30-second maximum is ever waited, not 150 (5 times 3 times 10).

Note: The WAIT keyword does not control wait/retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is 3 seconds and the default retry count is 30. This results in a total wait time of 90 seconds. For information about controlling the wait/retry attempts for system resources, see "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

## WRITECHECK



WRITECHECK specifies that the data copied is to be verified for successful completion. This keyword increases the overall elapsed time.

#### Note:

- 1. On a data set copy in which a utility performs the copy, DFSMSdss ignores this
- 2. The WRITECHECK keyword is not supported for extended-format sequential data sets.

## Data Integrity Considerations for Full or Tracks Copy Operation

For a full or tracks copy operation, DFSMSdss serializes the VTOC to preclude DADSM functions (such as ALLOCATE, EXTEND, RENAME, and SCRATCH) from changing the contents of the VTOC on the volume during the copy operation. Data sets are *not* serialized on these full or tracks operations. Therefore, some data sets might be opened by other jobs during the copy, resulting in copies of partially updated data sets. You can minimize this possibility by performing the copy when there is low system activity.

Full data integrity can only be guaranteed by performing copy operations by data set when TOL(ENQF) or SHARE are not specified.

## **Examples of Full and Tracks Copy Operations**

The following examples are for FULL and tracks COPY operations.

## **Example 1: Data Set Copy Operation**

```
//JOB1 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//DASD1 DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//DASD2 DD UNIT=3380, VOL=(PRIVATE, SER=222222), DISP=OLD
//SYSIN DD *
command input
/*
```

See command input in "Example 1A: A Full Copy Operation" and "Example 1B: A Tracks Copy Operation."

**Example 1A: A Full Copy Operation** 

```
COPY INDDNAME(DASD1) OUTDDNAME(DASD2) -
ALLDATA(*) ALLEXCP CANCELERROR COPYVOLID
```

**Example 1B: A Tracks Copy Operation** 

```
COPY TRACKS(1,0,1,15) INDDNAME(DASD1) -
OUTDDNAME(DASD2) CANCELERROR
```

The data from DASD volume 111111 is to be copied to DASD volume 222222. For the full copy operation (example 1A), all allocated space in sequential or partitioned data sets, and in data sets with a data set organization that is null, is copied (ALLDATA(\*)). The volume serial number (VOLID) of the source volume will be copied to the target volume. The result is that both volumes will have the same serial number (111111).

The preceding applies only to data sets that are not empty. For data sets that are empty, DFSMSdss copies all data within the allocated space (ALLEXCP). The copy operation is to be ended if a permanent read error occurs (CANCELERROR).

## **Example 2: A Tracks Copy with Track Relocation**

The following example shows a tracks copy operation in which the contents of cylinder 1, tracks 0 through 14, on source volume 338000 are copied to cylinder 3, tracks 0 through 14, on target volume 338001. The operation stops if a permanent error occurs on the source volume (CANCELERROR). The data written to the target volume is to be verified (WRITECHECK).

```
//J0B2
          JOB accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//SYSIN
          DD
COPY TRACKS(1,0,1,14) /* SOURCE TRACKS */ -
                     /* TARGET TRACKS */ -
  OUTTRACKS(3,0)
  INDYNAM(338000)
                      /* ALLOC VOL 338000 DYNAMICALLY */ -
  OUTDYNAM(338001)
                     /* ALLOC VOL 338001 DYNAMICALLY */ -
  CANCELERROR
                      /* STOP ON INPUT ERROR
                      /* VERIFY DATA WRITTEN TO OUT VOL */
  WRITECHECK
```

## **Examples of Data Set Copy Operations**

The following examples are for data set copy operations.

## Example 1: A Data Set Move—Only Single Volume Data Sets

```
//J0B3
          JOB accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//SYSIN DD
COPY DATASET(
                              /* FILTER ON DS W/1ST LEV Q USER1 */ -
  INCLUDE(USER1.**)
  BY(MULTI,=,NO))
                             /* FILTER ON SINGLE VOLUME
                            /* ALLOC VOL 338000, 338002 DYNAMICALLY */ -
  INDYNAM (338000,338002)
  OUTDYNAM(338001)
                            /* ALLOC VOL 338001 DYNAMICALLY */ -
  DELETE
```

Example 1 shows a data set copy operation in which all single-volume data sets with the first-level qualifier USER1 on the source volumes that are labeled 338000 and 338002 are copied to the target volume that is labeled 338001. All source data sets that are selected and successfully processed are deleted. The copied non-SMS, non-VSAM data sets are not cataloged.

## Example 2: A Data Set Copy to Move Data Sets to a Single Volume—Device Conversion

```
//J0B4
          JOB accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//SYSIN
          DD
COPY DATASET(
  INCLUDE(USER1.**)) /* FILTER ON DS W/1ST LEV Q USER1 */ -
  OUTDYNAM(338001)
                     /* ALLOC VOL 338001 DYNAMICALLY
  DELETE CATALOG FORCE -
  TGTALLOC(SOURCE)
```

Example 2 shows a data set copy operation in which all cataloged data sets with a first-level qualifier of USER1 (USER1.\*\*) are consolidated on a single target volume that is labeled 338001. The data sets can reside on multiple source volumes. The target volume can differ in device type from other volumes on which the source data sets reside. A few data sets might already reside on volume 338001. Data sets are cataloged in the standard search order. Expired source data sets are scratched and uncataloged after they are successfully moved to volume 338001. On volume 338001, they have the same allocation type (BLK, TRK, or CYL) that they had on the source volumes. FORCE is specified to include unmovable data sets.

## **Example 3: A Data Set Copy of a Multivolume Data Set**

```
//J0B5
          JOB accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
          DD UNIT=(SYSDA,2), VOL=SER=(VOL111, VOL222), DISP=SHR
//IVOL1
//IVOL2
          DD UNIT=SYSDA, VOL=SER=VOL222, DISP=SHR
//SYSPRINT DD
              SYSOUT=A
//SYSIN DD
COPY DATASET(
  INC(USER.MULTI.VOLUME1)) /* SELECT THIS DATA SET
  INDD(IVOL1,IVOL2) /* IDENTIFY INPUT VOLUMES */ -
  OUTDYNAM((338001),(338002),(338003)) /* DYNAM ALLOC VOLS */ -
  PCTU(80,80,80)
                         /* PERCENTUTIL = 80 PERCENT */ -
  RECATALOG (USERCAT2)
```

Example 3 shows a data set copy operation in which a multivolume data set is copied to a set of target volumes labeled 338001, 338002, and 338003. The source data set is not deleted. The copied data set is cataloged in a new catalog, USERCAT2. The data set currently exists on multiple source volumes. Multiple output volumes are specified for overflow purposes. However, the output cannot be on more volumes than the source data set. These target volumes might already have data sets that reside on them. Space is left on these volumes to allow expansion of the data sets that remain on the volumes.

To include SELECTMULTI processing, you can change Example 3 as shown later in this section. The INCLUDE keyword specifies that you want to select all data sets on input volumes VOL111 and VOL222. The SELECTMULTI(ANY) keyword specifies that a cataloged data set that resides on volumes VOL111, VOL444, and VOL555 is copied even though VOL444 and VOL555 are omitted from the LOGINDD volume list.

```
//J0B5
           JOB accounting information, REGION=nnnnK
          EXEC PGM=ADRDSSU
//STEP1
          DD UNIT=(SYSDA,2), VOL=SER=(VOL111, VOL222), DISP=SHR
//IVOL1
//IVOL2
          חח
               UNIT=SYSDA, VOL=SER=VOL222, DISP=SHR
//SYSPRINT DD
               SYSOUT=A
//SYSIN DD
COPY DATASET(
                           /* SELECT ALL DATA SETS
   INC(**))
   LOGINDD(IVOL1,IVOL2)
                            /* IDENTIFY INPUT VOLUMES */ -
   OUTDYNAM((338001),(338002),(338003)) /* DYNAM ALLOC VOLS */ -
   SELECTMULTI (ANY)
                              /* PROCESS MISSING VOLUMES */ -
   PCTU(80,80,80)
                              /* PERCENTUTIL = 80 PERCENT */ -
   RECATALOG(USERCAT2)
```

## Example 4: A Data Set Copy with DELETE and RENAMEU **Options**

```
//J0B6
          JOB accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//SYSIN DD
COPY DATASET(
   INCLUDE(USER1.**)) /* FILTER ON DS W/1ST LEV Q USER1 */ -
   OUTDYNAM((338001),(338002),(338003)) /* DYNAM ALLOC VOLS */ -
  RENAMEU (USER2)
   RECATALOG (USERCAT2)
```

Example 4 shows a data set copy operation. All the data sets with the high-level qualifier USER1 that are in the standard search order are copied to the target volumes that are labeled 338001, 338002, and 338003. The copied data sets are renamed to the high-level qualifier USER2, followed by the second through last qualifiers of the old names. If data sets with the same name as the new names are on the target volumes or if the data sets are already cataloged in USERCAT2, they are not copied. The copied, expired data sets are deleted from the source volumes, uncataloged, and recataloged in the USERCAT2 catalog. This process moves the data sets from one set of volumes to another set of volumes, from one catalog to another catalog, and renames them.

## Example 5: A Data Set Copy With REBLOCK Option

```
//J0B7
           JOB accounting information, REGION=nnnnK
//STEP1
           EXEC PGM=ADRDSSU, PARM='UTILMSG=YES'
//SYSPRINT DD SYSOUT=A
           DD UNIT=3380, VOL=(PRIVATE,,,,SER=338001),DISP=SHR
//DISK
//DISK2
           DD UNIT=3390, VOL=(PRIVATE,,,,SER=339001), DISP=SHR
//SYSIN
           DD
COPY DATASET(
   INCLUDE(**) )
                        /* INCLUDE ALL DATA SETS */ -
   LOGINDDNAME(DISK) /* INPUT VOLUME
OUTDDNAME(DISK2) /* OUTPUT VOLUME
   REBLOCK(**.USER1.**)
```

Example 5 shows a data set copy operation in which all data sets on the 3380 source volume that is labeled 338001 are copied to the 3390 target volume that is labeled 339001. If data sets with the same name are on the target volume, they are not copied. The sequential and partitioned data sets that meet the filtering criteria that is specified in the REBLOCK keyword are reblocked on the target volume. The block size is selected by DFSMSdss, unless it is modified by the user reblock exit routine.

## **Example 6: A Data Set Copy to a Preallocated Target Data Set**

```
//J0B8
            J0B
                 accounting information, REGION=nnnnK
//STEP1
            EXEC PGM=ADRDSSU
//SYSPRINT
                 SYSOUT=A
           חח
//DASD1
                 UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//DASD2
            DD
                 UNIT=3380, VOL=(PRIVATE, SER=222222), DISP=OLD
//SYSIN
            DD
COPY DATASET(
   INCLUDE(USER.TEST.DATA) ) -
   LOGINDDNAME(DASD1) -
  OUTDDNAME(DASD2) -
   REPLACE
  DELETE
```

Example 6 shows a data set copy in which a source data set (USER.TEST.DATA) allocated on volume 111111 and cataloged in catalog USERCAT is copied to a preallocated target data set (with the same name as the source) on volume 222222. The REPLACE keyword specifies that you want DFSMSdss to search the target volume for a usable preallocated data set. The data set is deleted from the source volume, if it is expired.

## Example 7: Using the COPY Command to Convert to SMS

Example 7 shows non-SMS-managed volumes that are converted to SMS-managed volumes. It is a two-step process.

```
//J0B9
            JOB accounting information, REGION=nnnnK
//STEP1
           EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SYSIN
           DD
COPY
  DS(INC(**)) -
       LOGINDYNAM ( -
           (338001) -
           (338002) -
      STORCLAS(DB2PERF) -
      MGMTCLAS (DBBACKUP) -
      BYPASSACS(**) -
       DFIFTE -
       PURGE
```

In step 1 of Example 7, all data sets on the non-SMS-managed volumes 338001 and 338002 are copied to SMS-managed volumes on the system. DELETE and PURGE processing is used to avoid duplicate catalog entries. ACS routines are not invoked to determine the target data set classes for this copy operation. Instead, users provide storage and management classes with the STORCLAS and MGMTCLAS keywords. In addition, users can suppress calls made to the ACS routines with the BYPASSACS(\*\*) keyword. All data sets that are supported by SMS are given these new storage and management classes. All data sets that cannot be SMS-managed (for example, unmovable data sets) are not copied.

```
//JOB9 JOB accounting information, REGION=nnnnK
//STEP2 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
COPY -
DS(INC(**)) -
LOGINDYNAM (-
(338001) -
(338002) -
) -
RENUNC(AUG0387)
/*
```

In step 2 of Example 7, all data sets on the non-SMS-managed volumes 338001 and 338002 are copied to SMS-managed volumes on the system. The RENUNC command is used to avoid duplicate catalog entries. The ACS routines select a target storage and management class for each data set. Those data sets that cannot be SMS-managed (storage class ACS routine returns a null storage class) are not copied because no output volume is specified. Each data set that is copied is given a new high-level qualifier (AUG0387) and automatically cataloged.

## **Example 8: A Data Set Copy Using CONVERT PDSE**

```
//JOB2 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
COPY -
DS(INC(USER.PDS.**)) -
LOGINDYNAM ( -
(338001) -
(338002) -
) -
CONVERT (PDSE(**)) -
RENUNC (USER.PDS.**, USER.PDSE.**)
/*
```

Example 8 shows all data sets with the first two qualifiers of USER.PDS on non-SMS-managed volumes 338001 and 338002 are copied to SMS-managed volumes on the system. CONVERT PDSE is used to convert data sets to PDSE. The RENUNC keyword is used to avoid duplicate catalog entries. The ACS routines select a target storage and management class for each data set. Each data set that is copied and converted is given a new secondary qualifier (PDSE) and automatically cataloged.

## Example 9: A Data Set Copy with CONCURRENT

```
//DSSJOB JOB accounting information,REGION=nnnnK
//COPYSTEP EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
COPY DATASET(INCLUDE(USER.LOG,USER.TABLE,USER.XREF)) -
OUTDYNAME(OVOL01,0VOL02,0VOL03,0VOL08) -
ALLDATA(*) ALLEXCP CONCURRENT -
STORCLAS(BACKUP) RENAMEUNCONDITIONAL(USERX)
/*
```

Example 9 shows the required JCL for DFSMSdss to perform a logical data set copy using the concurrent copy feature. This job continues (with a warning message) if concurrent copy initialization fails.

## **Example 10: Copying a HFS using logical COPY**

Example 10 shows the required JCL for DFSMSdss to perform a logical copy of a HFS.

## **ALLDATA and ALLEXCP Interactions**

Table 22 on page 370 and Table 23 on page 371 describe the functions of the ALLDATA and ALLEXCP keywords during a data set copy to LIKE and UNLIKE devices, respectively.

## **COPY Command**

Table 22. ALLDATA and ALLEXCP Interactions When Copying to LIKE Device. Read the first eleven columns to find the row that matches your situation. Read the last column to find what DFSMSdss does.

- Y
- N No
- Either X
- Not Applicable
- Allocate and copy all the allocated space 1
- 2 Allocate and copy only the used space
- 3 Allocate and copy only one track
- 4 Allocate all the allocated space, and copy only the used space
- 5 Allocate all the allocated space, and copy only one track
- Do not process the data set 6

Empty Data Set	EOF as First Record	DSORG	Load Module	ALLDATA(*)	ALLDATA(dsn)	ALLEXCP	NOPACKING	REBLOCK	Action
X	Х	Undefined	-	Х	Х	Х	-	X	1
N	Х	Sequential <sup>1</sup>	-	N	N	Х	-	Х	2
N	Х	Sequential <sup>1</sup>	-	Y	-	Х	-	N	1
N	Х	Sequential <sup>1</sup>	-	Y	-	Х	-	Y	4
N	X	${\sf Sequential}^1$	-	-	Y	Χ	-	N	1
N	X	${\sf Sequential}^1$	-	-	Y	Χ	-	Y	4
N	Х	Partitioned <sup>2</sup>	Х	N	N	Х	N	X	2
N	Х	Partitioned <sup>2</sup>	Х	N	N	N	Y	Х	1
N	Х	Partitioned <sup>2</sup>	N	Y	-	Х	N	X	4
N	Х	Partitioned <sup>2</sup>	N	-	Y	X	N	Х	4
N	Х	Partitioned <sup>2</sup>	Y	Y	-	Х	N	N	1
N	Х	Partitioned <sup>2</sup>	Y	Y	-	Х	N	Y	4
N	Х	Partitioned <sup>2</sup>	Y	-	Y	Х	N	N	1
N	Х	Partitioned <sup>2</sup>	Y	-	Y	Х	N Y		4
Y	N	Sequential <sup>1</sup>	-	Χ	Χ	N	-	X	6
Y	N	Sequential <sup>1</sup>	-	Χ	X	Y	-	N	1
Y	N	Sequential <sup>1</sup>	-	Х	Х	Y	-	Y	6
Y	Y	Sequential <sup>1</sup>	-	Х	Х	Y	-	N	1
Y	Y	Sequential <sup>1</sup>	-	Х	Х	Y	-	Y	3
Y	Y	Sequential <sup>1</sup>	-	N	N	N	-	X	5
Y	Y	Sequential <sup>1</sup>	-	Y	-	N	-	Х	3
Y	Y	Sequential <sup>1</sup>	-	-	Y	N	-	X	3

<sup>• 1</sup> When ALLDATA or ALLEXCP is specified for a sequential extended format data set, data beyond the last used block pointer is not retained. The target data set is allocated with the same amount of space as the source data set during a logical restore or copy operation.

<sup>• &</sup>lt;sup>2</sup>Partitioned data sets that have directories (whether or not there are empty members in the directory) are treated as not empty.

Table 23. ALLDATA and ALLEXCP Interactions When Copying to UNLIKE Device. Read the first twelve columns to find the row that matches your situation. Read the last column to determine what DFSMSdss does.

- Y Yes
- N No
- X Either
- Not Applicable
- Allocate the same number of tracks as the source, and make a track image copy.
- 2 Allocate and copy only the used space
- 3 Allocate and copy only one track
- 4 Allocate all the allocated space, and copy only the used space
- 5 Allocate all the allocated space, and copy only one track
- 6 Do not process the data set

Empty Data Set		BLKSIZE=0 Data Set	DSORG	Load Module	Target Tracksize > Source	PROCESS (UNDEF)	ALLDATA (*)	ALLDATA (dsn)	ALLEXCP	Action
X	X	Χ	Undefined	-	Χ	N	X	Χ	X	6
X	X	Χ	Undefined	-	N	Y	X	X	X	6
X	X	Χ	Undefined	-	Y	Y	X	X	X	1
N	Х	N	Sequential <sup>1</sup>	-	X	-	N	N	N	2
N	X	N	Sequential <sup>1</sup>	-	Χ	-	Y	-	X	4
N	Х	N	Sequential <sup>1</sup>	-	Х	-	-	Y	Х	4
N	Х	Y	Sequential <sup>1</sup>	-	Х	-	Х	Χ	Х	6
N	Х	Х	Partitioned <sup>2</sup>	N	Х	-	N	N	N	2
N	Х	Х	Partitioned <sup>2</sup>	N	Х	-	Y	-	Х	4
N	Х	Х	Partitioned <sup>2</sup>	N	Х	-	-	Y	Х	4
N	Х	N	Partitioned <sup>2</sup>	Y	Х	-	N	N	Х	2
N	Х	N	Partitioned <sup>2</sup>	Y	Х	-	Y	-	Х	4
N	Х	N	Partitioned <sup>2</sup>	Y	Х	-	-	Y	Х	4
N	Х	Y	Partitioned <sup>2</sup>	Y	Х	-	Х	Χ	Х	6
Y	N	Х	Sequential <sup>1</sup>	-	Х	-	Х	Х	Х	6
Y	Y	N	Sequential <sup>1</sup>	-	Х	-	N	N	N	3
Y	Y	N	Sequential <sup>1</sup>	-	Х	-	N	N	Y	5
Y	Y	N	Sequential 1	-	Х	-	Y	-	N	3
Y	Y	N	Sequential <sup>1</sup>	-	X	-	-	Y	Х	5
Y	Y	Y	Sequential 1	-	Х		X	Х	X	6

#### Notes:

## **COPYDUMP command for DFSMSdss**

With the COPYDUMP command, you can make from 1 to 255 copies of DFSMSdss-produced dump data. The data to be copied, a sequential data set, can be on a tape or a DASD volume, and copies can be written to a tape or a DASD volume. If the dump data is produced from multiple DASD volumes by using a physical data set dump operation, you can selectively copy the data from one or more of those volumes.

 <sup>&</sup>lt;sup>1</sup> When ALLDATA or ALLEXCP is specified for an extended-sequential data set, data beyond the last used block pointer is not retained. The target data set is allocated with the same amount of space as the source data set during a logical restore or copy operation.

 <sup>2</sup> Partitioned data sets that have directories (whether or not there are empty members in the directory) are treated as not empty.

## **COPYDUMP Command for DFSMSdss**


The COPYDUMP command cannot change the block size of the DFSMSdss dump data set. If you are copying a dump data set to a DASD device, the source block size must be small enough to fit on the target device.

You can use the COPYDUMP command to convert a sequential data set between extended format and non-extended format.

#### Note:

- 1. Extra dump tapes can be used for such things as disaster recovery backup or distribution of dumped data (for example, a newly generated system).
- 2. COPYDUMP is the only supported method for copying DFSMSdss dump data sets. Using a copy produced by any other method or utility as input to a RESTORE operation can produce unpredictable results.

## COPYDUMP syntax



## **Explanation of COPYDUMP command keywords**


This section describes the keywords for the COPYDUMP command.

## **INDDNAME**



ddn Specifies the name of the DD statement that identifies the sequential data set to be copied. This data set can reside on one or more tapes, or on DASD volumes.

#### LOGICALVOLUME



Specifies the source DASD volume serial number from which dumped data volser is to be copied. Omission of the LOGICALVOLUME keyword causes DFSMSdss to copy data from all logical volumes in the dump data set. This keyword is useful only if the data being copied was created by a

physical data set dump operation from multiple DASD volumes. When copying a *logical* dump, LOGICALVOLUME is ignored.

### **OUTDDNAME**



ddn Specifies the name of the DD statement that identifies the output sequential data set. This data set can be on a tape or a DASD volume.

## **Examples of COPYDUMP operations**

The following are examples of the COPYDUMP command.

## Example 1: making two copies of a dump

```
//J0B1
          J0B
                accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD
                SYSOUT=A
//BACKUP DD
             UNIT=3480, VOL=SER=TAPE05, DISP=OLD,
// DSNAME=V111111.BACKUP
//COPY1 DD UNIT=3480, VOL=SER=TAPE06,
// DISP=(NEW,CATLG),DSNAME=V111111.BACKUP1
//COPY2 DD UNIT=3480, VOL=SER=TAPE07,
// DISP=(NEW,CATLG),DSNAME=V111111.BACKUP2
//SYSIN
         DD
  COPYDUMP -
    INDD(BACKUP) -
    OUTDD(COPY1, COPY2)
```

In this example, two copies are to be made from a DFSMSdss dump tape (OUTDD(COPY1,COPY2)).

# Example 2: copying a dump created by using physical data set processing

```
//J0B2
          J0B
                accounting information, REGION=nnnnK
          EXEC PGM=ADRDSSU
//STFP1
//SYSPRINT DD
                SYSOUT=A
//TAPE2 DD
               UNIT=3480, VOL=SER=TAPE20,
// LABEL=(1,SL),DISP=(OLD,KEEP),DSN=USER.BACKUP.REL3A
//OUTT2 DD UNIT=3480, VOL=SER=TAPE21,
// LABEL=(1,SL),DISP=(NEW,CATLG),DSN=USER.BACKUP.REL3A.A
//SYSIN
COPYDUMP -
                        /* DUMP TAPE TO BE COPIED
   INDD(TAPE2)
   OUTDD (OUTT2)
                         /* NEW DUMP TAPE
                         /* SER NO OF VOL TO BE COPIED */
  LVOL(338001)
```

Assume that a *physical* data set dump operation was used to create a dump tape, volume TAPE20. Also assume that source DASD volumes 338000, 338001, and so on were specified, resulting in VTOCs being used for data set selection. Only the dump data from DASD volume 338001 is to be copied (LVOL(338001)).

## Example 3: copying a dump created by using logical data set processing

```
//J0B3
                accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD
                SYSOUT=A
              UNIT=3480, VOL=SER=TAPE30,
//TAPE3 DD
// LABEL=(1,SL),DISP=(OLD,KEEP),DSN=USER.BACKUP.REL3B
//OUTT3
               UNIT=3480, VOL=SER=TAPE31,
          DD
// LABEL=(1,SL),DISP=(NEW,CATLG),DSN=USER.BACKUP.REL3B.A
//SYSIN
        DD
COPYDUMP -
  INDD(TAPE3)
                         /* DUMP TAPE TO BE COPIED
  OUTDD(OUTT3)
                         /* NEW DUMP TAPE
```

Assume that a logical data set dump operation was used to create a dump tape, volume TAPE30. All dump data is copied.

## **DEFRAG command for DFSMSdss**


When you enter the DEFRAG command, DFSMSdss relocates data set extents on a DASD volume to reduce or eliminate free space fragmentation. You can specify which data sets, if any, should be excluded from relocation. When the DEFRAG operation completes, a summary report is created to show the before and after statistics of the volume. The report includes the fragmentation index, the size of the largest free space extent, and so on.


The amount of time it takes for a DEFRAG operation to complete depends on the size and fragmentation of the volume being processed. In general, larger or more fragmented volumes take longer to process.


Before using DEFRAG on a volume, you might want to use the CONSOLIDATE command to consolidate the extents of any multiple extent data sets on the volume.

Attention: Canceling the DEFRAG command is strongly discouraged, because doing so can damage data in numerous and unpredictable ways. Before using the DEFRAG command, consider how long the operation will take by evaluating the size and the fragmentation of the volume being processed. To limit the duration of the DEFFRAG operation, using the MAXTIME keyword is recommended.

## **DEFRAG** syntax







# **Explanation of DEFRAG command keywords**

This section describes the keywords for the DEFRAG command.

# **ADMINISTRATOR**




The ADMINISTRATOR keyword allows you to act as a DFSMSdss authorized storage administrator for the DEFRAG command. DFSMSdss-initiated access checking to data sets and catalogs is bypassed.

To use the ADMINISTRATOR keyword, all of the following must be true:

- The RACF FACILLITY class is active
- The applicable FACILITY class profile is defined
- You have READ access to that profile.

For more information about using the ADMINISTRATOR keyword see "ADMINISTRATOR keyword" on page 541.

# BY



BY specifies data set filtering criteria.

## DDNAME(ddn)

Specifies the name of the data definition (DD) statement that identifies a

sequential data set or member of a partitioned data set that contains the filtering criteria to use. This is in the form of card-image records, in DFSMSdss command syntax, that contain the BY keywords that are described below.

## **LIST((**schar,op,((arg))))

Specifies data set filtering. To select the data set for inclusion in the DEFRAG operation, *all* BY criteria must be met. See "Filtering by data set characteristics" on page 262 for a full discussion of *schar*, *op*, and *arg*.

### CONSOLIDATE



CONSOLIDATE specifies that DEFRAG perform extent reduction by combining the extents of data sets with multiple extents. When you specify CONSOLIDATE, DFSMSdss consolidates data set extents where possible and then continues with normal free space defragmentation processing.

**Note:** The process of combining data set extents can cause the free space to be more fragmented than it was before the operation began. And, although DFSMSdss performs free space defragmentation following the consolidation of data set extents, there is a possibility that the fragmentation index may be higher following a DEFRAG operation with CONSOLIDATE specified.


**Attention:** Use the CONSOLIDATE command instead of the DEFRAG command with the CONSOLIDATE keyword, which is obsolete. Otherwise, DFSMSdss issues an informational message and runs the CONSOLIDATE command instead, for all files on the device not excluded through the EXCLUDE or BY filtering keywords. When CONSOLIDATE processing completes, DEFRAG then runs as expected. To have consolidation proceed as it did in previous releases, you must specify the VERSION1 keyword with the CONSOLIDATE keyword.

### **DDNAME**



Specifies the name of the DD statement, *ddn*, that describes the volume to be processed.

# **DEBUG**



You can use the DEBUG keyword as a diagnostic tool. Specify DEBUG with one of the following sub-keywords:

#### **TRACE**

Specifies that DFSMSdss is to print messages that identify the relocated extents.

#### **FRMSG**

Specifies that DFSMSdss is to issue an informational message to explain why fast replication or Preserve Mirror operation could not be used during the DEFRAG operation. The DEBUG keyword overrides the DEBUG=FRMSG parameter specified in the JCL EXEC statement. For Preserve Mirror operations, the DEBUG(FRMSG) keyword might not have an effect if the FlashCopy target is not a PPRC Primary device.

If you specify DEBUG(FRMSG), you must also specify one of the following sub-keywords:

### FRMSG(MINIMAL)

Specifies that DFSMSdss is to issue an informational message with a minimal level of information. The following examples show the messages that are issued when you use this keyword:

# **Examples**

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR VOLUME SRCV01, RETURN CODE F
```

Return code F indicates that the volume does not support data set fast replication.

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR VOLUME SRCV01, RETURN CODE 3
```

Return code 3 indicates that the source device is not eligible for fast replication at this time.

#### FRMSG(SUMMARIZED)

Specifies that DFSMSdss is to issue an informational message with summary information. When applicable, summary information regarding ineligible volumes is provided in the message text. The following examples show the messages that are issued when you use this keyword:

#### **Examples**

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR VOLUME SRCV01, RETURN CODE F
```

Return code F indicates that the volume does not support data set fast replication.

In this example, the DEBUG(FRMSG(MINIMAL)) keyword provides the same level of informational message as when you specify the DEBUG(FRMSG(SUMMARIZED)) or DEBUG(FRMSG(DETAILED)) keyword.

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR
VOLUME SRCVO1, RETURN CODE 3
VOLUME SRCVO1 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 7 - VERSION 1 FC
RELATION EXISTS
```

In this example, the DEBUG(FRMSG(SUMMARIZED)) keyword provides the same level of informational message as when you specify the DEBUG(FRMSG(DETAILED)) keyword.

**Guideline:** When the FASTREPLICATION(REQUIRED) keyword is specified and the DEBUG(FRMSG(MIN | SUM | DTL)) keyword is not specified, DFSMSdss still issues an informational message when a data set fast replication method cannot be used in DEFRAG operation. It is as if the DEBUG(FRMSG(SUMMARIZED)) keyword had been specified.

# FRMSG(DETAILED)

Specifies that DFSMSdss is to issue an informational message with detailed information. When applicable, detailed information regarding ineligible volumes is provided in the message text.

**Note:** DFSMSdss issues an informational message with summary of reasons why fast replication is ineligible for this processing when applicable.

## **Example**

```
ADR918I (ttt)-mmmmm(yy), FAST REPLICATION COULD NOT BE USED FOR VOLUME SRCV01, RETURN CODE 3

VOLUME SRCV01 WAS REJECTED FOR QFRVOLS VOLUME REASON CODE 7 - VERSION 1 FC RELATION EXISTS
```

In this example, the DEBUG(FRMSG(DETAILED)) keyword provides the same level of informational message as when you specify the DEBUG(FRMSG(SUMMARIZED)) keyword.

# **DYNALLOC**



DYNALLOC specifies dynamic allocation, instead of enqueue, to serialize the use of data sets. The data sets whose extents are relocated are serialized throughout the DEFRAG operation. This allows cross-system serialization with the following considerations:

- The serialization is of value only when the dynamic allocation/JES3 interface is not disabled.
- Run time increases when you use the DYNALLOC keyword to serialize data sets (as opposed to enqueue) because overhead is involved in dynamic allocation and serialization across multiple processors.
- If you are running on a system using JES3 with MDS enabled and are not using multisystem GRS (or an equivalent function), you can use the DEFRAG command DYNALLOC keyword to provide serialization for data sets on shared DASD. However, not all data sets allocated within a JES3 environment are known to the global. The following are two cases where the use of the DYNALLOC keyword does not provide cross-system serialization for these data sets:
  - Allocation of existing (old) data sets whose names appear in the RESDSN and DYNALDSN lists are *not* protected by the DYNALLOC serialization

- mechanism of DFSMSdss. You can prevent DEFRAG processing for these data sets by placing their names (or filters for the names) in the EXCLUDE list for the DEFRAG command.
- New data sets created with nonspecific allocation (no volume serial supplied) are not protected by the DYNALLOC serialization mechanism of DFSMSdss. However, you can use BY filtering with the DEFRAG command to specifically include or exclude data sets from processing.

## **DYNAM**




DYNAM specifies that the volume to be processed is to be dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*).

Using the DYNAM keyword instead of DD statements to allocate DASD volumes does not appreciably increase run time and permits easier coding of JCL and command input.

volser Specifies the volume serial number of a DASD volume to be processed.

unit Specifies the device type of a DASD volume to be processed. This parameter is optional.

### **EXCLUDE**



## LIST(dsn)


Specifies a fully or partially qualified name of a data set to be excluded from the DEFRAG operation. You can specify either a cluster or component name for VSAM data sets.

### DDNAME(ddn)

Specifies the name of the DD statement that identifies a sequential data set or member of a partitioned data set, which contains the list of data sets to be excluded.

For additional information about specific types of data sets that must be placed in the EXCLUDE list if they are present on the volume being defragmented, see the "Data sets excluded from DEFRAG or CONSOLIDATE processing" on page 158.

#### **FASTREPLICATION**




FASTREPLICATION specifies whether the use of fast replication is preferred, required, or not desired. This keyword applies to fast replication methods such as FlashCopy and SnapShot.

PREFERRED specifies that you want to use a fast replication method, if possible. If fast replication cannot be used, DFSMSdss completes the operation using traditional data movement methods. PREFERRED is the default (unless changed to NONE by the installation).

REQUIRED specifies that fast replication must be used. If fast replication cannot be used, DFSMSdss fails the operation. DFSMSdss issues an informational message regarding why a fast replication method cannot be used even if the DEBUG(FRMSG(MIN|SUM|DTL)) keyword is not specified.

NONE specifies that DFSMSdss not use fast replication methods for the operation. Instead, DFSMSdss uses traditional data movement methods to complete the operation.

# **FCTOPPRCPrimary**



FCTOPPRCPrimary specifies that if FlashCopy is used to perform the copy operation, a Peer-toPeer Remote Copy (PPRC) primary volume is allowed to become a FlashCopy target volume. Use the following sub-keywords to specify whether the device pair is allowed to go to duplex pending state if the target volume of the FlashCopy operation is a metro mirror primary device:

### **PRESMIRREQ**

specifies that if the target volume is a Metro Mirror primary device, the pair must not go into a duplex pending state as the result of a FlashCopy operations.

# **PRESMIRPREF**

specifies that if the target volume is a Metro Mirror primary device, it would be preferable that the pair does not go into a duplex pending state as the result of a FlashCopy operation. However, if a Preserve Mirror operation cannot be accomplished, the FlashCopy operation is still to be performed.

#### **PRESMIRNONE**

specifies that Preserve Mirror operation is not to be done, even if all of the configuration requirements for a Preserve Mirror operation are met. If the target specified is a Metro Mirror primary device, the pair is to go into a duplex pending state while the secondary device is updated with the tracks to be copied. PRESMIRNONE is the default if you specify FCTOPPRCPrimary without a subkeyword.

Attention: When you specify FCTOPPRCPrimary or FCTOPPRCPrimary(PRESMIRNONE), the FlashCopy operation causes a PPRC primary volume to become a FlashCopy target volume. A Metro Mirror or Global Copy pair currently in full duplex state, goes into a duplex pending state when the FlashCopy relationship is established. When Metro Mirror or Global Copy completes the copy operation, the Metro Mirror or Global Copy pair goes to full duplex state. To prevent Metro Mirror or Global Copy pairs from going to duplex pending state during FlashCopy operation, you must specify FCTOPPRCPrimary(PRESMIRREQ).

For more information on PPRC options and volume states see: z/OS DFSMS Advanced Copy Services.

#### Note:

- 1. Using FCTOPPRCPRIMARY might require RACF authorization.
- 2. Do not specify the FCTOPPRCPrimary keyword with the FASTREPLICATION(NONE) keyword.
- 3. When FlashCopy is not used to perform the defrag operation, the FCTOPPRCPrimary keyword is ignored.
- 4. When FCTOPPRCPrimary is not specified or if the capability is not supported by the ESS, a PPRC primary volume is not eligible to become a FlashCopy target volume.

For additional information about RACF authorization see, Chapter 5, "Protecting DFSMSdss functions," on page 27.

For additional information about RACF FACILITY class profiles see, "Protecting DFSMSdss functions with RACF FACILITY class profiles" on page 29.

For additional information about PPRC (PPRC-SYNC), PPRC-XD, and PPRC V2 see: z/OS DFSMS Advanced Copy Services and IBM Redbook TotalStorage Enterprise Storage Server Implementing ESS Copy Services.

### **FORCECP**



FORCECP specifies that extents of checkpointed data sets resident on the SMS volume or volumes can be moved. The checkpoint indication is left in place for IMS<sup>177</sup> generalized sequential access method (GSAM) data sets, as the data set is still usable for a restart. The checkpoint indication is removed from all volumes for MVS checkpointed data sets, as the data sets are no longer usable for a restart.

Specifies a one-to-three digit number in the range of zero to 255. It also days specifies the number of days that must have elapsed since the last referenced date before the data set can be defragmented.


### **FRAGMENTATIONINDEX**



FRAGMENTATIONINDEX specifies that the DEFRAG operation is to end if the fragmentation index is less than n, where n is a 1- to 3-digit number. DFSMSdss prefixes your number, n, with a decimal point. For example, 1 becomes .1, .999 becomes .999, .001 becomes .001, and so forth.

For additional information about the fragmentation index of a volume, see "DEFRAG options" on page 159.

### **MAXMOVE**



- Specifies a 1- to- 6 digit number that specifies that DFSMSdss is to attempt to assemble up to n free tracks in a contiguous area. If n is greater than the total number of free tracks on the volume, for example MAXMOVE(999999), a message is issued and the DEFRAG operation adjusts n to the number of free tracks.
- Specifies a 1- to- 2 digit number that specifies that DFSMSdss is to make up to p passes in attempting to assemble the tracks. If p is not specified, for example MAXMOVE(99), only one pass is made, that is, MAXMOVE(99,1).

## **PASSDelay**

specifies the time delay between the passes (p) specified in MAXMOVE (n,p). PASSDELAY is only meaningful if (p) is greater than one.

nnnn Specifies a 1- to- 4 digit number from 0 to 9999 that specifies the time delay in milliseconds (1/1000 of a second). When MAXMOVE (n,p) is specified and PASSDELAY is not specified, a default PASSDELAY value of 999 (almost a second) is used to allow access to the volume between MAXMOVE passes.

DEFRAG processing attempts to move a fraction of the total free tracks during each pass. DEFRAG processing calculates an integer limit that is the larger of n divided by p or the value of 15. The limit is compared to the cumulative number of tracks moved after each extent is moved. If the limit is reached or exceeded, the current pass ends, and a new pass starts. Between each pass, the DEFRAG function releases and re-obtains volume serialization. This action reduces the overall time that a DEFRAG operation makes a volume unavailable to other applications.

The DEFRAG operation may end before completing p passes. If the DEFRAG operation cannot assemble n contiguous free tracks without moving more than n tracks, DFSMSdss issues a message and ends the DEFRAG operation. If n contiguous free tracks exist, the DEFRAG operation still attempts to reduce the fragmentation of the volume if it can do so without relocating more than n tracks.

The operation or the current pass also ends when DEFRAG processing criteria (for example, FRAGI) are satisfied. If you specified more than one pass, only the current pass ends. DFSMSdss issues message ADR233W for the current pass when the FRAGI criteria has been met. The DEFRAG function continues to run and attempts to complete the specified number of passes. DFSMSdss issues message ADR233W for each pass that meets the FRAGI criteria. The function continues

because activity on the volume between the DEFRAG passes may change the fragmentation index and the subsequent DEFRAG passes may further reduce the fragmentation of the volume.

In order to re-obtain volume serialization between DEFRAG passes, DFSMSdss uses a default value of WAIT(3,30). This means that DFSMSdss is to retry the volume serialization 30 times at 3 second intervals for a total wait time of 90 seconds. The DEFRAG operation issues a message and ends if DFSMSdss cannot obtain volume serialization; any remaining passes do not run. "The WAIT option" on page 563 explains how to change the wait/retry values for the volume serialization if the default is not satisfactory.

If MAXMOVE is not specified, DFSMSdss tries to assemble a contiguous free area of a size equal to the total number of free tracks on the volume in a single pass. The DEFRAG function uses two methods to assemble free tracks on the volume. The first method attempts to assemble the largest contiguous amount of free space with a minimum amount of data movement. The second method attempts to assemble multiple groups of large areas of contiguous free space and generally moves more data around than the first method. When MAXMOVE is specified, only the first method is used during each pass.

#### Note:

- 1. The MMOVPCT keyword is recommended instead of MAXMOVE when running DEFRAG on an EAV. The MMOVPCT will apply separately to the track-managed space and the cylinder-managed space.
- 2. MAXMOVE and MMOVPCT are mutually exclusive.

# **MAXTIME**

Specifies the maximum time, in minutes, for the DEFRAG operation to complete. MAXTIME is checked after each data set is processed. When the MAXTIME value is reached, the DEFRAG operation ends.

# **MAXTIME**




#### nummins

Specifies the maximum number of minutes (0-9999 in decimal) a DEFRAG operation can run. A value of 0 is ignored.

### Note:

- 1. The actual elapsed time of the DEFRAG operation might be slightly longer than the MAXTIME value; this value is checked only after each data set is processed.
- 2. The CONSOLIDATE and the MAXTIME keywords are mutually exclusive. If you specify the CONSOLIDATE keyword when MAXIME is specified, the DEFRAG command terminates and DFSMS issues syntax error message ADR139E.

# **MMOVPCT**



- n This 1- to 3-digit number specifies that DFSMSdss is to attempt to assemble up to n% of tracks as free tracks in a contiguous area. If n% is greater than the total number of free tracks available to the task, the DEFRAG operation resets this value to the number of free tracks available to the task.
- *p* This 1- or 2-digit number specifies that DFSMSdss is to make up to *p* passes in attempting to assemble the tracks. If *p* is not specified, only one pass is made.

### **PASSDelay**

Specifies the time delay between the passes (p) specified in MMOVPCT(p,n). PASSDELAY is meaningful only if (p) is greater than one.

*nnnn* This 1- to 4-digit number specifies the time delay in milliseconds (1/1000 of a second). When MMOVPCT (n,p) is specified and PASSDELAY is not specified, a default PASSDELAY value of 999 (almost a second) is used to allow access to the volume between MMOVPCT passes.

DEFRAG processing attempts to move a fraction of the free tracks during each pass. It calculates an integer limit that is the larger of n% of tracks divided by p or the value of 15. The limit is compared to the cumulative number of tracks moved after each extent is moved. If the limit is reached or exceeded, the current pass ends, and a new pass starts. Between each pass, the DEFRAG function releases and re-obtains volume serialization. This action can reduce the overall time in which a DEFRAG operation makes a volume unavailable to other applications.

The DEFRAG operation might end before completing p passes. If the DEFRAG operation cannot assemble n% contiguous tracks as free without moving more than n% tracks, DFSMSdss issues a message and ends the DEFRAG operation. If n% contiguous free tracks exist, the DEFRAG operation continues to reduce the fragmentation of the volume, if it can do so without relocating more than n% tracks.

The operation or the current pass also ends when DEFRAG processing criteria (for example, FRAGI) are satisfied. If you specify more than one pass, only the current pass ends. DFSMSdss issues message ADR233W for the current pass when the FRAGI criteria has been met. The DEFRAG function continues to run and attempts to complete the specified number of passes. DFSMSdss issues message ADR233W for each pass that meets the FRAGI criteria. The function continues because activity on the volume between the DEFRAG passes might change the fragmentation index and the subsequent DEFRAG passes might further reduce the fragmentation of the volume.

To restore volume serialization between DEFRAG passes, DFSMSdss uses a default value of WAIT(3,30). This means that DFSMSdss is to retry the volume serialization 30 times at 3 second intervals for a total wait time of 90 seconds. The DEFRAG operation issues a message and ends if DFSMSdss cannot obtain volume

serialization; any remaining passes do not run. "The WAIT option" on page 563 explains how to change the wait and retry values if the defaults are not suitable for your installation.

If you do not specify MMOVPCT, DFSMSdss attempts to assemble a contiguous free area of a size equal to the total number of free tracks on the volume in a single pass. The DEFRAG function uses two methods to assemble free tracks on the volume. The first method attempts to assemble the largest contiguous amount of free space with a minimum amount of data movement. The second method attempts to assemble multiple groups of large areas of contiguous free space and generally moves more data than the first method. If you specify MMOVPCT, only the first method is used during each pass.


#### Note:

- 1. Use MMOVPCT, rather than MAXMOVE, when running DEFRAG on an extended address volume. The MMOVPCT value applies separately to the track-managed space and the cylinder-managed space.
- 2. MMOVPCT and MAXMOVE are mutually exclusive.
- 3. MMOVPCT and VERSION1 are mutually exclusive.

### **PASSDELAY**

See "MAXMOVE" on page 383 or "MMOVPCT" on page 385.

# PASSWORD



PASSWORD specifies the passwords that DFSMSdss is to use for password-protected data sets. (Password checking is bypassed for RACF-protected data sets.) This keyword must be specified when:

- You do not have the required RACF DASDVOL or RACF DATASET access.
- The installation authorization exit does not bypass the checks.
- You do not want to be prompted for the password for VSAM data sets.

Note: You should specify the passwords for all data sets that do not have RACF protection but do have password protection. During processing, a utility invoked by DFSMSdss may have to prompt the operator for a password. You can control authorization checking by using the installation authorization exit.

For VSAM data sets, password checking is done only at the cluster level.

ddn Specifies the name of the DD statement that identifies the sequential data set, or member of a partitioned data set that contains data set names and their passwords. This data set must contain card-image records in DFSMSdss command syntax format.

dsn/pswd

dsn is a fully qualified data set name. pswd is its password. If no password follows the slash (/), dsn is treated as though it were ddn.

Printing of actual data set passwords specified in the input command stream is suppressed in the SYSPRINT output.

# **VERSION1**


VERSION1 indicates that DFSMSdss is to use the DEFRAG command available with earlier releases of z/OS. DEFRAG with VERSION1 specified can support only volumes of 65,520 or fewer cylinders.

### **VERSION1**



**Note:** VERSION1 is mutually exclusive with the MAXTIME and MMOVPCT keywords.

# WAIT



WAIT specifies to the length of a wait in seconds and the number of retries to obtain control of a data set.

#### numsecs

Specifies a decimal number from 1 to 255 that specifies the interval, in seconds, between retries.

#### numretries

Specifies a decimal number (0–99) that specifies the number of times an attempt to gain control of a data set is to be retried.

The default for *numsecs,numretries* is (2,2), which specifies two retries at 2-second intervals. If you do not want to wait for a data set, specify 0 for either numsecs or numretries.

**Note:** The WAIT keyword does not control wait/retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is 3 seconds and the default retry count is 30. This results in a total wait time of 90 seconds.

For additional information about controlling the wait/retry attempts for system resources, see "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

#### WRITECHECK



WRITECHECK specifies that the data moved by the DEFRAG operation is to be verified for successful completion. This keyword increases the overall elapsed time.

# **Examples of DEFRAG operations**

# Example 1: a DEFRAG operation with excluded data sets

```
//JOB1 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//DASD DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//A1 DD DSN=USER2.EXCLUDE, DISP=SHR
//SYSIN DD *
command input
/*
```

See command input in "Example 1A: with the names of excluded data sets in the input stream" and "Example 1B: with the names of excluded data sets in a data set."

# Example 1A: with the names of excluded data sets in the input stream

```
DEFRAG DDNAME(DASD) -
EXCLUDE(LIST(USER2.**.LIST,*.LOAD))
```

# Example 1B: with the names of excluded data sets in a data set

```
DEFRAG DDNAME(DASD) -
EXCLUDE(DDNAME(A1))
```

In examples 1A and 1B, DASD volume 111111 is defragmented. All data sets whose first and last qualifiers are USER2 and LIST, respectively, are to be excluded from this operation, as are data sets with two qualifiers whose second qualifier is LOAD. In example 1B, cataloged data set USER2.EXCLUDE contains a single card-image record with the following in columns 2 through 72:

```
USER2.**.LIST,*.LOAD
```

# Example 2: a DEFRAG operation using a BY criterion

```
//JOB2 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//DASD DD UNIT=3380,VOL=(PRIVATE,SER=111111),DISP=OLD
//SYSIN DD *
DEFRAG DDNAME(DASD) /* VOLUME TO BE PROCESSED */-
BY(LIST(REFDT LT *,-1)) /* DATE LAST REF LT RUN DATE -1 */
/*
```

In Example 2, only data sets that were last referenced more than one day before the run date are included in the DEFRAG operation. That is, those that were last referenced one day before or on the run date are excluded.

# Results of a successful DEFRAG operation

Figure 16 on page 390 is the printout from a DEFRAG run for a DASD volume. It gives an indication of the free space fragmentation before and after a DEFRAG operation, as well as the distribution of data set extents by size.

The following JCL was used for this job:

```
//STEPT010 EXEC PGM=ADRDSSU,PARM='RACFLOG=YES,TRACE=YES'
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
DEFRAG DYNAM(D9S060)
/*
```

```
PAGE 0001
              5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                                  1999.211 14:55
  DEFRAG
    DYNAM(D9S060)
ADR101I (R/I)-RI01 (01), TASKID 001 HAS BEEN ASSIGNED TO COMMAND 'DEFRAG '
ADR109I (R/I)-RI01 (01), 1999.211 14:55:33 INITIAL SCAN OF USER CONTROL
                         STATEMENTS COMPLETED.
ADR016I (001)-PRIME(01), RACF LOGGING OPTION IN EFFECT FOR THIS TASK
ADR006I (001)-STEND(01), 1999.211 14:55:33 EXECUTION BEGINS
ADR208I (001)-EANAL(01), 1999.211 14:55:34 BEGINNING STATISTICS ON D9S060:
                          FREE CYLINDERS
                                                             000058
                          FREE TRACKS
                                                              000003
                          FRFF FXTFNTS
                                                             000002
                          LARGEST FREE EXTENT (CYL, TRK) 000053,0003
                          FRAGMENTATION INDEX
                                                              0.050
                          PERCENT FREE SPACE
                                                                  97
ADR220I (001)-EANAL(01), INTERVAL BEGINS AT CC:HH 00001:0000 AND ENDS AT
                         CC:HH 00006:000C
ADR209I (001)-EFRAG(01), 1999.211 14:55:34 MOVED EXTENT 001 FROM
                         00006:0000-00006:0004 TO 00001:0000-00001:0004
                         FOR PUBSEXMP.ESDS.S01.DATA
ADR209I (001)-EFRAG(01), 1999.211 14:55:34 MOVED EXTENT 001 FROM
                         00006:0005-00006:0006 TO 00001:0005-00001:0006
                         FOR PUBSEXMP.KSDS.S01.DATA
ADR209I (001)-EFRAG(01), 1999.211 14:55:35 MOVED EXTENT 001 FROM
                         00006:0007-00006:0008 TO 00001:0007-00001:0008
                         FOR PUBSEXMP.SAM.S01
ADR209I (001)-EFRAG(01), 1999.211 14:55:35 MOVED EXTENT 001 FROM
                         00006:0009-00006:000A TO 00001:0009-00001:000A
                         FOR PUBSEXMP.PDS.S01
ADR209I (001)-EFRAG(01), 1999.211 14:55:35 MOVED EXTENT 002 FROM
                         00006:000B-00006:000B TO 00001:000B-00001:000B
                         FOR PUBSEXMP.PDS.S01
ADR213I (001)-EANAL(01), 1999.211 14:55:35 ENDING STATISTICS ON D9S060:
                          DATA SET EXTENTS RELOCATED
                                                             000005
                                                              000012
                          TRACKS RELOCATED
                          FREE CYLINDERS
                                                              000058
                          FREE TRACKS
                                                             000003
                          FREE EXTENTS
                                                              000001
                          LARGEST FREE EXTENT (CYL, TRK) 000058,0003
                          FRAGMENTATION INDEX
                                                              0.000
              5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
PAGE 0002
                                                               1999.211 14:55
ADR212I (001)-EANAL(01), EXTENT DISTRIBUTION MAP FOR D9S060:
                   EXTENT *FREE SPACE BEFORE* *FREE SPACE AFTER* *ALLOCATED *
                    SIZE
                      ΙN
                             NO.
                                   CUM.
                                            NO.
                                                  CUM.
                                                            NO.
                                                                   CUM.
                   TRACKS
                            EXTS PCT/100 EXTS PCT/100
                                                                  PCT/100
                                                           FXTS
                       1
                                                             4
                                                                  0.148
                       2
                                                             4
                                                                  0.444
                       5
                                                             1
                                                                  0.629
                      10
                                                                  1.000
                                  0.085
                      75
                              1
                    >499
                              1
                                  1.000
ADR006I (001)-STEND(02), 1999.211 14:55:35 EXECUTION ENDS
ADR013I (001)-CLTSK(01), 1999.211 14:55:35 TASK COMPLETED WITH RETURN CODE 0000
ADRO12I (SCH)-DSSU (01), 1999.211 14:55:35 DFSMSDSS PROCESSING COMPLETE. HIGHEST
                   RETURN CODE IS 0000
```

Figure 16. Printed Output Resulting from a Successful DEFRAG Run on nonEAV:

**Note:** The following section of the printed output resulting from a successful DEFRAG run changes for EAV to include two columns: first column refers to the entire volume, the second column refers to the cylinder-managed space, as follows:

```
ADR213I (001)-DFANL(01), 2007.226 12:50:17 ENDING STATISTICS ON C9NS05:
                         *STATISTICS*
                                                      *VOLUME*
                                                                   *TRKAREA*
                         DATA SET EXTENTS RELOCATED 00000037
                                                                   00000033
                         TRACKS RELOCATED
                                                       00003212
                                                                   00001007
                         FREE CYLINDERS
                                                       00086950
                                                                   00065236
                         FREE TRACKS
                                                       00000022
                                                                   00000022
                         FREE EXTENTS
                                                       00000005
                                                                   00000004
                         LARGEST FREE EXTENT (CYL, TRK) 00063426.03 00063426.03
                         FRAGMENTATION INDEX
                                                       0.050
                                                                   0.010
```

Figure 17. A Section of the Printed Output Resulting from a Successful DEFRAG Run on EAV:

The value in the first column of message ADR212I is the size of the extent in tracks (free space or data set) and is printed only if an extent of that size occurs. The second and third columns show the number of free space extents existing *before* processing that were of the size shown in the first column, along with their cumulative percentage divided by 100. The fourth and fifth columns give the same information for free space, but *after* processing. The sixth and seventh columns give the distribution of allocated data set extents, which do not change during a run.

# **DUMP command for DFSMSdss**

With the DUMP command, you can dump DASD data to a basic sequential data set, a large format sequential data set or an extended format sequential data set. The storage medium for a basic sequential data set can be a tape or DASD. The storage medium for the large format or extended format sequential data set must be DASD. You can dump data sets, an entire volume, or ranges of tracks.

**Note:** The FULL keyword for the DUMP command specifies that an entire DASD volume is to be dumped. The TRACKS keyword with the DUMP command specifies ranges of tracks to be dumped.

DFSMSdss offers two ways to process DUMP commands:

- Logical processing is data set-oriented, which means it operates against data sets independently of physical device format.
- *Physical processing* can operate against data sets, volumes, and tracks, but is oriented toward moving data at the track-image level.

The processing method is determined by the keywords specified on the command.

DFSMSdss logical dump processing cannot be used to process partitioned data sets containing location-dependent information that does not reside in note lists or in the directory. Furthermore, DFSMSdss cannot be used to dump migrated data sets.

Integrated catalog facility catalogs should not have a high-level qualifier of SYSCTLG because this causes DFSMSdss to treat them as CVOLs.

For more information about using the DUMP command, see Chapter 6, "Managing availability with DFSMSdss," on page 33.

# Special considerations for dump

The following special considerations apply when you are performing a dump operation:


- A logical data set dump cannot be performed on the following data sets:
  - VSAM data sets not cataloged in an integrated catalog facility catalog
  - Page, swap, and SYS1.STGINDEX data sets

- VSAM Volume Data Sets (VVDS)
- Partitioned data sets containing location-dependent information that does not reside in note lists or in the directory
- A physical data set dump cannot be performed on the following data sets:
  - KSDSs with key ranges. Use logical processing for this type of data set.
  - VSAM data sets not cataloged in an integrated catalog facility catalog.
  - Page, swap, and SYS1.STGINDEX data sets.


Note: DFSMSdss cannot be used to dump data sets with a volume serial of MIGRAT. The recommended method of dumping migrated data sets is ABARS.


For more information about dumping data sets, see z/OS DFSMSdss Storage Administration.

# **DUMP FULL and DUMP TRACKS syntax**




# A: Optional Keywords with DUMP FULL:





# **B: Optional Keywords with DUMP TRACKS:**







# **Notes:**

You cannot specify the FCWITHDRAW keyword with the CONCURRENT(ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ ) or RESET keywords at the same time.


# **DUMP DATASET syntax for logical data set**




# C: Additional Keywords with DUMP DATASET for Logical Data Set:



# D: Optional Keywords with DUMP DATASET for Logical Data Set:



# **DUMP Command**





# **Notes:**

You cannot specify the FCWITHDRAW keyword with the CONCURRENT(ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ) or RESET keywords at the same time.


2 You cannot specify the STORGRP keyword with the INDDNAME, INDYNAM, LOGINDDNAME or LOGINDYNAM keywords at the same time.

# **DUMP DATASET syntax for physical data set**







# E: Additional Keywords with DUMP DATASET for Physical Data Set:



# F: Optional Keywords with DUMP DATASET for Physical Data Sets:



# **DUMP Command**



#### Notes:

You cannot specify the FCWITHDRAW keyword with the CONCURRENT(ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ) or RESET keywords at the same time.

# **Explanation of DUMP command keywords**

This section describes the keywords for the DUMP command.

### **ADMINISTRATOR**



ADMINISTRATOR lets you act as a DFSMSdss-authorized storage administrator for the DUMP command. If you are not authorized to use the ADMINISTRATOR keyword, the command is ended with an error message. Otherwise, access checking to data sets and catalogs that are initiated by DFSMSdss are bypassed.

To use the ADMINISTRATOR keyword all of the following must be true:

- FACILITY class is active
- · Applicable FACILITY-class profile is defined
- You have READ access to that profile.

For more information about how to use the ADMINISTRATOR keyword, see "ADMINISTRATOR keyword" on page 541.

### **ALLDATA**



ALLDATA applies to full and data set dump operations.

dsn Specifies the fully qualified name of a data set whose data set organization is PS, PSU, PO, POU, or null, for which all allocated space is to be dumped.

# \* (asterisk)

Specifies that all allocated space is to be dumped for the following data sets:

- All sequential and partitioned data sets that are not empty, and
- Data sets whose data set organization is null and are not empty. (The last used block pointer in the data set's volume table of contents (VTOC) entry is not zero.)

### Note:

1. Data beyond the last used block pointer is not retained when ALLDATA or ALLEXCP is specified for an extended-format sequential data set during a logical dump operation. During a subsequent restore operation, the target data set is allocated with the same amount of space as the source data set.

# **DUMP Command**

- 2. All of the allocated space is always dumped for a physical dump of PDSE and HFS data sets.
- 3. For a logical dump of PDSE or HFS data sets, the following conditions are true:
  - If DFSMSdss can determine the amount of used space, DFSMSdss dumps only the used space, regardless of the ALLDATA keyword.
  - If you specify ALLDATA, DFSMSdss remembers the amount of allocated space. During a subsequent restore operation, DFSMSdss will allocate the target data set with the same amount of space as the source data set.
  - If DFSMSdss cannot determine the amount of used space, it assumes that the used space is equal to the allocated space. DFSMSdss then dumps all of the allocated space.

## **ALLEXCP**



ALLEXCP is an option for full and data set dump operations. It instructs DFSMSdss to dump all allocated space for data sets whose data set organization is PS, PSU, PO, POU, or null and are empty (the last used block pointer in the data set's VTOC entry is zero).

**Note:** Using the ALLEXCP keyword will result in all the allocated space being dumped for applicable data sets. However, whether or not all the allocated space is restored depends on data set characteristics and device characteristics during the restore. If you require that all of the unused space is restored, then you should be sure that the data set is restored to a like device type and not reblocked or compressed. Compress is the default for PDS data sets on restore unless you use the NOPACKING keyword.

# BY



BY specifies that the data sets selected up to this point by the processing of the INCLUDE and EXCLUDE keywords are to be further filtered. To select the data set, *all* BY criteria must be met. See "Filtering by data set characteristics" on page 262 for a full discussion of *schar*, *op*, and *arg*. See the separate discussions of INCLUDE and EXCLUDE for information on how these keywords are specified.

**Note:** You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

### CANCELERROR




CANCELERROR specifies that the dump operation is to be ended if a track-related permanent read error occurs. If this keyword is *not* specified and a permanent read error occurs, the track image record is flagged on the output volume as having an I/O error, and the dump operation continues. This track is not restored in a restore operation. When CANCELERROR is specified, the TOLERATE(IOERROR) keyword is ignored.

This keyword may be used in conjunction with the CHECKVTOC keyword to specify whether or not an operation is to continue in the event of terminating VTOC errors discovered during VTOC checking. Refer to the CHECKVTOC keyword.

**Note:** CANCELERROR has no effect on the following types of errors on a DASD volume:

- Equipment check
- · Command reject
- Intervention required
- Busout parity

## CHECKVTOC



CHECKVTOC specifies that a VTOC analysis of the source volume be performed during dump processing. In the event of terminating VTOC errors found during analysis, operation continues unless the CANcelerror keyword is specified. CHECKVTOC is ignored if CPVOLUME is also specified.

# **CICSVRBACKUP**



CICSVRBACKUP specifies that for a logical data set dump operation, DFSMSdss creates backups for use by CICSVR. DFSMSdss notifies the CICSVR server address space when a CICSVR backup is made for a VSAM base cluster. This enables CICSVR to manage backups made by DFSMSdss.

#### Note:

- 1. CICSVRBACKUP is intended to be used in conjunction with CICSVR. The minimum required CICSVR release is Version 3 Release 1. To use CICSVRBACKUP, the CICSVR server address space must be active.
- 2. CICSVRBACKUP applies to a logical data set dump only.
- 3. CICSVR manages VSAM base clusters backed up using the DFSMSdss DUMP command. The CICSVRBACKUP keyword is ignored for non-VSAM data sets and VSAM alternate indexes. When you specify CICSVRBACKUP, DFSMSdss DUMP processes AIXs as usual but does not notify CICSVR of backups that are made for AIXs.

# **COMPRESS**




COMPRESS specifies that the dumped data is to be written in compressed form to the output medium. This decreases the space occupied by the dump data at the expense of increased processor and elapsed times.

### Note:

- 1. The COMPRESS keyword is ignored if it is specified during a logical data set dump for either compressed-format sequential data sets or compressed-format VSAM data sets.
- 2. If you have a tape drive with the compaction feature and you want to use hardware data compaction, you do not need to specify the COMPRESS keyword. If software data compression is desired, you do not need to specify DCB=TRTCH=COMP in the JCL. However, you may specify both the COMPRESS keyword and DCB=TRTCH=COMP.
- 3. If you want to use compressed format sequential data sets on DASD, you do not need to specify the COMPRESS keyword. To obtain software data compression, you do not need to use a compressed format sequential data set on DASD. However, you may specify both the COMPRESS keyword and a data class on the output DD that requests compressed format sequential data sets.
- 4. To improve performance and save dump space, specify the OPTIMIZE keyword with the COMPRESS keyword.

# CONCURRENT



The CONCURRENT keyword specifies that the data is to be processed with concurrent copy. You can specify one of the following optional sub-keywords to indicate the type of concurrent copy to be used and whether DFSMSdss can use other methods of data movement when concurrent copy cannot be used or fails:

### ANYPREFERRED or PREFERRED

Specifies that data is to be processed with concurrent copy. Virtual concurrent copy is attempted first, if the storage subsystem on which the data resides is capable of it and working-space data sets have been

defined. Otherwise, cache-based concurrent copy is attempted if the storage subsystem is capable of it. If neither type of concurrent copy is possible or both fail, the data is processed with standard I/O. PREFERRED is the default if you specify the CONCURRENT keyword without a sub-keyword.

# ANYREQUIRED or REQUIRED

Specifies that data is to be processed with concurrent copy. Virtual concurrent copy is attempted first, if the storage subsystem on which the data resides is capable of it and working-space data sets have been defined. Otherwise, cache-based concurrent copy is attempted, if the storage subsystem is capable of it. If neither type of concurrent copy is possible or both fail, the data is not processed.

# **CACHEPREFERRED**

Specifies that data is to be processed with cache-based concurrent copy. If cache-based concurrent copy cannot be used or fails, the data is processed with standard I/O. DFSMSdss does not attempt to use virtual concurrent copy.

# **CACHEREQUIRED**

Specifies that data is to be processed with cache-based concurrent copy. If cache-based concurrent copy cannot be used or fails, the data is not processed. DFSMSdss does not attempt to use virtual concurrent copy or standard I/O.

### STANDARD or NONE

Specifies that data is to be processed with standard I/O as if the CONCURRENT keyword was not specified.

### **VIRTUALPREFERRED**

Specifies that data is to be processed with virtual concurrent copy. If virtual concurrent copy cannot be used or fails, the data is processed with standard I/O. DFSMSdss does not attempt to use cache-based concurrent copy.

#### VIRTUALREQUIRED

Specifies that data is to be processed with virtual concurrent copy. If virtual concurrent copy cannot be used or fails, the data is not processed. DFSMSdss does not attempt to use cache-based concurrent copy or standard I/O.

For a logical data set dump operation, you can also specify the NOTIFYCONCURRENT keyword, as follows:

# **NOTIFYCONCURRENT**

Specifies that DFSMSdss is to issue an informational message for each data set that is successfully included in the concurrent copy operation. If you do not specify NOTIFYCONCURRENT, DFSMSdss issues messages only for data sets that are not included in the concurrent copy operation.

#### Note:

- 1. Do not specify NOTIFYCONCURRENT with CONCURRENT(STANDARD | NONE).
- 2. You cannot use CONCURRENT(ANYPREF | ANYREQ | CACHEPREF | CACHEREQ | VIRTUALPREF | VIRTUALREQ) with the DELETE, UNCATALOG, or FCWITHDRAW keywords.

### **DUMP Command**

- 3. The RESET keyword is ignored if you specify CONCURRENT(ANYPREF | ANYREO | CACHEPREF | CACHEREO | VIRTUALPREF | VIRTUALREO), unless you apply a patch to allow the reset function.
- 4. The use of concurrent copy and virtual concurrent copy with the DFSMSdss DUMP command is controlled by the RACF FACILITY class profile, STGADMIN.ADR.DUMP.CNCURRNT.

For information about determining concurrent copy storage requirements and about virtual concurrent copy, see "Performance considerations" on page 55. For more information about working space data sets, see z/OS DFSMS Advanced Copy Services.

# **CPVOLUME**



CPVOLUME specifies that the input volume is a VM-format volume and that the OS-compatible VTOC must begin on track zero, record five. You must specify the track range to be copied with the TRACKS keyword, as the OS-compatible VTOCs do not describe the extents of any data on the volume. You must also specify the ADMINISTRATOR keyword with CPVOLUME because DFSMSdss cannot check access authorization for VM data.


### DATASET



DATASET specifies a data set dump operation, using filtering. See Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259 for an explanation of the filtering process used. Unless the ALLDATA or ALLEXCP keyword is specified, only used tracks are dumped for sequential and partitioned data sets and for data sets with no defined data set organization (for example, JES2/JES3 data sets). If the free space map in the VTOC is invalid, all tracks are dumped.

Note: Either the FILTERDD, INCLUDE, EXCLUDE, or BY keyword must be specified when DATASET is selected.

#### DELETE



For a physical data set dump, DELETE instructs DFSMSdss to delete expired single-volume, non-VSAM data sets that are successfully serialized and dumped. In addition, DFSMSdss is to uncatalog successfully deleted data sets. DELETE is ignored for VSAM data sets.

For a logical data set dump, DELETE can be used to delete expired single- and multivolume VSAM and non-VSAM data sets that are successfully serialized and dumped. Unmovable data sets can also be deleted. User catalogs cannot be deleted. *Unexpired* source data sets are deleted only if you also specify PURGE.

### Note:

- For both a *physical* and a *logical* data set dump operation, you cannot delete data sets with a high-level qualifier of SYS1 unless you specify PROCESS(SYS1). Even if PROCESS(SYS1) is specified, SYS1.VVDS and SYS1.VTOCIX data sets cannot be dumped and deleted. To delete or scratch a password-protected data set, the operator must supply the password for DADSM scratch password checking.
- 2. Do not specify SHARE if you specify DELETE.
- 3. Do not specify DELETE with CONCURRENT, because after the concurrent copy operation has begun, the original data can still be updated.
- 4. Do not specify DELETE for a mounted HFS data set. DFSMSdss can delete an HFS data set only if DFSMSdss can enqueue the data set exclusively. This is only possible if the data set is unmounted.
- 5. If the data set being processed is a generation data set (GDS), an exclusive enqueue on the GDG BASE is required in addition to the exclusive enqueue on the GDS.

# **DYNALLOC**



DYNALLOC specifies dynamic allocation, instead of enqueue, to serialize the use of data sets. This allows cross-system serialization in a JES3/MVS environment.

### Note:

- 1. The serialization is of value only when the dynamic allocation/JES3 interface is not disabled.
- 2. Run time increases when you use DYNALLOC to serialize data sets (as opposed to enqueue) because overhead is involved in dynamic allocation and serialization across multiple processors.
- 3. If a data set passes INCLUDE/EXCLUDE filtering and is migrated before BY filtering and DYNALLOC is used, the dynamic allocation causes the data set to be recalled. DFSMSdss waits for the recall processing to complete. If the data set is recalled to a different volume, a message is issued indicating that the VTOC entry was not found.
- 4. For an HFS data set, DFSMSdss ignores DYNALLOC and attempts to get a SYSZDSN enqueue. If DFSMSdss cannot enqueue the HFS data set, DFSMSdss attempts to quiesce the data set.

### **ENCRYPT**

ENCRYPT is a subparameter of the RSA and KEYPASSWORD keywords.

For more information, see "KEYPASSWORD" on page 410 and "RSA" on page 418.

# **EXCLUDE**



Specifies the name of a data set to be excluded from the data sets selected dsn by INCLUDE. Either a fully or a partially qualified data set name can be used.

Note: You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

For more information, see "BY" on page 400 and "INCLUDE" on page 409.

## **FCWITHDRAW**



#### Notes:

You cannot specify the FCWITHDRAW keyword with the CONCURRENT or RESET keywords at the same time.

FCWITHDRAW specifies that if the volume that is dumped is the target volume of a FlashCopy relationship, the relationship is withdrawn when the dump has successfully completed. Withdrawing the FlashCopy relationship releases the subsystem resources that maintain the FlashCopy relationship.

During DUMP FULL and DUMP TRACKS operations, DFSMSdss might invoke ICKDSF INITIALIZE to ensure that the source volume of the DUMP operation remains online to the system at the end of dump processing. If the VTOC tracks of a source volume that are part of the withdrawn FlashCopy relationship do not look like VTOC tracks, programs might not be able to process the volume. DFSMSdss invokes ICKDSF INITIALIZE only when all of the following conditions are true:

- FCWITHDRAW is specified
- The VTOC tracks on the source volume of the DUMP operation are the target of a FlashCopy relationship
- If TRACKS is specified, it designates one extent range that represents the entire
- The volume is not a VM-format volume (CP volume)
- The volume supports FlashCopy Version 2.

If the dumped volume is not FlashCopy capable, the FCWITHDRAW keyword is ignored.

#### Note:

1. When the FlashCopy relationship is withdrawn, the data on the volume that was dumped becomes invalid. Therefore, only use FCWITHDRAW if you no longer need the data on the volume that is dumped, after the dump has completed.

- 2. If you use the FCNOCOPY keyword, you must withdraw the FlashCopy relationship when the copy is no longer needed to free up the subsystem resources that maintain the FlashCopy relationship. You can withdraw the FlashCopy relationship by performing one of the following tasks:
  - Initiate a dump of the target of the copy and specify the FCWITHDRAW keyword on the DUMP command
  - Initiate the TSO FCWITHDR command.
- 3. The FCWITHDRAW keyword is not supported for devices that are attached at device address X'0000'. If you specify FCWITHDRAW for a volume attached at address X'0000', the system fails the FCWITHDRAW request with a warning message.

For information about the TSO FCWITHDR command, see *z/OS DFSMS Advanced Copy Services* 

Restrictions: For cases in which the FlashCopy target volume could not be initialized during FCWITHDRAW processing, using the FCNOCOPY keyword on the full volume copy and the FCWITHDRAW keyword on the full volume dump leaves the target volume (of the copy) in an indeterminate state. Some tracks on the volume might contain data from the source volume; other tracks might contain residual data from the target volume that existed before the copy. This indeterminate state can cause problems when accessing the target volume following the dump, if the VTOC locations of the source volumes and the target volumes are different before the copy.

## **FILTERDD**



FILTERDD specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set that contains the filtering criteria to use. The filtering criteria are in the form of card-image records, in DFSMSdss command syntax, containing the INCLUDE, EXCLUDE, and BY keywords that complete the DUMP command syntax.

**Note:** You must use FILTERDD when you have more than 255 entries in the INCLUDE, EXCLUDE, or BY list of subkeywords.

### **FORCECP**



FORCECP specifies that checkpoint data sets resident on the SMS volume or volumes can be logically dumped. Checkpoint indications are not removed from the data set during conversion.

days Specifies a one-to-three digit number in the range of zero to 255. It also specifies the number of days that must have elapsed since the last referenced date before the data set can be dumped.

# **FULL**



FULL specifies that an entire DASD volume is to be dumped. This is the default. Unallocated tracks are not dumped. Unless the ALLDATA or ALLEXCP keyword is specified, only used tracks are dumped for sequential and partitioned data sets and for data sets with no defined data set organization. (for example, JES2/JES3 data sets). If the free space map in the VTOC is invalid, all tracks are dumped. Used tracks consist of the tracks from the beginning of the data set to the last-used track (as indicated by the last used block pointer in the data set's VTOC entry).

**Note:** You cannot specify SHARE or TOL(ENQF) for FULL operations.

# **HWCOMPRESS**




HWCOMPRESS specifies that DFSMSdss writes the dumped data in compressed form to the output medium. This decreases the space occupied by the dump data. Hardware assisted compression is performed on the dumped data using the System z CMPSC instruction.

Logical Data Set DUMP: Data sets that are less than five tracks in size (used space or allocated space when ALLDATA is specified) are not compressed.

Physical Full Volume, Tracks, and Data Set DUMP: DFSMSdss rebuilds the compression dictionary after 15 consecutive compressions that do not have a new size of at most 94% the original size. The values 15, and 94% may be tuned with patch bytes as described in the DFSMSdss Storage Administration Guide.

Restriction: The HWCOMPRESS keyword cannot be specified with the COMPRESS keyword.

# **INCAT**



INCAT(catname) specifies that DFSMSdss search the user catalogs specified by the INCAT(catname) keyword, then follow the standard search order to locate data sets. INCAT allows you to identify specific source catalogs. To specify INCAT, RACF authorization may be required.

catname

Specifies a fully qualified catalog name.

## ONLYINCAT

Specifies that DFSMSdss only searches catalogs specified in the INCAT catalog name list.

DFSMSdss does not process an SMS-managed data set that is cataloged outside the standard search order. This is the case even if it is cataloged in one of the catalogs that is specified with the INCAT(catname) keyword. Ensure that the SMS-managed data sets are cataloged under standard catalog search order.

For more information about RACF authorization, see Chapter 5, "Protecting DFSMSdss functions," on page 27.

# **INCLUDE**



dsn Specifies the name of a data set eligible to be dumped. Either a fully or a partially qualified data set name can be used. See "Filtering by data set names" on page 260. If INCLUDE is omitted (but EXCLUDE or BY is specified) or if INCLUDE(\*\*) is specified, *all* data sets are eligible to be selected for dumping.

#### Note:

- 1. You must use FILTERDD when you have more than 255 entries in a list that is created using the INCLUDE, EXCLUDE, or BY keywords.
- 2. DFSMSdss does not support INCLUDE filtering of non-VSAM data sets using an alias.

For more information, see "BY" on page 400 and "EXCLUDE" on page 406.

## **INDDNAME**




ddn Specifies the name of the DD statement that identifies the input volume to be processed during FULL or TRACKS dump. To assure correct processing, each of the DD statements corresponding to a ddname (ddn) must identify only one volume serial number.

### Note:

- 1. Only one *ddn* can be specified for INDDname when you use a full or tracks dump operation. One or more are allowed for a physical data set dump operation.
- Specifying INDDNAME or INDYNAM results in a physical dump. To
  do a logical data set dump, either do not specify any input volumes
  with the DATASET keyword or use the LOGINDDNAME or
  LOGINDYNAM keywords.

# **INDYNAM**



INDYNAM specifies that volumes to be dumped are to be dynamically allocated for a full or tracks dump.


volser Specifies the volume serial number of a DASD volume to be dumped.

*unit* Specifies the device type of a DASD volume to be dumped. This parameter is optional.

#### Note:

- 1. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*).
- 2. Only one volume is allowed for a full or tracks dump operation; one or more volumes are allowed for a physical data set dump operation.
- 3. Using INDYNAM instead of DD statements to allocate DASD volumes does not appreciably increase run time and permits easier coding of JCL and command input.
- 4. If either INDDNAME or INDYNAM is specified, *physical* processing is used to perform the dump. If both INDDNAME and INDYNAM are omitted, a *logical* data set dump is performed. A logical data set dump is also performed if you specify the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword.

# **KEYPASSWORD**



### **KEYPASSWORD**

Specifies the 8 to 32 character password (in EBCDIC) that is used to generate a clear TDES triple-length key or a clear 128-bit AES key.

### **ICOUNT**

The ICOUNT optional parameter specifies how many times DFSMSdss performs the SHA-1 hash algorithm in the generation of the data key and initial chaining vector for encryption. n is an integer between 1 and 10000.

If you do not specify ICOUNT, the default number of iterations is 16.

### **ENCRYPT**

The ENCRYPT keyword allows you to specify the type of encryption to use. The data key used is generated from the password you specified on the KEYPASSWORD keyword. If the same password is specified on separate DUMP commands, the same data key will be generated for a particular encryption type. The types of encryption are:

#### CLRAES128

Specifies that the dumped data is encrypted with a clear 128-bit AES key. It will be done using CPACF on a z9 or z10 processor. On any other processor (z900, z800, z990, or z890), the AES cryptography is done by the ICSF software.

#### **CLRTDES**

Specifies that the dumped data is encrypted with a secure triple-length DES key. It will use CPACF on a z890, z990, z9, and z10 processor. On a z900 and z800, you will need to start ICSF in order to perform the DES cryptography.


If you do not specify ENCRYPT, the default type of encryption is CLRAES128.

#### Note:

- 1. When you specify KEYPASSWORD, the only types of encryption that are allowed are CLRTDES and CLRAES128. Secure Triple DES (ENCTDES) is not allowed.
- 2. When using the KEYPASSWORD keyword, you must take care to ensure that the password is not lost or forgotten. If you lose or forget the password, DFSMSdss cannot decrypt the encrypted data on the dump data set. No password recovery mechanism exists. Neither the password or the generated data key is stored on the output medium.
- 3. Use of the HWCOMPRESS keyword is recommended when using the ENCRYPT keyword.
- 4. The KEYPASSWORD keyword is mutually exclusive with the RSA keyword.
- 5. The KEYPASSWORD password that is specified in your input command stream is not printed in the SYSPRINT output.
- 6. The ICSF address space must be started up successfully regardless of the processor you are running DFSSMSdss on and the ENCRYPT sub-parameter you use.

For more information on the ENCRYPT keyword, see "RSA" on page 418.

## **LOGINDDNAME**



ddn Specifies the name of the DD statement that identifies the input volume that contains the data sets for a logical dump operation. To ensure correct processing, each of the DD statements corresponding to a DDNAME (ddn) must identify only one volume serial number.


#### Notes for LOGINDDNAME, LOGINDYNAM, and STORGRP keywords:

1. When you specify the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword, DFSMSdss uses logical processing to perform the dump operation. Logical processing also occurs when no input volume is specified.

2. A multivolume data set that has extents on volumes that are not specified with the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword will not be dumped unless you specify SELECTMULTI.

For information about the SELECTMULTI keyword, see "LOGINDYNAM."

## LOGINDYNAM



LOGINDYNAM specifies that volumes that contain the data sets to be dumped using logical processing are to be dynamically allocated.

Note: The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*).

volser Specifies the volume serial number of a DASD volume to be dumped.

unit Specifies the device type of a DASD volume to be dumped. This parameter is optional.

#### **SELECTMULTI**

Specifies the method for determining how cataloged multivolume data sets are to be selected during a logical data set dump operation. SELECTMULTI is accepted only when logical volume filtering is specified with one of the following keywords:

- LOGINDDNAME
- LOGINDYNAM
- STORGRP

If logical volume filtering is not used, the specification of SELECTMULTI is not accepted.

- ALL Specifies that DFSMSdss not dump a multivolume data set unless the following criteria are met:
  - The volume list that is created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword must list all the volumes that contain a part of the data set.
  - The volume list that is created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword must list all the volumes that contain a part of the VSAM cluster.

ALL is the default.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you only need to list all parts of the base cluster in the volume list.
- Do not specify SPHERE and you must list all parts of the base cluster and the associated alternate indexes in the volume list.

ANY Specifies that DFSMSdss dump a multivolume data set when any part of the non-VSAM data set or VSAM base cluster is on a

volume in the volume list created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword.

For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you only need to list any part of the base cluster in the volume list.
- Do not specify SPHERE and you must list any part of the base cluster and the associated alternate indexes in the volume list.

FIRST Specifies that DFSMSdss dump a multivolume data set only when the volume list includes the volume that contains the first part of the data set. The volume list is created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword.


For VSAM data sets, the volume list is affected by the use of the SPHERE keyword as follows:

- Specify SPHERE and you only need to list the volume that contains the first extent of the data component in the volume list.
- Do not specify SPHERE and you must list the following in the volume list:
  - The volume containing the first extent of the data component for the base cluster
  - The volume containing the first extent of the data component for the associated alternate indexes

## Notes for LOGINDDNAME, LOGINDYNAM, and STORGRP keywords:

- 1. If the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword is specified, DFSMSdss uses logical processing to perform the dump operation. Logical processing is also used if no input volume is specified.
- 2. A multivolume data set that has extents on volumes not specified with the LOGINDDNAME, LOGINDYNAM or STORGRP keyword will not be dumped unless you specify SELECTMULTI.

## NEWNAMEUNCONDITIONAL



NEWNAMEUNCONDITIONAL specifies a new name for a source data set during logical dump processing. This keyword provides an alternative to renaming data sets during RESTORE processing. You might also find this keyword to be useful in avoiding name contention between data sets that are backed up (dumped) and data sets that are active on your system.

NEWNAMEUNCONDITIONAL can only be used when invoking DFSMSdss through the application programming interface (API).

#### **DUMP Command**

NEWNAMEUNCONDITIONAL specifies that a source data set should be given a new name during dump processing, regardless of whether or not a data set already exists with the same name.

Specifies the prefix to be used to replace the first-level qualifier of the data pfx set name. It is optional. If you use it, you must specify it as the first parameter in the list of sub-keywords. You might want to use a prefix only if you do not specify the (on,nn) parameters, or if the old name filters do not match the data set name.

Specifies the old name to be used as a filtering criterion. on

Specifies the new name to be used if the data set name matches the old nn name filtering criterion (on).

The syntax rules for the (on,nn) parameters are the same as those for the RENAME keyword in a RESTORE operation. If the new name filter has errors, the data set is not dumped and an error message is issued. For data set naming conventions, see "INCLUDE" on page 409.

#### Note:

- 1. DFSMSdss does not verify whether the attributes of the source data set match those of the new-named data set. It is the responsibility of the program invoking DFSMSdss to perform this verification. This could cause the RESTORE operation to fail when attempting to restore to an existing data set when the attributes of the data set you are trying to restore to do not match.
- 2. If the new name is not fully qualified, it must contain the same number of qualifiers as the old name. For example, given the old-name filter DATE.\*\* and the new-name filter DATE.\*.\*.LIST, DATE.MARCH.TODAY.OLDLIST is renamed, but DATE.MARCH.OLDLIST is not.
- 3. To change the number of qualifiers, specify fully-qualified names, for example, NEWNAMEU((A.B.C,A.B.C.D)).
- 4. If necessary, DFSMSdss truncates the new name to 44 characters. If the new name ends with a period, that period is also truncated.
- 5. You cannot use GDG relative generation filtering for old or new names.

## NOTIFYCONCURRENT

See "CONCURRENT" on page 316.

#### NOVALIDATE

See "VALIDATE" on page 423.

#### ONLYINCAT

See "INCAT" on page 408.

## **OPTIMIZE**



OPTIMIZE specifies the number of tracks to be read at a time, as follows:

- If n is 1, DFSMSdss reads one track at a time.
- If n is 2, DFSMSdss reads two tracks at a time.
- If n is 3, DFSMSdss reads five tracks at a time.
- If n is 4, DFSMSdss reads one cylinder at a time.

If OPTIMIZE is not specified, OPTIMIZE(1) is the default. Specifying OPTIMIZE (2), (3), or (4) reduces the time for a dump. Notice that this keyword uses more real and virtual storage. It also keeps the channel busy for longer blocks of time.

**Recommendation:** To improve performance and save dump space, specify the OPTIMIZE keyword with the COMPRESS keyword.

### **OUTDDNAME**




ddn Specifies the name of the DD statement that identifies the (output) dump data set. This data set can be on a tape or a DASD volume. Up to 255 ddnames can be specified; that is, up to 255 dump copies can be made.

#### Note:

- 1. The default block size for output records that are written to tape is determined by obtaining the optimum block size for the device. The maximum is 262 144. You can change this default to 32 760 bytes by using the installation options exit routine
- 2. The default block size for output records written to DASD is the track length for devices whose track length is less than 32KB (KB equals 1 024 bytes), or one-half the track length for devices whose track length is greater than 32KB.
- 3. If the DCB keyword BLKSIZE is specified on the DD statement for tape, it must be in the range of 7 892 through 262 144. If the DCB keyword BLKSIZE is specified on the DD statement for DASD, it must be in the range of 7 892 through 32 760.
- 4. The COPYDUMP command cannot change the block size of the DFSMSdss dump data set. If you intend to copy the dump data set to a DASD device, you must ensure that the block size will be small enough to fit on the target device. **ATTENTION:** COPYDUMP is the only supported method for copying DFSMSdss dump data sets. Using a copy produced by any other method or utility as input to a RESTORE operation can produce unpredictable results.
- 5. If the DCB keyword RECFM is specified on the DD statement, it must have a value of "U".
- 6. If the DCB keyword LRECL is specified on the DD statement, it must have a value of "0" (zero).
- 7. The output data set must be a standard format sequential data set and cannot use any extended-format features, such as compression.
- 8. When creating multiple dump copies in one step, DFSMSdss uses the largest 'common' block size that the output DDs can handle, regardless of the block size determined at open time. For example, if an output dump data set is opened with a block size of 65520 and a second output dump data set is opened with a block size of 262144, DFSMSdss writes at most 65520 bytes of data in a block to each output dump data set.

For more information about the installation options exit routine, see *z/OS DFSMS Installation Exits*.

## **PASSWORD**



PASSWORD specifies the passwords that DFSMSdss uses for password-protected data sets for all dump operations. (DFSMSdss bypasses password checking for RACF-protected data sets.) DFSMSdss requires this keyword only when the following apply:

- · You do not have the required access for volume-level RACF DASDVOL or RACF DATASET.
- The installation authorization exit does not bypass the checks.
- You do not want a prompt for the VSAM data sets password.

#### Note:

- 1. Specify the passwords for all data sets that do not have RACF protection but do have password protection. A utility invoked by DFSMSdss may prompt the operator for a password during processing. You can control authorization checking by using the installation authorization exit.
- 2. Actual data set passwords that are specified in your input command stream are not printed in the SYSPRINT output.

The preferred method of protection is catalog protection through an access control facility, such as RACF. Catalog passwords are not supported to facilitate disaster recovery operations, application data transfers, and data set migration.

ddn Specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set that contains data set names and their passwords. This data set must contain card-image records in DFSMSdss command syntax format.

dsn/pswd

dsn is a fully qualified data set name. pswd is its password. If no password follows the slash (/), dsn is treated as though it were ddn.

#### **PHYSINDD**




#### **PHYSINDD**

may be specified to request that DFSMSdss perform a physical copy or dump operation. It specifies a ddname that describes an input volume to be used for the copy or dump operation. Only one ddname may be specified. The device described by the ddname must be the same type as the output device specified on the OUTDD or OUTDYNAM keyword.

**Note:** PHYSINDD may be abbreviated to PIDD.

## **PHYSINDYNAM**



#### **PHYSINDYNAM**

specifies the input volume that is to be dynamically allocated to a physical copy or dump operation. A nonspecific volume serial number cannot be specified by using an asterisk (\*). Only one volume may be specified for a FULL, TRACKS, or DATASET COPY. The device described by the volser must be the same type as the output device specified on the OUTDD or OUTDYNAM keyword.

**Note:** PHYSINDYNAM may be abbreviated to PIDY.

## **PROCESS**



SYS1 specifies that DFSMSdss allows data sets with a high-level qualifier of SYS1 to be dumped and that SYS1 data sets can be deleted and uncataloged. SYS1.VVDS and SYS1.VTOCIX data sets can be physically, but not logically, dumped. SYS1.VVDS and SYS1.VTOCIX data sets cannot be deleted or uncataloged. To specify PROCESS(SYS1), RACF authorization may be required.

For more information about RACF authorization, see Chapter 5, "Protecting DFSMSdss functions," on page 27.

#### **PURGE**



PURGE for a data set dump operation, specifies deletion of unexpired data sets that are dumped successfully. This keyword is valid only when DELETE has been specified.

## READIOPACING



READIOPACING specifies the pacing (that is, I/O delay) to be used for DFSMSdss DASD read channel programs. You can use this keyword to allow more time for other applications to complete I/O processing. DFSMSdss waits the specified time before issuing each channel program that reads from DASD.

*nnn* Specifies the amount of time in milliseconds. The maximum delay that can be specified is 999 milliseconds.

#### Note:

- 1. If READIOPACING is not specified, there will be no I/O delay.
- 2. The additional wait time does not apply to error recovery channel programs.
- 3. READIOPACING does not apply to concurrent copy I/O.

## RESET




RESET specifies that the data set changed flag in the VTOC entry is reset for all data sets that are serialized and dumped successfully. This applies to both a full dump and a data set dump operation.

#### Note:

- 1. Do not specify SHARE or FCWITHDRAW if you specify RESET.
- 2. You might not want to specify RESET if you use a storage management program, such as DFSMShsm.
- 3. DFSMSdss ignores the RESET keyword when a data set is dumped using record-level sharing (RLS) access.
- 4. Using the RESET keyword for a logical data set dump operation causes the enqueue on a data set to be held until all data sets are dumped. DFSMSdss does not reset the data set change indicator until after all data sets are dumped. This may be of particular interest when dumping user catalogs. That is because delays for other jobs that need access to the user catalog may be caused by DFSMSdss holding the enqueue for the user catalog until all the data sets are dumped. This may cause a lockout condition when another job is dumping the same catalog at the same time.
- 5. You may specify both CONCURRENT and RESET, but RESET is ignored and a warning message is printed unless your installation uses a patch to tell DFSMSdss to accept RESET with CONCURRENT and to reset the data set changed indicator after the concurrent copy initialization is complete. If your installation uses the patch, it is possible that the data set changed indicator is left reset (off) even when the dump of the data set is not successful. If this is unacceptable, do not specify RESET with CONCURRENT.

For more information about DFSMSdss patches, see Chapter 14, "DFSMSdss patch area," on page 217.

### **RSA**



## **RSA**

The RSA keyword allows you to specify the label of an existing RSA public key that is present in the ICSF PKDS. The RSA public key is used to encrypt a randomly generated data key, so that the encrypted data key can be stored on the output medium.

ICSF only allows labels for RSA keys to be up to 64 characters long. The first character must be alphabetic or a national character (#, \$, @). The remaining characters may be alphabetic, numeric, national, or a period.

#### Note:

- 1. You can also specify the label of an RSA public/private key pair. ICSF uses the public key when encrypting the data key.
- 2. The RSA keyword cannot be specified with the KEYPASSWORD keyword.
- 3. When using ENCTDES, or running on z800/z900 hardware, ensure that the RSA key is an internal key. Under these scenarios, an external RSA key will not be accepted by ICSF during the restore of the data.

#### **ENCRYPT**

The ENCRYPT keyword allows you to specify the type of encryption key and the type of encryption that DFSMSdss performs on the dumped data. You can specify one of the following options. If you do not specify the ENCRYPT keyword, CLRAES128 is the default. If you specify ENCRYPT with the RSA keyword, the data key is randomly generated for each DUMP command.

- CLRTDES This option specifies that the dumped data is encrypted with a clear triple-length DES key.
- CLRAES128 This option specifies that the dumped data is encrypted with a clear 128-bit AES key
- ENCTDES This option specifies that the dumped data is encrypted with a secure triple-length DES key.

## SELECTMULTI

See "LOGINDYNAM" on page 412.

#### SHARE



SHARE specifies that DFSMSdss is to share the data sets to be dumped for read access with other programs. Do not specify the DELETE, RESET, or UNCATALOG keyword if you specify SHARE. Use SHARE carefully to ensure that the contents of the dumped copy of the data set are valid.

**Restriction:** You cannot use the SHARE and FULL keywords at the same time.

#### Note:

1. Unlike the RESTORE command, the DUMP command honors the SHARE keyword for VSAM data sets. However, the SHARE keyword is only honored for VSAM data sets that were defined with share options other than (1,3) or (1,4).

Specifying the SHARE keyword does not cause DFSMSdss to honor the share options that are defined for VSAM data sets. For VSAM data sets that are defined with share options other than (1,3) or (1,4), specifying the SHARE keyword allows other programs to obtain read access, but not write access, to the data sets while they are being dumped. For VSAM data sets that are

- defined with share options (1,3) or (1,4), neither read access nor write access by other programs is allowed while the data set is being dumped, regardless of whether SHARE was specified.
- 2. Do not use the SHARE keyword during a physical dump of HFS or zFS data sets.
- 3. The SHARE keyword is required to logically dump mounted HFS data sets in DFSMSdss releases prior to DFSMSdss Release 1.5. The SHARE keyword is no longer required to logically dump mounted HFS data sets beginning in DFSMSdss Release 1.5.
- 4. For an HFS data set, DFSMSdss obtains both an ADRDSN enqueue and a SYSZDSN enqueue. SHARE determines only whether the ADRDSN enqueue is shared or exclusive.
- 5. For a zFS data set, DFSMSdss obtains an ADRDSN enqueue, a SYSDSN enqueue, and a number of SYSVSAM enqueues. SHARE determines only whether the ADRDSN enqueue is shared or exclusive. When specifying DELETE, DFSMSdss attempts to obtain exclusive SYSDSN and SYSVSAM enqueues. If you do not specify DELETE, DFSMSdss attempts to obtain shared SYSDSN and SYSVSAM enqueues.

For more information about dumping HFS or zFS data sets, see "Backing up data sets with special requirements" on page 44.

For more information about dumping HFS data sets, see "Dumping HFS data sets" on page 564.

For more information about dumping zFS data sets, see "zFS data sets" on page 565.

## **SPHERE**




SPHERE is an option for a logical data set dump. SPHERE specifies that for any VSAM cluster dumped DFSMSdss must also dump all associated AIX clusters and paths. Individual sphere components need not be specified, only the base cluster name.

#### Note:

- 1. The base cluster name must be specified to process the entire sphere. If the SPHERE keyword is specified but the base cluster name is not, none of the associations will be processed.
- 2. If an AIX is dumped without the SPHERE keyword, during a restore DFSMSdss treats the AIX as a normal VSAM KSDS.

## **STORGRP**



STORGRP specifies that all of the online volumes in the storage group be dynamically allocated. If a volume in the storage group is not online, that volume is not used for processing. You can specify up to 255 storage group names. Specifying STORGRP with a storage group name is equivalent to specifying LOGINDYNAM with all the online volumes in the storage group included in the list.

You can specify the STORGRP keyword with the SELECTMULTI keyword, but STORGRP cannot be used at the same time with the INDDname, INDYnam, LOGINDDname, or LOGINDYnam keywords.

See "LOGINDYNAM" on page 341 for a description of the SELECTMULTI keyword.

## Notes for LOGINDDNAME, LOGINDYNAM, and STORGRP keywords:

- 1. If the LOGINDNAME, LOGINDYNAM, or STORGRP keyword is specified, DFSMSdss uses logical processing to perform the dump operation. Logical processing is also used if no input volume is specified.
- 2. A multivolume data set that has extents on volumes not specified with the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword will not be dumped unless you specify SELECTMULTI.

## **TOLERATE**



## **ENQFailure**

specifies that data sets are to be processed even though shared or exclusive access fails.

TOL(ENQF) and FULL or TRACKS are mutually exclusive; you cannot specify these keywords together.

### Note:

- 1. Unlike PDS data sets, PDSE data sets that are open for update cannot be dumped even if TOL(ENQF) is specified.
- 2. If you must dump a PDSE data set and it must be open for update, process the data set with concurrent copy (specify CONCURRENT). If you cannot use concurrent copy, convert the PDSE back to PDS and then dump the PDS data set with TOL(ENQF).
- 3. TOL(ENQF) cannot be used when processing a **logical** dump of HFS or zFS data sets. HFS or zFS data sets cannot be dumped when the HFS or zFS data set is mounted on a system other than the system where the dump is being performed. TOL(ENQF) is not required when dumping an HFS data set or zFS data set is mounted on the same system where the dump is being performed.
- 4. Exercise caution if you use TOL(ENQF) during a **physical** dump of HFS data sets. Unlike other types of data sets, if an HFS data set is updated during a physical dump with TOL(ENQF), a subsequent restore can likely result in an unusable data set.

For more information about dumping HFS or zFS data sets, see "Backing up data sets with special requirements" on page 44. For more information about TOL(ENQF), see Chapter 21, "Data integrity—serialization," on page 561.


#### **IOERror**

specifies that DFSMSdss is to continue processing even though input errors occur, but is to end after 100 errors. This applies only to input errors and only to equipment check and busout parity.

#### Note:

- 1. TOL(IOERror) is ignored if CANcelerror is specified.
- 2. If a permanent read error occurs, the track image record is flagged on output as having an I/O error and the dump processing continues.
- 3. This track is cleared in a restore operation.

## **TRACKS**



TRACKS specifies ranges of tracks to be dumped. When you restore the data, this entire range or its subset must be specified with the RESTORE command.

**Restriction:** You cannot use the TRACKS keyword with the TOL(ENQF) keyword.

- c1,h1 Specifies the cylinder and head number of the beginning of the range. Specify hexadecimal numbers as X'c1' or X'h1'.
- c2,h2 Specifies the cylinder and head number of the end of the range. Specify hexadecimal numbers as X'c2' or X'h2'.

You can enter X'FFFFFFF' (or 268435455) as the high cylinder value. This causes DFSMSdss to choose the high cylinder value to be the end of the volume.

#### Note:

- 1. The *c*2 must be greater than or equal to *c*1.
- 2. If *c*2 equals *c*1, *h*2 must be greater than or equal to *h*1.

DFSMSdss verifies that the range is within the limits of the device. If you do not specify all four values for a range, DFSMSdss provides the missing values unless the omitted value causes a syntax error. No intervening values can be omitted. For example:

## **Specified**

#### Results

**None** Syntax error

*c*1 c1,0,c1, maximum head number *c1,h1 c1,h1,c1*, maximum head number

c1,h1,c2

*c1,h1,c2,* maximum head number

*c*1,,*c*2 Syntax error

,h1 Syntax error

c1,h1,X'FFFFFFF'

c1,h1,maximum cylinder number for the volume, maximum head number

For more information about using TRACKS during a physical dump operation, see Chapter 6, "Managing availability with DFSMSdss," on page 33.

## **UNCATALOG**



UNCATALOG applies to physical and logical data set dump operations.

For a *physical* data set dump operation, UNCATALOG instructs DFSMSdss to uncatalog any single-volume, non-VSAM, cataloged data sets successfully dumped from the current volume.

For a *logical* data set dump operation, UNCATALOG instructs DFSMSdss to uncatalog any successfully dumped single or multivolume non-VSAM data sets that are currently cataloged. (For VSAM or SMS-managed data sets, use the DELETE keyword.)

#### Note:

- 1. UNCATALOG is ignored for VSAM and SMS-managed data sets.
- 2. Do not specify UNCATALOG with CONCURRENT, because after the concurrent copy operation has begun, the original data can still be updated.
- 3. For a logical data set dump operation, the use of the UNCATALOG keyword causes the enqueue in a data set to be held until all data sets are dumped. DFSMSdss does not uncatalog the data set until after all data sets are dumped.
- 4. Any non-SMS, non-VSAM data set that has a high-level qualifier of SYS1 cannot be uncataloged unless PROCESS(SYS1) is specified.

For information about a patch to modify the UNCATALOG algorithm, see "Using RESET or UNCATALOG in a logical data set dump (PN60114)" on page 226.

## **VALIDATE**



VALIDATE on a logical data set dump, specifies that all indexed VSAM data sets are to be validated as they are dumped. If the NOVALIDATE keyword is specified, the indexed VSAM data sets are dumped without validation. VALIDATE is the default.

#### Note:

- 1. If an indexed VSAM data set is dumped using VALIDATE, it must be restored on a system that supports VALIDATE. Otherwise, an error message is issued, and the restore fails.
- 2. Do not specify the NOVALIDATE keyword when processing VSAM extended-format or extended-addressable data sets.
- 3. When a data set is restored, the free space in the control areas and control intervals are reset to the values in the catalog entry. You can override the values in the catalog entry by specifying the FREESPACE keyword on the restore.
- 4. Use the NOVALIDATE keyword on the DUMP command if you wish to restore to a DFDSS Version 2 Release 5 system that does not have the appropriate VALIDATE support, or to any level of DFDSS prior to Release 2 Version 5.

#### WAIT



For physical data set dump processing: WAIT specifies to DFSMSdss the length of a wait and the number of retries to obtain control of a data set.

numsecs

Specifies a decimal number from 0 to 255 that designates the interval, in seconds, between retries.

numretries

Specifies a decimal number from 0 to 99 that designates the number of times DFSMSdss must retry to gain control of a data set.

For logical data set dump processing: WAIT specifies to DFSMSdss the length of wait and the number of passes to obtain control of a data set.

numsecs

Specifies a decimal number from 0 to 255 that designates the interval, in seconds, to wait before attempting another pass through the list of selected data sets.

numretries

Specifies a decimal number from 0 to 99 that designates the number of passes to make through the list of selected data sets. Each pass is an attempt to obtain control of a data set.

The default for numsecs, numretries is (2,2), which specifies two retries at 2-second intervals. If you do not want to wait for a data set, specify 0 for either numsecs or numretries.

For logical data set dump operation, the WAIT keyword has a different meaning when: (1) data sets are being serialized, (2) multiple data sets are being processed, and (3) WAIT(0,0) is not specified. In this case, DFSMSdss makes multiple passes through the list of selected data sets. On each pass, DFSMSdss processes the data sets that (1) can be serialized without waiting for the resource and (2) were not processed before. At the end of a pass, if none of the data sets could be processed without waiting for a resource, then, in the next pass, at the first occurrence of a data set that was not processed, a WAIT will be issued. That data set and the remainder of the list will be processed if possible. The above procedure will be repeated until all data sets are processed or the WAIT limits are reached. For example, if WAIT(3,10) is specified and 5 data sets are left to be processed, up to

10 passes are made. On each pass, an unprocessed data set is waited upon for 3 seconds. Thus, only a 30-second maximum will ever be waited, not 150 (5 times 3 times 10).

**Note:** The WAIT keyword does not control wait/retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is 3 seconds and the default retry count is 30. This results in a total wait time of 90 seconds.

For more information about controlling the wait/retry attempts for system resources, see "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

## **ZCOMPRESS**



ZCOMPRESS specifies that DFSMSdss writes the dumped data in compressed format to the output medium using zEDC Services. This decreases the space occupied by the dumped data.

NONE requests that DFSMSdss not perform compression with zEDC Services. This is the default behavior and specifying this option is not necessary to bypass zCompression.

PREFERRED specifies that DFSMSdss use zEDC Services, if possible. If zEDC Services are not available or cannot be used, DFSMSdss continues processing normally.

REQUIRED specifies that compression via zEDC Services must be used. If they are not available or cannot be used, DFSMSdss fails the operation.

**Note:** ZCOMPRESS(PREFERRED) may be specified with either the COMPRESS or HWCOMPRESS keywords, but not both. If zEDC Services cannot be used, DFSMSdss will attempt to use the alternate compression method specified.

# Data integrity considerations for full or tracks dump operation

For a full or tracks dump operation, DFSMSdss serializes the VTOC to preclude DADSM functions (such as ALLOCATE, EXTEND, RENAME, and SCRATCH) from changing the contents of the VTOC on the volume during the dump operation. Data sets are *not* serialized on these full or tracks operations. Therefore, some data sets might be opened by other jobs during the dump operation, resulting in copies of partially updated data sets. You can minimize this possibility by performing the dump operation when there is low system activity.

Full data integrity can only be guaranteed by performing dump operations by data set when TOL(ENQF) or SHARE keywords are not specified.

# Format of the output data set

For the format of the output data set, see Chapter 6, "Managing availability with DFSMSdss," on page 33.

# **Examples of full and tracks dump operations**

In the following example, data from DASD volume 111111 is to be dumped to the first data set of standard label tape volumes TAPE01 and TAPE02.

The command input to be substituted for a full and tracks dump are shown below in Example 1A and Example 1B, respectively. To restore the same volume, refer to Examples 1, 1A, and 1B of the RESTORE command.

## Example 1: a data set dump

```
//JOB1 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//DASD DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//TAPE DD UNIT=(3480,2), VOL=SER=(TAPE01, TAPE02),
// LABEL=(1,SL), DISP=(NEW, CATLG), DSNAME=USER2.BACKUP
//SYSIN DD *
command input
/*
```

See command input in "Example 1A: a full dump operation" and "Example 1B: a tracks dump operation."

## Example 1A: a full dump operation

```
DUMP INDDNAME(DASD) OUTDDNAME(TAPE)
```

## Example 1B: a tracks dump operation

```
DUMP TRACKS(1,0,1,5) INDDNAME(DASD) - OUTDDNAME(TAPE)
```

## **Example 1C: full volume dump operation with CONCURRENT**

This JCL does a DFSMSdss full-volume dump using concurrent copy. This job continues (with a warning message) if concurrent copy initialization fails. No special action is required to perform a restore operation after a concurrent copy dump operation.

## Examples of physical data set dump operations

Example 2 depicts specified data sets on DASD volumes (numbered 111111 and 222222) that are being dumped to the first data set of standard label tape volume called TAPE02.

Examples 2A through 2G below complement examples 2A through 2D in the restore section, in any combination; for example, the dump tape produced in example 2C can be used as the input tape for example 2A under the RESTORE command.

## **Example 2: depicting DASD volume DUMP**

```
//JOB2 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//OASD1 DD UNIT=3380,VOL=(PRIVATE,SER=111111),DISP=OLD
//DASD2 DD UNIT=3380,VOL=(PRIVATE,SER=222222),DISP=OLD
//TAPE DD UNIT=3480,VOL=SER=TAPE02,
// LABEL=(1,SL),DISP=(NEW,CATLG),DSNAME=USER2.BACKUP
//SYSIN DD *
command input
/*
```

See command input in "Example 2A: using the INCLUDE subkeyword," "Example 2B: using the INCLUDE and EXCLUDE subkeywords," "Example 2C: using the INCLUDE, EXCLUDE, and BY subkeywords," "Example 2D: with filtering data in a data set" on page 428, "Example 2E: with passwords in the input stream" on page 428, "Example 2F: with passwords in a data set" on page 428, and "Example 2G: wait for data sets if they or other data sets with the same name are in use by other jobs" on page 428.

## Example 2A: using the INCLUDE subkeyword

```
DUMP INDDNAME(DASD1,DASD2) OUTDDNAME(TAPE) -
DATASET(INCLUDE(USER2.**,USER3.*))
```

## Example 2B: using the INCLUDE and EXCLUDE subkeywords

```
DUMP INDDNAME(DASD1,DASD2) OUTDDNAME(TAPE) -
DATASET(INCLUDE(USER2.**,USER3.*) -
EXCLUDE(USER2.**.REP))
```

# Example 2C: using the INCLUDE, EXCLUDE, and BY subkeywords

```
DUMP INDDNAME(DASD1,DASD2) OUTDDNAME(TAPE) -
DATASET(INCLUDE(USER2.**,USER3.*) -
EXCLUDE(USER2.**.REP) -
BY((DSCHA,EQ,1)))
```

## Example 2D: with filtering data in a data set

```
DUMP INDDNAME(DASD1,DASD2) OUTDDNAME(TAPE) -
DATASET(FILTERDD(A1))
```

Note: The following DD statement must be added to the JCL shown above:

```
//A1 DD DSNAME=USER2.FILTER,DISP=SHR
```

This cataloged data set (USER2.FILTER) contains three card-image records. The information shown is positioned in columns 2 through 72 of each record:

```
INCLUDE(USER2.**,USER3.*) -
EXCLUDE(USER2.**.REP) -
BY((DSCHA,EQ,1))
```

## Example 2E: with passwords in the input stream

```
DUMP INDDNAME(DASD1,DASD2) OUTDDNAME(TAPE) -
DATASET(INCLUDE(USER2.**,USER3.*)) -
PASSWORD(USER2.ABC.DEF/PSWD1,USER2.XYZ/PSWD2)
```

## Example 2F: with passwords in a data set

```
DUMP INDDNAME(DASD1,DASD2) OUTDDNAME(TAPE) -
DATASET(INCLUDE(USER2.**,USER3.*)) -
PASSWORD(PDD)
```

**Note:** The following DD statement must be added to the JCL shown above:

```
//PDD DD DSNAME=USER2.PASSWORD,DISP=SHR
```

This cataloged data set (USER2.PASSWORD) contains a single card-image record. The information shown is positioned in columns 2 through 72:

```
USER2.ABC.DEF/PSWD1,USER2.XYZ/PSWD2
```

# Example 2G: wait for data sets if they or other data sets with the same name are in use by other jobs

```
DUMP INDDNAME(DASD1) OUTDDNAME(TAPE) -
DATASET(INCLUDE(**)) -
WAIT(1,99)
```

If a data set is in use, DFSMSdss waits for one second, then tries to gain access to the resource again. This is done as many as 99 times for each data set.

## Example 2H: clearing volumes of uncataloged data sets

```
DUMP DATASET(INCLUDE(**) -
BY((DSORG NE VSAM) -
(CATLG EQ NO))) -
INDDNAME(DASD1, DASD2) -
OUTDDNAME(TAPE) -
DELETE PURGE
```

If you do not want a dump of the uncataloged data sets, the output ddname TAPE can be a dummy. DASD1 and DASD2 identify the input volumes. A physical data set dump can handle multiple uncataloged single-volume data sets with the same name if multiple volumes are specified. This is because each volume is processed in order, one at a time. The dump cannot handle a multivolume data set even if all the volumes on which it resides are specified as input volumes.

# Examples of logical data set dump operations

This section contains examples of logical data set dump operations.

## Example 1: dumping data sets constantly in use

```
//J0B1
           J0B
                 accounting information, REGION=nnnnK
//STEP1
           EXEC PGM=ADRDSSU
//SYSPRINT DD
                 SYSOUT=A
//DASD1 DD
                 UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
          DD UNIT=3380, VOL=(PRIVATE, SER=2222222), DISP=OLD UNIT=3480, VOL=SER=TAPE02,
//DASD2
//TAPE
// LABEL=(1,SL),DISP=(NEW,CATLG),DSNAME=USER2.BACKUP
//SYSIN
           חח
DUMP LOGINDDNAME(DASD1) OUTDDNAME(TAPE) -
       DATASET(INCLUDE(**)) TOL(ENQF) WAIT(0,0)
```

DFSMSdss does not wait (WAIT(0,0)) if a data set is in use. Instead, it processes the data set without serialization or enqueuing (TOL(ENQF)).

## Example 2: dumping a user catalog and its aliases

To dump a user catalog, you perform a logical data set dump with the fully qualified user catalog name as the data set name. No filtering is allowed. If the user catalog has any aliases, the aliases are automatically dumped.

```
//J0B2
           J0B
                 accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
//SYSPRINT DD
                 SYSOUT=A
//DASD1
          DD
                 UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
                UNIT=3480, VOL=SER=TAPE02,
//TAPE
          DD
// LABEL=(1,SL),DISP=(NEW,CATLG),DSNAME=USER2.BACKUP
//SYSIN
         DD
DUMP OUTDDNAME (TAPE) -
      DS(INCLUDE(MY.USER.CAT))
```

## Example 3: logical data set dump operation with catalog filtering

```
//JOB3 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//TAPE DD UNIT=3480,VOL=SER=TAPE04,
// LABEL=(1,SL),DISP=(NEW,CATLG),DSN=USER3.BACKUP
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
DUMP OUTDD(TAPE) -
    DS(INCL(USER1.**))
/*
```

All data sets cataloged in the standard search order whose first-level qualifier is USER1 are to be dumped. Because some of these data sets are multivolume, source DASD volumes are not specified, resulting in data set selection by catalog.

Example 3 can be modified as follows to dump only data sets changed since the last backup. In addition, data sets that end with a qualifier of LISTING are not to be dumped (EXCL(\*\*.LISTING)).

```
//SYSIN DD *
DUMP OUTDD(TAPE) -
DS(INCL(USER1.**) -
EXCL(**.LISTING) -
BY((DSCHA EQ 1)))
/*
```

## Example 4: logical data set dump operation with VTOC filtering

```
//J0B4
                accounting information, REGION=nnnnK
          J0B
//STEP1
           EXEC PGM=ADRDSSU
//SYSPRINT DD
                SYSOUT=A
                VOL=SER=338001,UNIT=3380,DISP=OLD
//DASD1
          DD
                UNIT=3480, VOL=SER=TAPE04,
//TAPE
          DD
// LABEL=(1,SL),DISP=(NEW,CATLG),DSN=USER3.BACKUP
          DD
//SYSIN
     DUMP DATASET(INCLUDE(USER3.**)) -
     LOGINDDNAME(DASD1) -
     OUTDDNAME (TAPE)
      DELETE PURGE
```

All data sets on volume 338001 whose first qualifier is USER3 are included in a logical data set DUMP. DFSMSdss filters using the VTOC of volume 338001. Catalogs are also used, as needed, for multivolume and VSAM data sets.

The previous example can be modified as follows to dynamically allocate volume 338001 and to do SELECTMULTI processing. All single volume data sets on volume 338001 are included in a logical data set dump operation. SELECTMULTI(ANY) specifies that a cataloged data set residing on volumes 338001, 338003, and 338005 will be dumped even though 338003 and 338005 are not in the LOGINDYNAM volume list.

```
//JOB4 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//TAPE DD UNIT=3480,VOL=SER=TAPE04,
// LABEL=(1,SL),DISP=(NEW,CATLG),DSN=USER3.BACKUP
//SYSIN DD *
DUMP DATASET(INCLUDE(**)) -
    SELECTMULTI(ANY) -
    LOGINDYNAM(338001) -
    OUTDDNAME(TAPE) -
    DELETE PURGE
/*
```

# Example 5: logical data set dump operation for Storage Management Subsystem (SMS)

```
//JOB5 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//TAPE DD DSN=BACKUP(+1), DISP=(,CATLG),
// DCB=(SYS1.DFDSS.DSCB)
//SYSIN DD *
DUMP LOGINDYNAM(338001) -
SELECTMULTI(FIRST) -
DATASET(INCLUDE(**)) -
OUTDDNAME(TAPE) -
DELETE
/*
```

This example backs up the volume to a generation data set. You can use generation data set groups to create and manage multiple backup versions of a volume or data sets.

A volume is backed up for converting to or from SMS management by using a logical data set dump function.

## **Example 6: logical dump operation with CONCURRENT**

```
//JOB6 JOB accounting information,REGION=nnnnK
//DUMPSTEP EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//TAPE DD UNIT=TAPE,VOL=SER=(TAPE01,TAPE02,TAPE03),LABEL=(1,SL),
// DISP=(NEW,KEEP),DSN=USER.BACKUP
//SYSIN DD *
DUMP DATASET(INCLUDE(USER.LOG,USER.TABLE,USER.XREF)) -
OUTDDNAME(TAPE) OPTIMIZE(4) CONCURRENT
/*
```

This JCL does a DFSMSdss logical data set dump of three fully qualified data sets using concurrent copy. This job continues with a warning message if concurrent copy initialization fails. No special action is required to perform a restore operation after a concurrent copy dump operation.

## Example 7: clearing volumes of uncataloged data sets

```
//J0B7
                 accounting information, REGION=nnnnK
//STEP1
           EXEC PGM=ADRDSSU
//SYSPRINT DD
                 SYSOUT=A
//DASD1
                 VOL=SER=MYVOL1,UNIT=SYSDA,DISP=OLD
//DASD2
           DD
                 VOL=SER=MYVOL2, UNIT=SYSDA, DISP=OLD
//TAPE
           DD
                 UNIT=3480, VOL=SER=TAPE04, LABEL=(1,SL),
// DISP=(NEW,CATLG),DSN=USER3.BACKUP
//SYSIN
          חח
 DUMP DATASET(INCLUDE(**) -
               BY ((DSORG NE VSAM) -
                  (CATLG EQ NO))) -
       LOGINDDNAME (DASD1, DASD2) -
       OUTDDNAME (TAPE) -
       DELETE PURGE
```

Logical data set dump cannot be used to dump SMS data sets that are not cataloged or are cataloged outside the standard order of search. DFSMSdss physical data set dump or IDCAMS DELETE NVR can be used for such cleanup operations.

If you do not want a dump of the uncataloged data sets, the output ddname TAPE can be a dummy. DASD1 and DASD2 identify the input volumes. A logical data set dump cannot handle multiple uncataloged data sets with the same name in the same job even if all the volumes on which they reside are specified as input volumes.

A logical dump can handle a legitimate multivolume uncataloged data set if all the volumes on which it resides are specified as input volumes and if no cataloged data set by the same name exists on the system.

## PRINT command for DFSMSdss

With the PRINT command, you can print:

- A single-volume non-VSAM data set, as specified by a fully qualified name. You must specify the volume where the data set resides, but you do not need to specify the range of tracks it occupies.
- A single-volume VSAM data set component (not cluster). The component name specified must be the name in the VTOC, not the name in the catalog.
- Ranges of tracks.
- All or part of the VTOC. The VTOC location need not be known.


Note: In order to print a multivolume data set, multiple PRINT commands with the appropriate INDD/INDY keywords must be used.

Unless the ALLDATA keyword is specified, only the used space is printed for sequential or partitioned data sets or data sets with data set organizations of null.

If an error occurs in reading a record, DFSMSdss attempts to print the record in error. You can print all requested tracks or just a subset of the tracks that have data checks.

Related reading: For additional information about authorization checking, see Chapter 20, "Data security and authorization checking," on page 531.

# **PRINT** syntax



## Explanation of PRINT command keywords

This section describes the keywords for the PRINT command.

## **ADMINISTRATOR**



ADMINISTRATOR allows you to act as a DFSMSdss-authorized storage administrator for the PRINT command. DFSMSdss-initiated access checking to data sets and catalogs is bypassed. If you are not authorized to use the ADMINISTRATOR keyword, the command ends with an error message.

To use the ADMINISTRATOR keyword, all of the following conditions must be true:

- FACILITY class is active.
- The applicable FACILITY-class profile is defined.
- You have READ access to that profile.

Related reading: For additional information about the use of the ADMINISTRATOR keyword, see "ADMINISTRATOR keyword" on page 541.

## **ALLDATA**



ALLDATA specifies, when the DATASET keyword is also specified, that all allocated space in the data set is to be printed.

## **CPVOLUME**



CPVOLume specifies that the volume is VM-formatted and that the OS-compatible VTOC must begin on track zero, record five. The OS-compatible VTOC does not describe the extents of any data on the volume. Therefore, you must specify the track ranges to be printed with the TRACKS keyword. CPVOLUME is only allowed with the ADMINISTRATOR keyword because DFSMSdss cannot check access authorization for VM data.

## DATALENGTH



Specifies the logical length, in decimal format, of the data portion of a 11. record. It is used only if the count field of a record on any track has a data check.

## **DATASET**



dsn Specifies the fully qualified name of the data set to be printed. The data set is printed in logical sequence.

**Note:** Data set filtering is not allowed with the PRINT command.

## **DYNALLOC**



DYNALLOC specifies dynamic allocation, instead of enqueue, to serialize the use of data sets. This allows cross-system serialization in a JES3/MVS environment.

#### Consider:

- The serialization is of value only when the dynamic allocation/JES3 interface is not disabled.
- Run time increases when you use the DYNALLOC keyword to serialize data sets (as opposed to enqueue) because overhead is involved in dynamic allocation and serialization across multiple processors.

## **ERRORTRACKS**



ERRORTRACKS specifies that only tracks on which data checks occur are to be printed.

## **INDDNAME**



ddn Specifies the name of the DD statement that identifies a volume that contains the data set, range of tracks, or the VTOC to be printed. If you want to print a multivolume data set, you must print one volume at a time.

## **INDYNAM**



INDYNAM specifies that the volume that contains the data set, range of tracks, or the VTOC to be printed is to be dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*). Using INDYNAM instead of DD statements to allocate DASD volumes does not noticeably increase run time and permits easier coding of JCL and command input.

volser Specifies the volume serial number of a DASD volume to be printed.

*unit* Specifies the device type of a DASD volume to be printed. This parameter is optional.

### **KEYLENGTH**



*n* Specifies the key length, in decimal format, of a record. It is used only if the count field of a record on any track has a data check.

## **OUTDDNAME**




ddn Specifies the name of the DD statement that identifies the (output) print data set. Each of the DD statements corresponding to a DDNAME (ddn) must identify only one volume serial number. If this keyword is not specified, the default is SYSPRINT.

#### Note:

- 1. If the DCB keyword LRECL is specified on the DD statement, it must be in the range of 84 to 137 inclusive. If BLKSIZE is specified, it must be at least four greater than the LRECL.
- 2. If an LRECL less than 84 is chosen, the return code is 8 and an error message is issued.
- 3. If the specified LRECL is greater than 137, LRECL and BLKSIZE are set to 137 and 141, respectively.

## **PASSWORD**



PASSWORD specifies the passwords DFSMSdss is to use for password-protected data sets. (Password checking is bypassed for RACF-protected data sets.) This is required only if:

- You do not have the required volume-level RACF DASDVOL or RACF DATASET access.
- The installation authorization exit does not bypass the checks.
- You do not want to be prompted for the password for VSAM data sets.

**Note:** You should specify the passwords for all data sets that do not have RACF protection but do have password protection. During processing, a utility invoked

by DFSMSdss may have to prompt the operator for a password. You can control authorization checking by using the installation authorization exit.

For VSAM data sets, passwords are checked at the cluster level only.

Note: The PASSWORD keyword is not valid for a PRINT VTOC command.

ddn Specifies the name of the DD statement that identifies the sequential data set, or member of a partitioned data set, that contains data set names and their passwords. This data set must contain card-image records in DFSMSdss command syntax format.

#### dsn/pswd

dsn is a fully qualified data set name. pswd is its password. If no password follows the slash (/), dsn is treated as though it were ddn.

Printing of actual data set passwords specified in your input command stream is suppressed in the SYSPRINT output.

#### SHARE



SHARE specifies that DFSMSdss is to share, for read access with other programs, the data set that is to be printed.

## **TOLERATE**



#### **ENOFailure**


Specifies that data sets are to be processed even though shared or exclusive access fails. TOLERATE(ENQFAILURE) is ignored if it is specified in a PRINT TRACKS or PRINT VTOC operation.

## **IOERror**

Specifies that DFSMSdss is to continue processing even though I/O errors occur, but is to end after 100 errors.

**Related reading:** For additional information about TOL(ENQF), see Chapter 23, "Examples of the application program with the user interaction module (UIM)," on page 625.

#### **TRACKS**



TRACKS specifies ranges of tracks to be printed.

- c1,h1 Specifies the cylinder and head number of the beginning of the range. Specify hexadecimal numbers as X'c1' or X'h1'.
- c2,h2 Specifies the cylinder and head number of the end of the range. Specify hexadecimal numbers as X'c2' or X'h2'. The c2 must be greater than or equal to c1. If c2 equals c1, h2 must be greater than or equal to h1.

You can enter X'FFFFFFF (or 268435455) as the high cylinder value. This causes DFSMSdss to choose the high cylinder value to be the end of the volume.

DFSMSdss verifies that the range is within the limits of the device. If you do not specify all four values for a range, DFSMSdss provides the missing values unless the omitted value causes a syntax error. No intervening values can be omitted. For example:

## Specified

#### Results

**None** Syntax error

c1 c1,0,c1, maximum head number

c1,h1 c1,h1,c1, maximum head number

c1,h1,c2

*c1,h1,c2*, maximum head number

c1,c2 Syntax error

,h1 Syntax error

c1,h1,X'FFFFFFF'

c1,h1,maximum cylinder number for the volume, maximum head number

## **VTOC**



VTOC specifies that all or part of the VTOC is to be printed. Omitting the VTOC, DATASET, and TRACKS keywords causes the entire VTOC to be printed. Part of the VTOC can be printed by specifying:

VTOC(a,b)


where *a* and *b* are the relative track numbers (1 is the first track) of the first and last tracks to be printed. The value of *b* must be equal to or greater than the value of *a* and equal to or less than 65535 (X'FFFF'). Either of these numbers can be specified in decimal or hexadecimal. To specify a hexadecimal number, code X'nn'.

If only the first value (a) is specified, only that track is printed.

If the second value (*b*) is greater than the relative track number of the last physical track of the VTOC, DFSMSdss prints up to and including the last track of the VTOC. Therefore, another way of printing the entire VTOC would be to specify: VTOC(1,X'FFFF')

Note: The PASSWORD keyword is not valid for a PRINT VTOC command.

## WAIT



WAIT specifies to DFSMSdss the length of a wait in seconds and the number of retries to obtain control of a data set.

#### numsecs

Specifies a decimal number from 1 to 255 that designates the interval, in seconds, between retries.

#### numretries

Specifies a decimal number from 0 to 99 that designates the number of retries to gain control of a data set.

The default for *numsecs,numretries* is (2,2), which specifies two retries at 2-second intervals. If you do not want to wait for a data set, specify 0 for either numsecs or numretries.

**Note:** The WAIT keyword does not control wait/retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is 3 seconds and the default retry count is 30. This results in a total wait time of 90 seconds.

**Related reading:** For more information about controlling the wait/retry attempts for system resources, see the "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

# **Examples of print operations**

The following are examples of the PRINT command.

## **Example 1: printing a range of tracks**

```
//JOB2 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//DASD DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//SYSIN DD *
PRINT TRACKS(1,0,1,5) INDDNAME(DASD)
/*
```

Prints a hard copy of tracks 0 through 5 from cylinder 1 on volume 111111.

# Example 2: printing a component of a Virtual Storage Access Method (VSAM) cluster

```
//JOB3 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
PRINT INDYNAM(338000) /* ALLOC VOL 338000 DYNAMICALLY */-
DS(PARTS.VSAM1.INDEX) /* DATA SET THAT HAS BAD TRACK */-
WAIT(0,0) /* DO NOT WAIT IF ENQ FAILS */-
TOL(ENQF) /* IGNORE ENQ FAILURES */-
PSWD(PARTS.VSAM1/USERPSWD) /* PASSWORD FOR CLUSTER */
/*
```

A component of a VSAM data set is to be printed. The printing proceeds even if the component cannot be serialized (enqueued).

## Example 3: printing a data set

```
//STEPT003 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
PRINT DATASET(PUBSEXMP.SAM.S01) INDYNAM(D9S060)
/*
```

The output shown in Figure 18 on page 441 was produced from the example above.

```
PAGE 0001
              5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                                 1999.211 14:55
 PRINT
    DATASET(PUBSEXMP.SAM.SO1) -
    INDYNAM(D9S060)
ADR101I (R/I)-RI01 (01), TASKID 001 HAS BEEN ASSIGNED TO COMMAND 'PRINT '
ADR109I (R/I)-RI01 (01), 1999.211 14:55:44 INITIAL SCAN OF USER CONTROL STATEMENTS COMPLETED.
ADR016I (001)-PRIME(01), RACF LOGGING OPTION IN EFFECT FOR THIS TASK
ADRO06I (001)-STEND(01), 1999.211 14:55:44 EXECUTION BEGINS
*** TRACK(CCHH) 0000000E
                                  RO DATA 0000000F00000000
   COUNT 0000000E01000190
0000 F0F0F0F0 F0F1D7E4 C2E2C5E7 D4D74BE2 C1D44BE2 F0F1C1C2 C3C4C5C6 C7C8C9D1
 *000001PUBSEXMP.SAM.S01ABCDEFGHIJ*
0020 D2D3D4D5 D6D7D8D9 E2E3E4E5 E6E7E8E9 C1C2C3C4 C5C6C7C8 C9D1D2D3 D4D5D6D7
 *KLMNOPQRSTUVWXYZABCDEFGHIJKLMNOP*
 0040 D8D9E2E3 E4E5E6E7 E8E9C1C2 C3C4C5C6 F0F0F0F0 F0F2D7E4 C2E2C5E7 D4D74BE2
 *ORSTUVWXYZABCDEF000002PUBSEXMP.S*
 0060 C1D44BE2 F0F1C1C2 C3C4C5C6 C7C8C9D1 D2D3D4D5 D6D7D8D9 E2E3E4E5 E6E7E8E9
 *AM.S01ABCDEFGHIJKLMNOPQRSTUVWXYZ*
 0080 C1C2C3C4 C5C6C7C8 C9D1D2D3 D4D5D6D7 D8D9E2E3 E4E5E6E7 E8E9C1C2 C3C4C5C6
 *ABCDEFGHIJKLMNOPQRSTUVWXYZABCDEF*
 00A0 F0F0F0F0 F0F3D7E4 C2E2C5E7 D4D74BE2 C1D44BE2 F0F1C1C2 C3C4C5C6 C7C8C9D1
 *000003PUBSEXMP.SAM.S01ABCDEFGHIJ*
00C0 D2D3D4D5 D6D7D8D9 E2E3E4E5 E6E7E8E9 C1C2C3C4 C5C6C7C8 C9D1D2D3 D4D5D6D7
 *KLMNOPQRSTUVWXYZABCDEFGHIJKLMNOP*
 00E0 D8D9E2E3 E4E5E6E7 E8E9C1C2 C3C4C5C6 F0F0F0F0 F0F4D7E4 C2E2C5E7 D4D74BE2
 *QRSTUVWXYZABCDEF000004PUBSEXMP.S*
 0100 C1D44BE2 F0F1C1C2 C3C4C5C6 C7C8C9D1 D2D3D4D5 D6D7D8D9 E2E3E4E5 E6E7E8E9
 *AM.S01ABCDEFGHIJKLMNOPORSTUVWXYZ*
 0120 C1C2C3C4 C5C6C7C8 C9D1D2D3 D4D5D6D7 D8D9E2E3 E4E5E6E7 E8E9C1C2 C3C4C5C6
 *ABCDEFGHIJKLMNOPQRSTUVWXYZABCDEF*
 0140 F0F0F0F0 F0F5D7E4 C2E2C5E7 D4D74BE2 C1D44BE2 F0F1C1C2 C3C4C5C6 C7C8C9D1
 *000005PUBSEXMP.SAM.S01ABCDEFGHIJ*
 0160 D2D3D4D5 D6D7D8D9 E2E3E4E5 E6E7E8E9 C1C2C3C4 C5C6C7C8 C9D1D2D3 D4D5D6D7
 *KLMNOPQRSTUVWXYZABCDEFGHIJKLMNOP*
 0180 D8D9E2E3 E4E5E6E7 E8E9C1C2 C3C4C5C6
*ORSTUVWXYZABCDEF
ADRO06I (001)-STEND(02), 1999.211 14:55:44 EXECUTION ENDS
ADR013I (001)-CLTSK(01), 1999.211 14:55:44 TASK COMPLETED WITH RETURN CODE 0000
ADRO12I (SCH)-DSSU (01), 1999.211 14:55:44 DFSMSDSS PROCESSING COMPLETE. HIGHEST
        RETURN CODE IS 0000
```

Figure 18. Output Resulting from a PRINT Command

#### RELEASE command for DFSMSdss

The RELEASE command releases allocated but unused space from all eligible sequential, partitioned, and extended-format VSAM data sets that pass INCLUDE, EXCLUDE, and BY filtering criteria. The RELEASE command does not release space from guaranteed-space VSAM extended-format data sets. DFSMSdss only selects data sets that have space that can be released.

DFSMSdss offers two ways to process RELEASE commands:

Logical processing operates on a single selected data set at a time. The data set
can be multivolume. The user has the option to not specify volumes or to
specify one or more volumes with the LOGDDNAME, LOGDYNAM, or
STORGRP keywords. Releasing unused space from extended-format VSAM data
sets requires logical processing.

If no input volumes are specified and the INCAT keyword is not specified, DFSMSdss selects from all data sets cataloged in the catalogs accessible through the standard search order. For INCAT keyword details, see the INCAT keyword description in this section.

## **RELEASE Command for DFSMSdss**

 Physical processing operates on all selected data sets that reside on a single volume. The user must specify one or more volumes with the DDNAME or DYNAM keywords. You cannot use physical processing to release unused space from extended-format VSAM data sets.

To process multivolume data sets, do one of the following:

- Specify no input volumes.
- · Specify LOGDDNAME, LOGDYNAM, or STORGRP with an appropriate SELECTMULTI option or a volume list.
- Specify DDNAME or DYNAM with the volume or volumes on which the data set has space that can be released.


You must exclude, by using the EXCLUDE keyword, data sets whose last used block pointer in the data set's VTOC entry are not properly maintained. This can occur if you use an access method other than BSAM, QSAM, or BPAM. DFSMSdss does not release any space for data sets that are empty (the last used block pointer in the data set's VTOC entry is zero). This restriction does not apply to PDSE data sets; used space in PDSE data sets is maintained internally, rather than by reference to the data set's VTOC entry.

The following apply to the RELEASE command:


- A data set with the maximum number of extents already in use will not have any space released. For an extended-format VSAM data set, the maximum is 255 extents. For a partitioned data set extended (PDSE) and an extended-format sequential data set, the maximum is 123 extents. For other partitioned and sequential data sets, the maximum is 16 extents.
- For extended-format VSAM data sets, DFSMSdss releases space from only the data component of a base cluster or an alternate index (AIX).
- For striped VSAM data sets, DFSMSdss releases eligible space from each stripe.
- Free tracks in cylinder-allocated extents are not released. Only free cylinders are
- DFSMSdss excludes system data sets beginning with SYS1, unless the PROCESS keyword is used.
- DFSMSdss logical processing releases space from each volume on which an extended-format sequential data set contains data.
- DFSMSdss does not support the release of HFS data sets, as the DADSM PARTREL macro no longer supports HFS data sets.
- DFSMSdss does not support the release of zFS data sets.

For additional information about filtering, see Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259.

# RELEASE syntax for physical processing




## **RELEASE Command for DFSMSdss**




# **RELEASE** syntax for logical processing




## A: Additional Keywords for Physical or Logical Processing:



## **B: Optional Keywords for Physical or Logical Processing:**




## C: Optional Keywords with RELEASE for Logical Processing:



443

## **RELEASE Command for DFSMSdss**



# **Explanation of RELEASE command keywords**

This section describes the keywords for the RELEASE command.

## **ADMINISTRATOR**



ADMINISTRATOR allows you to act as a DFSMSdss-authorized storage administrator for the RELEASE command. DFSMSdss-initiated access checking to data sets and catalogs is bypassed. If you are not authorized to use the ADMINISTRATOR keyword, the command ends with an error message.

To use the ADMINISTRATOR keyword, all of the following conditions must be true:

- FACILITY class is active.
- Applicable FACILITY-class profile is defined.
- You have READ access to that profile.

For additional information about using the ADMINISTRATOR keyword, see "ADMINISTRATOR keyword" on page 541.

## BY



BY specifies that the data sets selected up to this point, by the processing of the INCLUDE and EXCLUDE keywords, are to be further filtered. To select the data set, all BY criteria must be met. See the separate discussions of INCLUDE and EXCLUDE for information on how these keywords are specified.

Note: You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

For additional information about the BY keyword, see "INCLUDE" on page 446 and "EXCLUDE" on page 445.

#### **DDNAME**



DDNAME requests physical processing.

ddn Specifies the name of the DD statement that identifies a volume whose sequential and partitioned data sets, if selected, are to have their unused space released. To assure correct processing, each of the DD statements corresponding to a DDname (ddn) must identify only one volume serial number.

## **DYNALLOC**




DYNALLOC specifies dynamic allocation, instead of the ENQ macro, to serialize the use of data sets. This allows cross-system serialization in a JES3/MVS environment.

#### Consider:

- This serialization is of value only when the dynamic allocation/JES3 interface is not disabled.
- Run time increases when you use DYNALLOC to serialize data sets (as opposed to enqueue) because overhead is involved in dynamic allocation and serialization across multiple processors.

#### **DYNAM**



DYNAM requests physical processing and specifies that the volume to be processed be dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*). Using DYNAM instead of DD statements to allocate DASD volumes will not appreciably increase run time and permits easier coding of JCL and command input.

volser Specifies the volume serial number of a DASD volume to be processed.

*unit* Specifies the device type of a DASD volume to be processed. This parameter is optional.

## **EXCLUDE**



dsn Specifies the name of a data set to be excluded from the data sets selected by INCLUDE. Either a fully or a partially qualified data set name can be used. See the separate discussions of INCLUDE and BY for information on how these keywords are specified.

**Note:** You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

For more information, see "BY" on page 444 and "INCLUDE" on page 446.

## **INCAT**



INCAT(catname) specifies that DFSMSdss search the user catalogs specified by the INCAT(catname) keyword, then follow the standard search order to locate data sets. INCAT(catname) allows you to identify specific source catalogs. To specify INCAT, RACF authorization might be required.

catname

Specifies a fully qualified catalog name.

#### **ONLYINCAT**

Specifies that DFSMSdss only searches catalogs that are specified in the INCAT catalog name list.

DFSMSdss does not process an SMS-managed data set that is cataloged outside the standard search order. This is the case even if the data set is cataloged in one of the catalogs that is specified with the INCAT(catname) keyword. Ensure that the SMS-managed data sets are cataloged under standard catalog search order.

## **INCLUDE**




dsn Specifies the name of a data set whose unused space is eligible to be released. Either a fully or a partially qualified data set name can be used. See "Filtering by data set names" on page 260. If INCLUDE is omitted (but EXCLUDE or BY is specified) or if INCLUDE(\*\*) is specified, all data sets are eligible to be selected for releasing.

Note: You must use FILTERDD when you have more than 255 entries in INCLUDE, EXCLUDE, or BY list keywords.

For more information, see "BY" on page 444 and "EXCLUDE" on page 445.

## LOGDDNAME




LOGDDname specifies logical processing that is based on a designated volume list.

Specifies the name of the DD statement that identifies a single volume that ddn contains the data sets to be released by logical processing. You can specify

up to 255 DDNAME entries with the LOGDDNAME keyword. Each DD statement can correspond to only one volume serial number.

For more information see "SELECTMULTI" on page 449 and "LOGDYNAM."

#### **LOGDYNAM**



LOGDYNAM requests logical processing and specifies that the volumes that contain the data sets to be processed are dynamically allocated.

volser Specifies the volume serial number of a DASD volume to be dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number by using an asterisk(\*). You can specify up to 511 volumes with the LOGDYNAM keyword.

*unit* Specifies the device type of a DASD volume to be processed. This parameter is optional.

#### **SELECTMULTI**

Specifies how DFSMSdss selects cataloged multivolume data sets. DFSMSdss accepts SELECTMULTI only when you specify logical processing with the LOGDDNAME, LOGDYNAM, or STORGRP keyword. Otherwise, DFSMSdss cannot accept the specification of SELECTMULTI.

- **ALL** Specifies that DFSMSdss *not process* a multivolume data set unless the following criteria is met:
  - The volume list created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword must list all the volumes that contain a part of the data set.
  - The volume list created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword must list all the volumes that contain a part of the VSAM cluster.

ALL is the default.

- **ANY** Specifies that DFSMSdss process a multivolume data set when the following criteria are met:
  - Any volume specified in the volume list that is created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword must contain a part of the data set.
  - Any volume specified in the volume list that is created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword must contain a part of the VSAM cluster.

FIRST Specifies that DFSMSdss process a multivolume data set only when the volume list includes the volume that contains the first part of the data set. The volume list is created by the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword. For VSAM data sets, the volume list must include the volume that contains the first extent of the data component for the cluster.

Notes for LOGDDNAME, LOGDYNAM and STORGRP keywords:

## **RELEASE Command**

- 1. If the LOGDDNAME, LOGDYNAM, or STORGRP keyword is not specified, DFSMSdss selects from all data sets cataloged in the catalogs accessible through the standard search order.
- If the LOGDDNAME, LOGDYNAM, or STORGRP keyword is specified, DFSMSdss still uses the standard catalog search order, but it selects data sets only from the specified volumes.
- 3. A multivolume data set that has extents on volumes is processed when you specify the SELECTMULTI keyword if the following criteria are met:
  - The volumes cannot be designated on the volume list created by the LOGDDNAME, LOGDYNAM, or STORGRP keyword.
  - You must specify the SELECTMULTI keyword option (ANY or FIRST) to release a multivolume data set that has extents on volumes which are not identified with the LOGDDNAME, LOGDYNAM, or STORGRP keyword.

# **MINSECQTY**



Because DFSMSdss releases all the allocated but unused space when you have not specified a secondary allocation quantity, you will not be able to add records to the data set after the release operation. MINSECQTY solves this problem. The release operation is not performed unless the secondary allocation quantity in the VTOC (VVDS for extended-format VSAM) is equal to or greater than n tracks and the data set has not reached the maximum number of used extents (16 extents for sequential and partitioned data sets, 123 extents for extended-format sequential data sets and PDSEs, or 255 extents for extended-format VSAM data sets). The letter n represents a 1-to-8-digit decimal number with a range from zero to 99999999. The default is one track, if you do not specify MINSECQTY (n).

### **MINTRACKSUNUSED**




MINTRACKSUNUSED specifies that the release operation is to be performed only if the number of unused tracks for a selected data set is equal to or greater than n(n is a 1-to-8-digit decimal number with a range from 0 to 99999999). When you do not specify MINTRKS, DFSMSdss uses a default value of 1. All unused tracks will be released if you perform a release operation.

## **ONLYINCAT**

See "INCAT" on page 339.

## **PASSWORD**



PASSWORD specifies the passwords DFSMSdss uses for selected password-protected sequential and partitioned data sets. (Password checking is bypassed for RACF-protected data sets.) This keyword is required only if:

- You do not have the required volume-level RACF DASDVOL or RACF DATASET access.
- The installation authorization exit does not bypass the checks.

**Note:** You should specify the passwords for all data sets that do not have RACF protection but do have password protection. During processing, a utility invoked by DFSMSdss may have to prompt the operator for a password. You can control authorization checking by using the installation authorization exit.

ddn Specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set that contains data set names and their passwords. This data set must contain card-image records in DFSMSdss command syntax format.

dsn/pswd

dsn is a fully qualified data set name. pswd is its password. If no password follows the slash (/), dsn is treated as though it were ddn.

Printing of actual data set passwords specified in your input command stream is suppressed in the SYSPRINT output.

For additional information about the installation authorization exit, see *z*/*OS DFSMS Installation Exits*.

## **PROCESS**



PROCESS specifies that the release operation is to be performed for data sets with a high-level qualifier of SYS1. To specify PROCESS(SYS1), RACF authorization may be required.

For additional information about RACF authorization, see the Chapter 5, "Protecting DFSMSdss functions," on page 27.

## **SELECTMULTI**

See "LOGDDNAME" on page 446, "LOGDYNAM" on page 447, and "STORGRP" on page 450.


## **SPHERE**



SPHERE specifies that DFSMSdss also select all associated alternate index clusters whenever you select a VSAM base cluster. You do not need to specify individual names of sphere components, only the base cluster name. If you specify a volume list (with LOGDDNAME or LOGDYNAM), you do not need to specify the volumes on which the AIX clusters reside.

To select an entire sphere, specify the base cluster name by using fully or partially qualified data set names. If you specify SPHERE but not the base cluster name, DFSMSdss processes only those data components of the sphere whose names are specified.

## **STORGRP**



STORGRP specifies that all of the online volumes in the storage group be dynamically allocated. If a volume in the storage group is not online, that volume is not used for processing. You can specify up to 255 storage group names. Specifying STORGRP with a storage group name is equivalent to specifying LOGDYNAM or LOGDDNAME with all the online volumes in the storage group included in the list.

You can specify the STORGRP keyword with the SELECTMULTI keyword, but STORGRP cannot be specified at the same time with the DDNAME, DYNAM, LOGDDNAME, or LOGDYNAM keywords.

#### Notes for LOGDDNAME, LOGDYNAM, and STORGRP keywords:

- 1. DFSMSdss selects from all data sets that are cataloged in the catalogs that are accessible through the standard search order if you do not specify the LOGINDDNAME, LOGINDYNAM, or STORGRP keyword.
- 2. When you specify the LOGDDNAME, LOGDYNAM, or STORGRP keyword, DFSMSdss still uses the standard catalog search order. However, DFSMSdss selects data sets only from the specified volumes.
- 3. You can process a multivolume data set that has extents on volumes when you specify the SELECTMULTI keyword if the following criteria are present:
  - The volumes cannot be designated on the volume list that is created by the LOGDDNAME, LOGDYNAM, or STORGRP keyword.
  - You must specify the SELECTMULTI keyword option (ANY or FIRST) to release a multivolume data set that has extents on volumes which are not identified with the LOGDDNAME, LOGDYNAM, or STORGRP keyword.

For more information about the SELECTMULTI keyword, see "LOGDYNAM" on page 447.

## WAIT



WAIT specifies to DFSMSdss the length of a wait in seconds and the number of retries to obtain control of a data set.

#### numsecs

Specifies a decimal number from 0 to 255 that designates the interval, in seconds, between retries.

#### numretries

Specifies a decimal number from 0 to 99 that designates the number of retries to gain control of a data set.

The default for *numsecs,numretries* is (2,2), which specifies two retries at 2-second intervals. If you do not want to wait for a resource, specify 0 for either numsecs or numretries.

**Note:** The WAIT keyword does not control wait/retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is 3 seconds and the default retry count is 30. This results in a total wait time of 90 seconds.

For information about controlling the wait/retry attempts for system resources, see the "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

# Example of a release operation

The following is an example of a release operation on selected sequential and partitioned data sets.

```
//JOB1 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
RELEASE INCLUDE(**) -
DYNAM(338000) /* DYNAM ALLOC VOL 338000 */-
MINTRKS(10) /* THERE ARE 10 OR MORE UNUSED TRKS */-
/* MINSEC NOT SPEC. IT DEFAULTS TO 1 */
```

Unused tracks of sequential and partitioned data sets on volume 338000 are to be released if both:

- The number of unused tracks in the data set is greater than or equal to 10.
- The data set can be extended later if required (MINSEC(1)). This need not be specified, because it is the default.

The above example can be modified as follows to release unused tracks of all sequential and partitioned data sets, other than system data sets, that have any unused tracks and that can be extended:

```
//SYSIN
RELEASE INCLUDE(**)
   DYNAM(338000)
                       /* DYNAM ALLOC VOL 338000 */
```

The following is an example of the commands used to release unused space from extended-format VSAM data sets residing wholly or in part on a specific volume, and to release unused space from the data sets' alternate indexes that reside on any volumes:

```
//SYSIN
             DD
RELEASE INCLUDE(**) -
  BY(DSORG EQ VSAM) /* RELEASE ONLY VSAM
 LOGDYNAM(339000) /* DYN ALLOC VOL 339000 */-
SELECTMULTI(ANY) /*EVEN IF MULTIVOL */-
                  /* RELEASE AIXES
```

To release unused space from all eligible data sets that are cataloged in a particular user catalog, without specifying any volume:

```
//SYSIN
          DD
RELEASE INCLUDE(**)
 INCAT (CATALOGA) ONLYINCAT /* ONLY FROM CATALOG */
```

# RESTORE command for DFSMSdss

With the RESTORE command, you can restore data to DASD volumes from DFSMSdss-produced dump volumes. You can restore data sets, an entire volume, or ranges of tracks. You can restore to unlike devices from a logical dump tape.

The FULL keyword with the RESTORE command restores an entire DASD volume. The TRACKS keyword for the RESTORE command restores a range of tracks.

DFSMSdss offers two ways to process RESTORE commands:

- Logical processing is data set-oriented, which means it operates against data sets independently of physical device format.
- Physical processing can operate against data sets, volumes, and tracks, but is oriented toward moving data at the track-image level.

The processing method is determined by what type of dump tape is used as input and by the keywords specified on the command.

Target data set allocation differs between a physical data set and logical data set restore of non-VSAM data sets. Logical data set restore allocates target data sets according to the amount of used space in the source data set, thereby freeing unused space. Physical data set restore preserves the original size of the source data set. To force unused space to be kept during logical data set restore, the ALLDATA or ALLEXCP keyword must be specified during a dump. However, the action that restore takes with respect to these keywords depends on data set characteristics and device characteristics. If you require that all of the unused space is restored, then you should be sure that the data set is restored to a like device

#### **RESTORE Command for DFSMSdss**

type and not reblocked or compressed. Compress is the default for PDS data sets on restore unless you use the NOPACKING keyword.

DFSMSdss logical restore processing cannot be used to process partitioned data sets containing location-dependent information that does not reside in note lists or in the directory.

Extended-physical-sequential data sets, VSAM extended-format data sets, and SAM compressed extended function data sets cannot be restored to non-SMS-managed target volumes during a physical or logical data set restore. Data sets with DFM attributes (created by DFM/MVS) can be restored to non-SMS-managed target volumes but the DFM attributes will be lost and a warning message will be issued.

For more information about using the RESTORE command, see Chapter 6, "Managing availability with DFSMSdss," on page 33.

# Special considerations for RESTORE

The following special considerations apply when you perform a restore operation:

- When restoring a partitioned data set that has a secondary allocation of zero, the amount of unused space allocated to the target data set might be different from that of the source data set if the ALLDATA and ALLEXCP keywords were not specified for the dump.
- When restoring a VSAM data set with no secondary allocation, a secondary allocation can be added as follows:
  - When the primary allocation is less than one cylinder, a secondary allocation equal to the primary is created.
  - When the primary allocation is greater than or equal to one cylinder, a secondary allocation is created by computing one percent of the primary and rounding up to the next cylinder (in tracks).

The index component can also have secondary space added if it has no secondary allocation.

- The RESTORE FULL or RESTORE TRACK commands might invoke ICKDSF to rebuild the VTOC INDEX data set for a target volume. Therefore, users of these commands require the appropriate authority for ICKDSF.
- When performing a logical or physical data set restore operation of a VSAM extended-format data set, the target data set allocation must be consistent with the source data set allocation as follows:
  - If the source is an extended-format VSAM, then the target must be an extended-format VSAM.
  - If the source is a compressed VSAM KSDS, then the target must be a compressed VSAM KSDS.
  - If the source is an alternate index for an extended-format KSDS, then the target must be an alternate index for an extended-format KSDS.
  - The target control interval size must be equal to the source.
- The actions DFSMSdss performs for RENAME, RENAMEUNCONDITIONAL, REPLACE, or REPLACEUNCONDITIONAL depend on the keywords you specify and the configurations of data sets on volumes. This section contains figures that describe specific environments for DFSMSdss restore operations.
- If you restore a data set that has an F8/F9 DSCB pair on the volume from which it is dumped to a volume that does not support F8/F9 DSCBs, the attributes in the F9 DSCB are lost. To retain these extended attributes, the target volumes of the RESTORE must support F8/F9 DSCBs.

# Data integrity considerations for full or tracks restore operations

For a full or tracks restore operation, DFSMSdss serializes the VTOC to prevent DADSM functions such as ALLOCATE, EXTEND, RENAME, and SCRATCH from changing the contents of the VTOC on the volume during the restore operation. Data sets are not serialized on these restore operations and thus, some data sets can be opened by other jobs during the restore operations. The result might be that partially updated data sets are restored. Full data integrity can always be guaranteed by performing restore operations by data set only when TOLERATE(ENQFAILURE) or SHARE is not specified.


During full or tracks restore operations, and stand-alone restore, it is possible to duplicate a volume serial number in the sysplex. If there is data in the coupling facility for the duplicated volume serial number, data integrity can be compromised. The recommended procedure before restoring a suspected volume is as follows:

- 1. Use the D SMS,CFVOL(volid) command to determine if there is any data in the coupling facility caches for the volume serial number to be restored.
- 2. Determine the disposition of any data that is in the caches.
- 3. Do not restore the suspected volume until the duplicated volume can be varied offline to the sysplex, thus ensuring that there is no data in any coupling facility cache for the duplicated volume.


During full or tracks restore operations, DFSMSdss resets the data-set-changed indicator for each data set being restored. Because the data set has not changed since the backup was performed, DFSMSdss resets the data-set-changed indicator.

Use caution when using DFSMSdss Full Volume Restore in an environment in which other data set applications or backup applications are used. If the applications rely on the data-set-changed indicator to mean that the data set has not changed since earlier processing, a data integrity issue can result when using DFSMSdss to Restore full volumes when other applications are tracking the data sets on that volume.


# RESTORE FULL and RESTORE TRACKS command syntax



#### A: RESTORE FULL Command Optional Keywords:




# **B: RESTORE TRACKS Command Optional Keywords:**




# RESTORE DATASET command syntax for logical data set




## C: Additional Keywords Used for Logical Data Sets:




# D: Optional Keywords Used for Logical Data Sets:






RSA(label)


# RESTORE DATASET command syntax for physical data set




# E: Additional Keywords for Physical Data Sets:



# F: Optional Keywords Used for Physical Data Sets:





# **Explanation of RESTORE command keywords**

This section describes the keywords for the RESTORE command.

## **ADMINISTRATOR**



The ADMINISTRATOR keyword allows you to act as a DFSMSdss authorized storage administrator for the RESTORE command. For administrators, DFSMSdss bypasses access checking for data sets and catalogs.

To use the ADMINISTRATOR keyword, all of the following conditions must be true:

- FACILITY class is active.
- Applicable FACILITY-class profile is defined.
- You have READ access to that profile.

If you are not authorized to use the ADMINISTRATOR keyword, the command ends with an error message.

For more details, see "ADMINISTRATOR keyword" on page 541.

Requirement: You must also specify the ADMINISTRATOR keyword with CPVOLUME because DFSMSdss cannot check access authorization for VM data.

#### AUTORELBLOCKADDRESS



AUTORELBLOCKADDRESS specifies that direct access data sets are to be automatically processed as being organized by relative block address provided that they were accessed with an OPTCD setting indicating relative block addressing. These direct access data sets are to be processed by relative block address rather than by TTR, and without maintaining the relative track and record number for each record. The blocks must fit on the tracks of the target volume.

#### Note:

- 1. If any such data set is actually organized by TTR, the data set might become unusable.
- 2. The TTRADDRESS keyword takes precedence over the AUTORELBLOCKADDRESS keyword. Refer to the RELBLOCKADDRESS and TTRADDRESS keywords for more information.
- 3. AUTORELBLOCKADDRESS is ignored for direct access data sets with variable records formats or with standard user labels.

For more information about OPTCD, see z/OS DFSMS Macro Instructions for Data Sets.

# **BCSRECOVER**



BCSRECOVER facilitates recovery of pre-allocated logical data sets. The BCSRECOVER parameter applies to both RLS and non-RLS catalogs. You must specify one of the following subparameters:

#### BCSRECOVER(LOCK)

specifies a serialized close of user catalogs.

#### **BCSRECOVER(SUSPEND)**

specifies that access to the catalog is suspended from all systems in the sysplex.

As part of BCSRECOVER processing, DFSMSdss automatically unlocks and resumes the catalog.

#### Note:

- 1. Programs using BCSRECOVER require READ access to RACF FACILTY CLASS resource IGG.CATLOCK.
- **2**. If a user catalog is locked or suspended using IDCAMS or the MODIFY CATALOG command, the system ignores the BCSRECOVER keyword..

#### BY



BY specifies that the data sets selected up to this point, by the processing of the INCLUDE and EXCLUDE keywords, are to be further filtered. To select the data set, *all* BY criteria must be met.

For more information, see:

- "Filtering by data set characteristics" on page 262.
- "EXCLUDE" on page 467.
- "INCLUDE" on page 470.

#### **BYPASSACS**



BYPASSACS specifies that Automatic Class Selection (ACS) routines are not to be invoked to determine the target data set's storage class or management class names. To specify BYPASSACS, RACF authorization might be required.

dsn Specifies a fully or partially qualified data set name.

If a data set is being renamed, the old name must be specified.

**Note:** If BYPASSACS(dsn) is specified, all data sets that pass the BYPASSACS selection criteria are guaranteed the specified storage class. The combination of NULLSTORCLAS and BYPASSACS(dsn) forces the selected data sets to be non-SMS managed.

For more information about RACF authorization, see Chapter 5, "Protecting DFSMSdss functions," on page 27. For more information about data set names, see "Filtering by data set names" on page 260.

## **CANCELERROR**



CANCELERROR specifies that the restore function be ended for a permanent read error, or that the restore of a data set be ended for a write error.

- Permanent read error (permanent I/O error):
  - If CANCELERROR is specified, the restore task is ended. If this keyword is not specified, DFSMSdss attempts to recover from the input errors, but the results can be unpredictable as a result of the difficulty in repositioning and assembling the data.
- Write error, such as an invalid track format:

For data set restore, processing of the data set ends and the target data set is deleted. The restore operation continues with the next data set. For full volume and tracks restore, processing for the volume ends. Subsequent tracks are not

DFSMSdss allows you to change this default operation. A patch byte is provided to allow you to change the default handling of invalid tracks created during RESTORE processing.

CANCELERROR has no effect on the following types of errors on a DASD volume:

- Equipment check
- Command reject
- Intervention required
- Busout parity

For more information about the patch bytes, see Chapter 14, "DFSMSdss patch area," on page 217.

# CATALOG or RECATALOG



For a logical restore operation, CATALOG instructs DFSMSdss to catalog data sets that it allocates. For a physical restore operation, CATALOG is used for non-VSAM single volume data sets; RECATALOG is ignored. DFSMSdss does not catalog VSAM data sets during physical restore. If the CATALOG keyword is specified, it is ignored when processing VSAM data sets. You must use IDCAMS DEFINE RECATALOG to catalog the data sets after the physical restore.

#### **CATALOG**

catalogs the target data set in a catalog as determined by the standard catalog search order. This is the default for VSAM data sets, multivolume data sets, and SMS-managed data sets (during logical data set restore). It is also the default for single-volume, non-VSAM, SMS-managed data sets (in physical data set restore).

## **RECATALOG**(newcatname)

catalogs the target data set in the newcatname catalog.

#### RECATALOG(\*)

catalogs the target data set in the same catalog that points to the source data set. If the source data set was not cataloged, the new data set is not cataloged either.

#### Note:

- 1. CATALOG or RECATALOG fails if the target data set is already cataloged in the same catalog and RENAME is not specified.
- 2. CATALOG and RECATALOG are ignored when the target data set is preallocated.
- 3. RECATALOG is ignored for SMS-managed data sets.
- 4. Be careful when using RECATALOG(newcatname) because the target data set might already be cataloged outside of the standard order of search.
- 5. If RECATALOG is specified for a physical restore it is ignored. DFSMSdss does not attempt to catalog the data set. If the data set is already cataloged on another volume:
  - The catalog entry is not updated, and
  - The data set is restored, but it is not cataloged.
- 6. If CATALOG is specified for a physical restore of a single-volume non-VSAM data set, DFSMSdss attempts to catalog the data set. If the data set is already cataloged on another volume:
  - Message ADR385E, reason code 08, is issued,
  - The catalog entry will not be updated, and
  - The data set will be restored, but it will not be cataloged.
- DFSMSdss physical data set restore does not create catalog entries for VSAM, multivolume non-VSAM, or preallocated data sets. The user must create all catalog entries.
- 8. For multivolume non-VSAM data sets, use IDCAMS DEFINE NONVSAM.

## **COPYVOLID**



COPYVOLID specifies that the volume ID from the dumped DASD volume is to be copied to the output DASD volume. This applies to a full restore operation; it applies to a tracks restore only if track 0 (zero) is to be restored.

When the volume serial number on a DASD volume is changed, the operator is notified. The operating system then initiates either:

- A demount if there is another volume with the same serial number
- A mount to get the volume with the new serial number mounted

This might change the mount attributes of the volume. You should exercise operating precautions if there are two or more processors sharing the same DASD volume.

When the volume serial number is changed by using a COPYVOLID keyword or when both the dumped volume and the restored volume have different serial

numbers, profiles are not built for the RACF-protected data sets on the restored volume or for the RACF DASDVOL for RACF-protected DASD volumes.

#### Note:

- 1. If you are doing a full restore operation and the input has VSAM data sets, the VOLID must be copied.
- 2. The COPYVOLID keyword is required for a full-volume restore operation of SMS-managed source volumes.
- 3. Exercise caution using the COPYVOLID keyword in a multiple task job step when two or more of the tasks are using the same output volume. If the output volume is made unavailable by the first task, all succeeding tasks that use the same output volume will fail.

## **CPVOLUME**



CPVOLUME specifies that the output volume is a VM-format volume and that the OS-compatible VTOCs must begin on track zero, record five. You must specify the track range to be copied with the TRACKS keyword, as the OS-compatible VTOCs do not describe the extents of any data on the volume. You must also specify the ADMINISTRATOR keyword with CPVOLUME because DFSMSdss cannot check access authorization for VM data.

## **DATASET**



DATASET specifies a data set restore operation, using filtering.

Note: Either the FILTERDD, INCLUDE, EXCLUDE, or BY keyword must be used when DATASET is selected.

For more information about filtering, see Chapter 16, "DFSMSdss filtering—choosing the data sets you want processed," on page 259.

#### **DEBUG**



DEBUG(SMSMSG) instructs DFSMSdss to display ACS WRITE statements to the job output.

#### DELETECATALOGENTRY



DELETECATALOGENTRY specifies that the user wants to perform a disaster recovery and that the existing catalog entries for the target data sets might no longer be valid. If a target data set is cataloged but not available, then DFSMSdss performs a DELETE NOSCRATCH operation for the data set.

Specifying the DELETECATALOGENTRY command requires proper RACF facility class authorization.

For more information about RACF, see *z/OS DFSMSdss Storage Administration*. For more information about protecting keywords with RACF, see *z/OS Security Server RACF Security Administrator's Guide*.

**Caution**: Use extreme care with the DELETECATALOGENTRY keyword. If any of the following conditions exist, a DELETE NOSCRATCH operation is performed:

#### Condition 1

The target data set is cataloged but it is not found on the volume indicated by the catalog.

#### Condition 2

The target data set is cataloged but the volume indicated by the catalog does not exist on the restoring system and the restoring system is not sharing catalogs with another system.

#### Condition 3

The target data set is cataloged but the volume indicated by the catalog is offline on the restoring system and the restoring system is not sharing catalogs with another system.

#### Condition 4

The target data set is cataloged but the volume indicated by the catalog does not exist on the restoring system and the restoring system is sharing catalogs with another system.

#### Condition 5

The target data set is cataloged but the volume indicated by the catalog is offline on the restoring system and the restoring system is sharing catalogs with another system.

# Condition 6

The target data set is a multivolume data set and some, but not all of the data, is no longer available. For this purpose, a multivolume data set is one in which any part of the data set resides on more than one volume. Examples include the following:

- A VSAM KSDS with the data- and index-components on one volume and an alternate index (AIX) on another volume.
- A VSAM KSDS with the index-component on a different volume than the data-component.
- A key-range VSAM data set with the key-ranges residing on more than one volume.

For conditions 1 and 2, it is appropriate to use DELETECATALOGENTRY to have DFSMSdss perform a DELETE NOSCRATCH operation for the catalog entries.

Condition 1 typically occurs during a disaster recovery when DFSMSdss restores or imports the catalogs before recovering the data sets. The target data set does not exist on the volumes indicated by the catalog. The restore will not be successful unless you or DFSMSdss delete the data set entries in the catalogs.

Condition 2 typically occurs during a disaster recovery when DFSMSdss restores the data sets to different volumes on a different operating system. DFSMSdss catalogs the target data sets, but points to volumes that do not exist on the target system. The restore will not be successful unless you or DFSMSdss delete the data set entries in the catalogs.

If you specify DELETECATALOGENTRY for conditions 3 through 6, the following damage is most likely to occur:

- Condition 3 typically occurs during a disaster recovery when DFSMSdss restores the data sets to different volumes on a different operating system. DFSMSdss cataloged the target data sets, but points to offline volumes on the target system. The restore will not be successful unless you or DFSMSdss delete the data set entries in the catalogs.
- Condition 3 can also occur in any environment where volumes are varied on and offline.
  - If you specify DELETECATALOGENTRY and then vary the volume back online, you might find that there are two copies of a data set: the original data set on the volume that was varied offline and the restored data set. DFSMSdss will no longer catalog the original data set.
- Conditions 4 and 5 typically occur in a shared system environment with a nonsymmetric system configuration. The following examples apply:
  - There are shared catalogs between two systems.
  - A data set is dumped from system A, but restored into system B.
  - The data set is cataloged in system A in a catalog that is shared by system B.
  - The volume containing the data set and, if applicable, its VVDS is on system A and is unavailable to system B.
    - Restriction: If you specify DELETECATALOGENTRY and then vary the volume back online, you might find that there are two copies of a data set: the original data set on the volume that was varied offline and the restored data set. If this happens, DFSMSdss can no longer catalog the original data set.
- DFSMSdss attempts to detect Condition 6 and issues an error message instead of performing the DELETE NOSCRATCH. However, it will not always be possible to do so. In that event, the DELETE NOSCRATCH is performed and DFSMSdss attempts to restore the data set with one of the following results:
  - DFSMSdss successfully restores the data set, and there is no residual data from the original data set. In this case, there is nothing further for you to do.
  - DFSMSdss successfully restores the data set, but there is residual data from the original data set. Although DFSMSdss restored the data set, you might find, for example, that there is an uncataloged AIX from the original data set. In this case, you will have to perform other corrective actions. These are the same actions that you would have had to perform even if you had not used the DELETECATALOGENTRY keyword.
  - An error occurs during the restore that prevents the data set from being restored. The error results from the fact that the data set was only partially missing. For example, residual data and the VSAM Volume Record (VVR) might exist on a second volume. When the data set that is being restored is extended to that volume, a duplicate entry condition is created. Again, if this occurs, you will have to perform other corrective actions before you can successfully restore the data set.

#### Note:

1. Use DELETECATALOGENTRY only for logical data set restore.

- Do not use DELETECATALOGENTRY to restore partially damaged volumes or data sets.
- 3. You cannot use DELETECATALOGENTRY to delete catalog entries for any of the following:
  - · User catalogs.
  - Migrated data sets (VOLSER=MIGRAT).
  - The SYSRES volume (VOLSER=\*\*\*\*\*).
  - A data set for which the volser(s) in the catalog do not match either the source volser(s) from the dump tape or the target volser(s) specified with OUTDD/OUTDYNAM.
- 4. If you are performing a disaster recovery and the original volumes are not available on the restoring system, you should also specify the IMPORT parameter. If you do not specify the IMPORT keyword, the system might prompt you to mount the volumes on which the target data resides (as indicated by the catalog). Even if you reply 'CANCEL', DFSMSdss attempts to perform a DELETE NOSCRATCH on the data set because it does not recognize the 'CANCEL' request. Even if the DELETE NOSCRATCH is successful, DFSMSdss might cause the following results:
  - DFSMSdss might fail to allocate the volume
  - DFSMSdss might issue the message ADR405E
  - DFSMSdss might not restore the data set
- 5. DELETECATALOGENTRY will not delete any catalog entry when the phantom entry indicates a different type of data set than the source data set.

# **DYNALLOC**



DYNALLOC specifies that DFSMSdss is to use dynamic allocation, instead of enqueue, to serialize the use of data sets. This allows cross-system serialization in a JES3/MVS environment. The following conditions apply to DYNALLOC: refids="b370\_13">

- The serialization is of value only when the dynamic allocation/JES3 interface is *not* disabled.
- Run time increases when you use DYNALLOC to serialize data sets (as opposed to enqueue). This is because overhead is involved in a dynamic allocation and serialization across multiple processors.

## **EXCLUDE**



dsn Specifies the name of a data set to be excluded from the data sets selected by INCLUDE. Either a fully or a partially qualified data set name can be used.

For more information, see:

- "BY" on page 461,
- "INCLUDE" on page 470.

Guideline: When data sets have location-dependent data, list their names in the EXCLUDE list. This prevents DFSMSdss from restoring them even if you use the FORCE keyword.


#### **FILTERDD**



ddn Specifies the name of the DD statement that identifies the sequential data set or member of a partitioned data set containing the filtering criteria to use. This is in the form of card-image records in DFSMSdss command syntax. It contains the keywords INCLUDE, EXCLUDE, and BY, completing the RESTORE command syntax.

Note: You must use FILTERDD when you have more than 255 entries in the INCLUDE, EXCLUDE, or BY list of subkeywords.

#### **FORCE**



For a logical data set restore operation, FORCE specifies that DFSMSdss allows an unmovable data set or a data set allocated by absolute track allocation to be moved.

#### Note:

- 1. Use the EXCLUDE keyword with the FORCE keyword when you are restoring data sets that have location-dependent data. Naming these data sets in the EXCLUDE list prevents DFSMSdss from restoring them even when you specify the FORCE keyword.
- 2. Specify the FORCE keyword with the REPLACE or REPLACEUNCONDITIONAL keyword if you want to restore the data from unmovable data sets whose extents do not match.

# **FORCECP**




FORCECP specifies that any checkpointed data sets resident on the SMS volume or volumes can be logically restored or that MVS checkpointed data sets can be physically restored. Checkpoint indications are removed from the data sets.

days Specifies a one-to-three digit number in the range of zero to 255. It also specifies the number of days that must have elapsed since the last referenced date before the data set can be restored.

**Note:** For IMS GSAM checkpointed data sets that are physically restored, FORCECP is not required, and checkpoint indications are not removed from the data sets regardless of whether or not FORCECP is specified.

## **FREESPACE**



FREESPACE specifies free space values for DFSMSdss-allocated target VSAM data sets. If this keyword is omitted, the control interval and control area free space are the same as the source data set.

- CI Specifies the percentage of freespace to be kept in each control interval during allocation of the data set.
- CA Specifies the percentage of freespace to be kept in each control area during allocation of the data set. When omitted, the control area free space is the same as the source data set.

#### **FULL**



FULL specifies that an entire DASD volume is to be restored. This is the default for the RESTORE command.

#### Note:

- 1. You cannot specify SHARE or TOL(ENQF) for FULL operations.
- 2. It is possible to duplicate a volume serial number during a restore FULL operation.

For more information about how to maintain data integrity when restoring a volume with FULL restore, see "Data integrity considerations for full or tracks restore operations" on page 454.

#### **IMPORT**



IMPORT specifies that the data sets that are being restored were dumped from a different system and they should be considered new data sets.

Because the restored data sets are new to the system, DFSMSdss modifies certain source data set processing. The following examples apply:

• DFSMSdss bypasses checking to see if you are authorized to read a data set with the same name as the one that was dumped.

If you are authorized to read the input dump data set that contains the data sets that are being restored, DFSMSdss considers that you have the authority to read any data set that is being restored. DFSMSdss continues to check to see that you are authorized to create a new target data set or replace an existing target data set.

If you are restoring the data set without renaming it, the restore might be unsuccessful. There are several common reasons for such a failure:

- You do not have sufficient authority to create a target data set with the same name as the source data set. You must obtain the required access authority to do so before you can restore the data set.
- A data set already exists with the same name as the source data set and you did not specify the REPLACE or REPLACEUNCONDITIONAL keyword. You must also specify the REPLACE or REPLACEUNCONDITIONAL keyword if you want the restore to replace an existing data set.
- A data set with the same name as the source data set is already cataloged, but is not available to the restoring system. You must make the volumes that contain the data set, and, as applicable, its VVDS, available to the restoring system before you can restore the data set.
- A catalog contains a phantom entry for a data set with the same name as the source data set. In this case, the data set does not exist on any volume. You can perform a separate DELETE NOSCRATCH operation for that data set name. Or you can specify the DELETECATALOGENTRY parameter to request that DFSMSdss perform a DELETE NOSCRATCH operation for you.

Attention: Do not use the DELETECATALOGENTRY keyword if the restoring system is sharing catalogs, but not the data set volumes, with another system.

 DFSMSdss can try to access a VVDS for a source data set in order to obtain information such as the resource owner. If you specify IMPORT, DFSMSdss suppresses a VVDS not available error.

To specify IMPORT, you must have the proper RACF facility class authorization.

#### Note:

- 1. IMPORT should be RACF-protected.
- 2. IMPORT is only supported for logical data set restore.
- 3. DELETECATALOGENTRY might have to be specified to successfully restore a data set with the old data set name.
- 4. When IMPORT is specified, DFSMSdss does not create a discrete data set profile unless the source data set is RACF-protected when it is dumped and you specify the MENTITY keyword.

For more information about RACF authorization, see Chapter 5, "Protecting DFSMSdss functions," on page 27.

For more information about using the IMPORT keyword, see "Protecting the usage of DFSMSdss" on page 533.

For more information about using the DELETECATALOGENTRY keyword to successfully restore a data set with the old data set name, see Chapter 6, "Managing availability with DFSMSdss," on page 33.

# **INCLUDE**



dsn Specifies the name of a data set eligible to be restored. Either a fully or a partially qualified data set name can be used. See "Filtering by data set

names" on page 260. If INCLUDE is omitted (but EXCLUDE or BY is specified) or if INCLUDE(\*\*) is specified, *all* data sets are eligible to be selected for restoring.

For more information, see:

- "BY" on page 461,
- "EXCLUDE" on page 467.

#### INDDNAME



dan Specifies the name of the DD statement that identifies the (input) dump data set. This data set can be on a tape or DASD volume.

**Note:** Concatenating multiple DFSMSdss dump data sets for the input for RESTORE is not supported and the results are unpredictable. Data sets on any dump data set after the first one in the concatenation will not be restored.

## **KEYPASSWORD**




KEYPASSWORD specifies an 8 to 32 character password (in EBCDIC) that is used to generate a clear TDES triple-length key or a clear 128-bit AES key.

If you specified the KEYPASSWORD keyword on a previous DUMP command, you must also specify this value when restoring the dump through the RESTORE command.

**Note:** The KEYPASSWORD password that is specified in your input command stream is not printed in the SYSPRINT output.

#### LOGICALVOLUME



LOGICALVOLUME specifies, for a *physical* data set restore operation, the volume serial numbers of the source DASD volumes that are to be processed. For example, if you have taken a data set dump from volumes 111111, 222222, and so forth, but you want to restore only some data sets from source volume 222222, specify LOGICALVOLUME (222222). LOGICALVOLUME is useful for restoring multivolume data sets.

## **MAKEMULTI**



MAKEMULTI allows DFSMSdss to convert single volume data sets into multivolume data sets. The default is not to convert single volume data sets into multivolume data sets.

This keyword applies only to SMS-managed target data sets. Only single volume, non-VSAM data sets are eligible to be changed into multivolume data sets.


SMS-managed target data sets are given a volume count (VOLCOUNT) that is either:

- The number of SMS output volumes specified in the RESTORE command, if output volumes are specified through OUTDDNAME or OUTDYNAM.
- The number of volumes in the target storage group or 59, whichever is less.

A data set's volume count is the maximum number of volumes to which the data set can extend. At any one time, there might be a mixture of primary volumes (volumes on which space is allocated for the data set) and candidate volumes (volumes on which space can be allocated at a future time). The total sum of the primary volumes and candidate volumes is the data set's volume count.

Note: When MAKEMULTI is specified and VOLCOUNT is also specified with an option other than VOLCOUNT(\*), the VOLCOUNT option overrides MAKEMULTI.


## MENTITY



MENTITY specifies a model entity and, optionally, the serial number of the volume containing that entity (volser) to be used when DFSMSdss defines discrete profiles. These keywords are used to define the data sets to RACF. Specification of MVOLSER is optional when the model entity (MENTITY) is either (1) cataloged in an integrated catalog facility catalog or (2) a non-VSAM data set cataloged in the standard catalog search order. When MVOLSER is specified for a VSAM model entity, the volser specified must be the volume serial number of the catalog in which the model entity is cataloged. If these keywords are not specified, DFSMSdss defines the data set to RACF without using a model.

**Restriction:** You cannot specify the MVOLSER(volser) keyword by itself. It can only be specified with the MENTITY(modeldsn) keyword.

# **MGMTCLAS**



MGMTCLAS specifies the user-desired management class that is to replace the source management class as input to the ACS routines. You must have the proper RACF authority for the management class specified. The keyword itself does not require RACF authorization.

NULLMGMTCLAS/NMC specifies that the input to the ACS routines is to be a null management class rather than the source data set's management class.

MGMTCLAS and NULLMGMTCLAS are mutually exclusive.

**Note:** All SMS-managed data sets specified in the BYPASSACS keyword will be assigned the specified management class because the ACS routines will not be invoked. Non-SMS-managed data sets do not have a management class.

#### NOPACKING



NOPACKING specifies that DFSMSdss is to allocate the target partitioned data set only to devices that are the same or like device type as the source, and that DFSMSdss is to use track level I/O to perform data movement. This results in an exact track-for-track image of the source data set on the target volume.

dsn Specifies the fully or partially qualified names of a PDS to be processed.

NOPACKing is only valid with a PDS. If specified, REBLOCK is ignored for the data set.

A PDS restored using NOPACKing is not compressed during data movement. NOPACKing can be used for a damaged PDS that is currently usable by an application but would be made unusable by compression or other rearrangement of the physical layout of the data.

**Note:** NOPACKing only applies to logical restore operations. Physical restore uses only track-level I/O. Therefore, no compression will take place against the PDS.

#### NULLMGMTCLAS

See "MGMTCLAS" on page 344.

#### NULLSTORCLAS

See "STORCLAS" on page 355.

## **OUTDDNAME**




ddn Specifies the name of the DD statement that identifies a volume to be restored to. To assure correct processing, each of the DD statements corresponding to a DDNAME (ddn) must identify only one volser. For a

logical data set restore or when you specify spill files, you can specify multiple names, separated by commas. For any other type of restore, you can specify only one name.

For more information, see "OUTDYNAM."

## **OUTDYNAM**



OUTDYNAME specifies that the volume to be restored to is to be dynamically allocated. The volume must be mounted and online. You cannot specify a nonspecific volume serial number using an asterisk (\*). For a logical data set restore or when you specify spill files, one or more volumes are allowed. For any other type of restore, only one volume is allowed.

Specifies the volume serial number of a DASD volume to be restored.


Specifies the device type of a DASD volume to be restored. This parameter unit is optional.

## Notes for OUTDDNAME and OUTDYNAM Keywords:

- OUTDDNAME or OUTDYNAM is required for a physical restore, even for SMS-managed data. They are optional for a logical restore operation, except:
  - For multivolume data sets that are preallocated on volumes that are different from the original source volumes; or
  - When the original source volume is not available, and the restored data set is not going to be SMS-managed.
- DFSMSdss now distinguishes between non-SMS and SMS volumes specified in the OUTDDNAME or OUTDYNAM keywords. For non-SMS allocations, only the volumes that are non-SMS are considered for allocation. Similarly, only SMS volumes are considered for SMS allocations.
  - This distinction is also used when determining the volume count for a multivolume allocation. Where volume count is determined from the number of specified volumes, only those volumes eligible for the type of allocation being done are counted. If there are no volumes that match the type of allocation (SMS volumes for SMS allocation, or non-SMS volumes for non-SMS allocation), processing proceeds with a null volume list.
- If a non-VSAM data set is migrated by DFSMShsm after a logical dump operation is performed on the data set, it should be recalled before a restore is attempted for the data set. If it is not recalled and if either OUTDDNAME or OUTDYNAM is specified indicating an output volume with REPLACE or REPLACEUNCONDITIONAL and RECATALOG(\*), DFSMSdss issues a message indicating that an error occurred while trying to catalog the restored data set because it was already cataloged as a migrated data set. The data set will be restored on the volume specified by the OUTDDNAME or the OUTDYNAM, but the data set will not be cataloged. If neither OUTDDNAME nor OUTDYNAM is specified, DFSMSdss issues a message indicating that data sets with a volume serial of MIGRAT cannot be restored.

If the DD statement corresponding to the ddn of the OUTDDNAME contains the data set name and disposition but not the volser, DFSMShsm recalls the data set automatically and DFSMSdss restores the data set.


## **OUTTRACKS**



OUTTRACKS specifies, for a track restore operation, the beginning location of the cylinder (*cc*) and head (*hh*) number of the target volume to which the track is to be restored. The number of (cc,hh) combinations specified in the OUTTRACKS keyword must be the same as the number of (c1,h1,c2,h2) combinations specified in the TRACKS keyword.

If OUTTRKS is not specified, the track is restored to its original cylinder and head number.

#### **PASSWORD**



PASSWORD specifies the passwords DFSMSdss is to use for password-protected data sets for all restore operations. (Password checking is bypassed for RACF-protected data sets.) The PASSWORD keyword is required only if:

- You do not have the required volume-level RACF DASDVOL or RACF DATASET access.
- The installation authorization exit does not bypass the checks.
- You do not want to be prompted for the password for VSAM data sets.

**Note:** Specify the passwords for all data sets that do not have RACF protection but do have password protection. During processing, a utility invoked by DFSMSdss might prompt the operator for a password. You can control authorization checking by using the installation authorization exit.

Catalog passwords are not supported to facilitate disaster recovery operations, application data transfers, and data set migration. Catalog protection via an access control facility, such as RACF, is the preferred method of protection.


ddn Specifies the name of the DD statement that identifies the sequential data set, or member of a partitioned data set, that contains data set names and their passwords in the format dsn/pswd[,...]. This data set must contain card-image records in DFSMSdss command syntax format.

dsn/pswd

dsn is a fully or partially qualified data set name. pswd is its password. If no password follows the slash (/), dsn is treated as though it were ddn.

**Note:** Printing of actual data set passwords specified in your input command stream is suppressed in the SYSPRINT output.

## **PERCENTUTILIZED**



PERCENTUTILIZED specifies that DFSMSdss must stop allocating data sets to the target volumes when the allocated space reaches n percent of the total space on the target volume. The default is 100. Specify more than one n if you have more than one target volume (for instance, a volume for overflow). If there are more target volumes than you have values in this keyword, the last value is used for the remaining target volumes.

If the output volume is an extended address volume and DFSMSdss is allocating non-VSAM or unsupported VSAM data sets, the PERCENTUTILIZED value specifies that DFSMSdss is to stop allocating data sets to the target volumes when the allocated space reaches n percent of the track-managed space on the target volume.

#### Note:

- 1. PERCENTUTILIZED is ignored if the target data set is preallocated or if you do not specify an output volume.
- 2. PERCENTUTILIZED is not supported in an SMS environment.
- 3. PERCENTUTILIZED is valid only for logical data set restore operations.

#### **PROCESS**



## **UNDEFinedsorg**

specifies that the logical data set restore operation is to be allowed for data sets with undefined data set organization going to an unlike target device of a larger capacity and that DFSMSdss is to use track level I/O to perform data movement. This results in an exact track-for-track image of the source data set on target volume. To specify PROCESS, RACF authorization might be required.

**Note:** Even though the data is being copied to a device with a larger track capacity, the data might not fit on the output device. For example, if the source device is a 3380, and the output device is a 3390 and the data set's block size is less than 277 bytes, a track on the target cannot contain as much data as a track on the source and the message ADR366W (Invalid Track Format) is issued.

For more information about RACF authorization, see Chapter 5, "Protecting DFSMSdss functions," on page 27.

## **PURGE**



PURGE prevents a FULL (or TRACK) restore operation from ending while unexpired data sets remain on the target volume. For more information, refer to the REPLACE keyword for data set restore discussion.

**Note:** You must specify PURGE for a FULL volume RESTORE operation if the VVDS name on the target volume does not match the target volume serial number. This type of volume can be created using full volume COPY in conjunction with one of the following conditions:

- · DUMPCONDITIONING is specified
- Neither COPYVOLID nor DUMPCONDITIONING are specified

#### **REBLOCK**



REBLOCK specifies that DFSMSdss is to reblock one or more of the selected sequential or partitioned data sets.

dsn Specifies the fully or partially qualified names of a sequential or partitioned data set to be restored and reblocked.

The REBLOCK keyword is ignored for:

- Unmovable data sets
- Data sets with record format of U (except for partitioned load modules)
- · Data sets with a record format of V, VS, VBS, or F
- Partitioned data sets with note lists (except for partitioned load modules)
- · partitioned data sets that are also specified in the NOPACKING keyword
- Compressed data sets in zEDC format.

Additionally, both the installation options exit and the installation reblock exit can override the specification of the REBLOCK keyword. The installation options exit can specify that no data set is to be reblocked. The installation reblock exit can specify whether a given data set is to be reblocked.

Some sequential and partitioned data sets have an attribute of being 'reblockable'. These data sets might be automatically reblocked by DFSMSdss independent of the REBLOCK keyword.


DFSMSdss uses DASD calculation services to determine the optimal block size for the target. The reblocking method used, DFSMSdss or DASD calculation services, is presented to the installation reblock exit.

For more information about DFSMSdss processing of reblockable data sets, see "Maximizing track utilization by reblocking data sets" on page 164.

# RECATALOG

See "CATALOG" on page 314.


#### RELBLOCKADDRESS



RELBLOCKADDRESS identifies the direct data sets (BDAM) whose names match the fully or partially qualified names specified (dsn). These direct data sets are organized by relative block address instead of TTR and are to be restored block by block. DFSMSdss updates the block reference count (the relative position of the physical record as stored on its track) of dummy records. This keyword applies only to direct data sets with fixed record formats and without standard user labels.

**Note:** If the data set is actually organized by TTR, the data set might become unusable.

#### RENAME



RENAME specifies that, if a data set with the old name exists on the output DASD volume, DFSMSdss is to allocate a new data set with the new name and restore the data set. If the data set with the old name does not exist on the volume, the data set is restored with the old name. For a VSAM data set that already exists on another DASD volume and is cataloged, the VSAM data set is restored with the new name unless the new name also exists and is cataloged.

VSAM data sets can only be renamed during a physical data set restore by using the RENAMEUNCONDITIONAL keyword. If a data set is preallocated with the new name, it is not restored. If a data set is not preallocated, it is restored using the old name. This keyword only applies to movable data sets; therefore, unmovable data sets will not be renamed. RENAME and RENAMEUNCONDITIONAL are mutually exclusive; you cannot specify these keywords together.

Note: If the RENAME keyword is specified in conjunction with the REPLACE keyword, only one of the keywords take effect for any particular data set. The RENAME keyword takes precedence over the REPLACE keyword. If a source data set name matches the RENAME criteria, then rename processing is performed and replace processing is not performed. If a preallocated target data set exists with the new name as chosen by the rename criteria, then the restore fails even if the REPLACE keyword was specified. If you want to replace a preallocated target with the new name, specify the REPLACEUNCONDITIONAL keyword. If a source data

set name does not match the rename criteria, and a preallocated target data set with the source name exists, the preallocated target data set is replaced.

- pfx Specifies the prefix to be used to replace the first-level qualifier of the data set name. It is optional, but if specified, must be the first parameter in the list of subkeywords. The prefix is used only if the (on,nn) parameters are not specified or the old name filters do not match the data set name.
- on Specifies the old name to be used as filtering criteria for matching data set names on the target volume.
- nn Specifies the new name to be used to derive the new data set name if the data set name selected by the corresponding old name filtering criteria matches the name of a data set that already exists on the target volume.

If none of the old name filters match the data set name and the prefix is specified, the prefix is used to derive the new name. If old name filters do not match and the prefix is not specified, the data set is not renamed. If the old name filter matches and there is an error in the new name filter, the data set is not renamed.

The syntax for the **prefix** is as follows:

- Single-level, fully qualified, unquoted DSNAME.
- 8 characters or less.
- The first character must be alphabetic or national.
- The remaining characters can be alphanumeric or national.

The syntax for the **old name** filter is exactly like that of the INCLUDE filter, and their rules match.

Examples of valid syntax for the **new name** filter are:

- \*\* Restore the data set with the old name. This provides a powerful tool whereby some data sets can be restored with the old name and others can be restored with the new name.
- \* If DSNAME has one level, then restore with old name.
- **A.\*\*** First level of DSNAME replaced by A.
- **A.B.**\*\* First two levels of DSNAME replaced by "A.B".
- \*.A.\*\* Second level of DSNAME replaced by A.
- \*\*.BCD

Last level of DSNAME replaced by BCD.

## DATE.\*\*.LIST

First and last levels are replaced by DATE and LIST.

- **Q.\*** If DSNAME has two levels, replace the first by Q.
- Q.\*.B If DSNAME has three levels, replace the first and last by Q and B.

#### \*.\*.SYSLIST

If DSNAME has three levels, replace the last by SYSLIST.

# ABC.DEF

No asterisk in substring; replace the entire name with "ABC.DEF".

Examples of invalid syntax for the **new name** filter are:

#### \*\*.DATA.\*\*

Invalid (level to be replaced is ambiguous).

\*SYS\* Invalid (a qualifier is not completely replaced).

Invalid (a qualifier is not completely replaced). SYS\*

\*SYS Invalid (a qualifier is not completely replaced).

#### SYS\*TEM

Invalid (a qualifier is not completely replaced).

#### SYS.DAT%

Invalid (a qualifier is not completely replaced).

**Restriction:** The use of the wildcard character (%) is not supported for the new name filter of the RENAME, RENAMEU, or RENUNC keywords for the COPY or RESTORE operations.

You cannot change the number of qualifiers unless you use fully-qualified names, for example, RENUNC((A.B.C,A.B.C.D)).

If the new name filter has errors, the data set is not restored. The new name that is derived is truncated to fit 44 characters. If it ends with a period, that period is also truncated.

If the new name is not fully qualified, then it must contain the same number of qualifiers as the old name. For example, given the old name filter DATE.\*\* and the new name filter DATE.\*.\*.LIST, DATE.MARCH.TODAY.OLDLIST would be renamed, but DATE.MARCH.OLDLIST would not.

If two or more rules match the old data set name, the resulting new name is the first match.


GDG relative generation filtering cannot be used for old or new names.

For more information about the use of the RENAME keyword, see "Special considerations for RESTORE" on page 453.

For more information about filtering, see "Filtering by data set names" on page 260.

"INCLUDE" on page 470.

## RENAMEUNCONDITIONAL



RENAMEUNCONDITIONAL specifies that the data set should be restored with the new name, whether or not the data set exists on DASD with the old name. If the data set exists on the volume with the new name, it is not restored. RENAMEUNCONDITIONAL is not supported for VSAM Alternate Index (AIX) data sets during a physical data set restore. This keyword only applies to movable data sets; therefore, unmovable data sets will not be renamed. If the old name filter matches and there is an error in the new name filter, the data set is not restored.

#### Note:

- 1. RENAME and RENAMEUNCONDITIONAL are mutually exclusive; you cannot specify these keywords together. RENAMEUNCONDITIONAL is not supported for physical restore of VSAM data sets, and, if specified, the data sets will not be restored.
- 2. RENAMEUNCONDITIONAL specifies that the data set must be restored with the new name, regardless of whether the data set exists on DASD with the old name. If the data set exists on the target volume with the new name and REPLACEUNCONDITIONAL is not specified, an error message is issued and the data set is not restored.
- 3. If the RENAMEU keyword is specified in conjunction with the REPLACE keyword, only one of the keywords take effect for any particular data set. The RENAMEU keyword takes precedence over the REPLACE keyword. If a source data set name matches the RENAMEU criteria, then rename processing is performed and replace processing is not performed. If a preallocated target data set exists with the new name as chosen by the rename criteria, then the restore fails even if the REPLACE keyword was specified. If you want to replace a preallocated target with the new name, specify the REPLACEUNCONDITIONAL keyword. If a source data set name does not match the rename criteria, and a preallocated target data set with the source name exists, the preallocated target data set is replaced.
- pfx Specifies the prefix used to replace the first-level qualifier of the data set name. It is optional but, if specified, must be the first parameter in the list of subkeywords. The prefix is used only if the (on,nn) parameters are not specified or the old name filters do not match the data set name.
- on Specifies the old name to be used as a filtering criterion to check if it matches the data set name.
- nn Specifies the new name to be used to derive the new data set name if the data set name matches the corresponding old name filtering criterion.

For more information about the use of the RENAME keyword, see "Special considerations for RESTORE" on page 453.

For syntax rules, see the discussion of *pfx*, *on*, and *nn* under "RENAME" on page 478.

## **REPLACE**



REPLACE specifies that DFSMSdss is to search the target volumes for usable preallocated data sets. If a usable preallocated data set is found, it will be replaced with the data set from the source volume. If no preallocated target is found, DFSMSdss attempts to allocate a data set.

DFSMSdss searches for preallocated data sets as follows:

• For SMS-managed data sets, DFSMSdss first searches in the standard order of search for a catalog entry for the data set.

- For VSAM or Non-VSAM data sets that are not SMS-managed, DFSMSdss searches for a preallocated data set, cataloged or uncataloged, in the following order:
  - 1. In any output volumes specified.
  - 2. If DFSMSdss finds no preallocated data set, it then searches the catalogs in the standard order of search.
  - 3. If no catalog entry is found for the data set, DFSMSdss searches the volume that the data set was dumped from.
- If no preallocated target is found, DFSMSdss attempts to allocate a data set. DFSMSdss invokes the ACS routines to determine if the data set should be SMS managed. If it should be SMS managed, then allocation is done according to the SMS constructs. If the data set should not be SMS managed, the output volumes specified are used. If no output volumes were specified, the volume the data set resided on at dump time is used. If allocation is successful, the data set is restored.
  - PURGE is accepted and is treated the same as REPLACE. REPLACE only applies if the data set is not being renamed. REPLACEUNCONDITIONAL should be used when renaming a data set and a preallocated target data set should be replaced.
- The REPLACE and REPLACEUNCONDITIONAL keywords can not be specified

The volume that the data set was dumped from on system A is shared with system B, where the data set was being restored. If the data set was NONSMS when it was dumped, and the REPLACE keyword is specified on the RESTORE, the order of search, for a pre-allocated data set that is cataloged or uncataloged, will first search any output volumes specified. If no pre-allocated data set is found, then it will search the catalogs in the standard order of search. If no catalog entry is found for the data set, then it will search the volume the data set was dumped from.

#### Note:

- 1. REPLACE or REPLACEUnconditional must be specified to restore to preallocated data sets.
- 2. If the source data set is an extended-addressable VSAM data set, then the target must also be an extended-addressable VSAM data set.
- 3. If REPLACE is specified with the RESTORE command, the SMS constructs already associated with the preallocated data set remain the same.
- 4. CATALOG and RECATALOG are ignored for preallocated data sets.
- 5. The target data set name must match the source data set name. REPLACEUnconditional must be specified to replace a target data set that has a name matching the rename criteria.
- 6. If you delete and reallocate a striped VSAM data set that is being replaced, DFSMSdss uses the same rules that apply to a new allocation. In general, it is best to not specify output volumes, or the VOLCOUNT keyword, when you are replacing striped VSAM data sets.
- 7. If the target data set is smaller than the source data set, DFSMSdss scratches the target data set and reallocates it with the size of the source data set.
- 8. Specify the FORCE keyword with the REPLACE keyword if you want to restore the data from unmovable data sets whose extents do not match.
- 9. If the RENAME or RENAMEU keywords are specified in conjunction with the REPLACE keyword, only one of the keywords take effect for any particular data set. The RENAME or RENAMEU keyword takes precedence over the

REPLACE keyword. If a source data set name matches the RENAME or RENAMEU criteria, then rename processing will be performed and replace processing will not be performed. If a preallocated target data set exists with the new name as chosen by the rename criteria, then the restore fails even if the REPLACE keyword was specified. If you want to replace a preallocated target with the new name, specify the REPLACEUNCONDITIONAL keyword. If a source data set name does not match the rename criteria and a preallocated target data set with the source name exists, the preallocated target data set is replaced.

- 10. If the data set being restored is a large format sequential data set, but the preallocated target is not a large format sequential data set, the preallocated target will be used and turned into a large format sequential data set as long as it has enough allocated space for the data set being restored. If the preallocated new name target does not have enough allocated space, it will be scratched and reallocated as a large format sequential data set with enough space for the data set being restored.
- 11. If REPLACE is specified with the RESTORE command, the CA Reclaim attribute already associated with the preallocated data set remains the same.
- 12. The preallocated data set is usable if all of the following conditions that apply to the data set being processed are met:
  - The user is authorized to update the target data set.
  - If VSAM, the cluster types match
  - · The DSORG matches.
  - If the data set being processed is multivolume or single volume and the non-SMS preallocated data set matches the multivolume or single volume.

For more information about the REPLACE keyword, see "Special considerations for RESTORE" on page 453.

### REPLACEUNCONDITIONAL



REPLACEUNCONDITIONAL specifies that DFSMSdss is to search the target volumes for usable preallocated data sets. If a usable preallocated data set is found, it IS replaced with the data set from the source volume. When used with the RENAME or RENAMEUnconditional keywords, usable preallocated data sets with the new name are replaced. When used without the RENAME or RENAMEUnconditional keywords, usable preallocated data sets with the same name as the source data set are replaced. If no preallocated target is found, DFSMSdss attempts to allocate a data set. The REPLACE and REPLACEUnconditional keywords can not be specified together.

### Note:

- REPLACEUnconditional must be specified to restore to preallocated data sets that match the rename criteria specified by the RENAME or RENAMEUnconditional keywords.
- 2. If the source data set is an extended-addressable VSAM data set, then the target must also be an extended-addressable VSAM data set.
- 3. If REPLACEUnconditional is specified with the RESTORE command, the SMS constructs already associated with the preallocated data set remain the same.

- 4. CATALOG and RECATALOG are ignored for preallocated data sets.
- 5. If DFSMSdss deletes and reallocates a striped VSAM data set that is being replaced, the same rules that apply to a new allocation are used to reallocate the data set. In general, it is best to not specify output volumes, or the VOLCOUNT keyword, when you are replacing striped VSAM data sets.
- 6. If the target data set is smaller than the source data set, DFSMSdss scratches the target data set and reallocates it with the size of the source data set.
- 7. If the data set being restored is a large format sequential data set, but the preallocated target is not a large format sequential data set, the preallocated target will be used and turned into a large format sequential data set as long as it has enough allocated space for the data set being restored. If the preallocated new name target does not have enough allocated space, it will be scratched and reallocated as a large format sequential data set with enough space for the data set being restored.
- 8. If REPLACEUnconditional is specified with the RESTORE command, the CA Reclaim attribute already associated with the preallocated data set remains the same.

### RESET



The RESET keyword directs how DFSMSdss determines if the data-set-changed indicator (DS1DSCHA) must be reset for the data sets on the volume being restored.

#### YES

DFSMSdss resets the data-set-changed indicator (DS1DSCHA=OFF) for all the data sets on the volume being restored

NO DFSMSdss does not alter the DS1DSCHA values. Each DS1DSCHA represents the value the data sets had at the time the dump was taken.

### **DUMP**

DFSMSdss resets the data-set-changed indicator (DS1DSCHA=OFF) only if the RESET keyword was specified on the DUMP command. This is the default.

When RESET is not specified, DFSMSdss treats the RESTORE as though RESET(DUMP) were specified. It only resets DS1DSCHA if the RESET keyword was specified at DUMP time.

#### Note:

- 1. If the dump was created with a release of z/OS prior to z/OS V2R1, and RESET(DUMP) is specified, DFSMSdss does not alter the DS1DSCHA values, as if RESET(NO) were specified.
- 2. If you use a storage management program such as DFSMShsm that performs incremental backups, you should be careful in coding the RESET keyword.

### SHARE



SHARE specifies that DFSMSdss is to share, for read access with other programs, the data sets that are to be restored. The resetting of the data set change indicator is bypassed if SHARE is specified on a data set restore operation.

SHARE and FULL are mutually exclusive; you cannot specify these keywords together.

The SHARE keyword is not honored for VSAM data sets. Exclusive control is obtained for VSAM data sets even if the SHARE keyword is specified. Neither read access nor write access by other programs is allowed while the VSAM data set is being restored, regardless of the share options defined for the data set.

#### SPHERE



SPHERE specifies that for any VSAM cluster dumped with the SPHERE keyword, DFSMSdss must also restore all associated AIX clusters and paths. Individual sphere component names need not be specified; only the base cluster name is required.

#### Note:

- 1. If an AIX is dumped without the SPHERE keyword, during a restore DFSMSdss treats the AIX as a normal VSAM KSDS.
- The base cluster name must be specified to process the entire sphere. If the SPHERE keyword is specified but the base cluster name is not, none of the associations will be processed.

### **RSA**




#### **RSA**

The RSA keyword allows you to specify a different label of an existing RSA private key that is present in the ICSF PKDS than what was specified on the RSA keyword during the DUMP command. The RSA public key is used to encrypt a randomly generated data key, so that the encrypted data key can be stored on the output medium.

### Note:

1. If the RSA keyword was specified during the DUMP command, it doesn't need to be specified on the RESTORE command when the same label for the same RSA private key exists in the ICSF PKDS.

### **STORCLAS**




STORCLAS specifies the user-desired storage class that is to replace the source storage class as input to the ACS routines. The user must have the proper RACF authorization for the storage class specified. The keyword itself does not require authorization.

NULLSTORCLAS/NSC specifies that the input to the ACS routines is to be a null storage class rather than the source data set's storage class.

STORCLAS and NULLSTORCLAS are mutually exclusive.

**Note:** If BYPASSACS(dsn) is specified, all data sets that pass the BYPASSACS selection criteria are guaranteed the specified storage class. The combination of NULLSTORCLAS and BYPASSACS(dsn) forces the selected data sets to be non-SMS managed.

### **TGTALLOC**



TGTALLOC specifies, during a logical data set restore function, how DFSMSdss will allocate the target data set.

**BLK** Specifies to allocate by blocks.

**CYL** Specifies to allocate by cylinders.

**TRK** Specifies to allocate by tracks.


### SOURCE/SRC

Specifies to allocate with the same space allocation type as that of the source data set.

### Note:

- 1. If the TGTALLOC keyword is omitted, the target allocation defaults to source.
- 2. If SRC is specified and if the source data set is allocated by track or if TRK is specified, then the final VSAM allocation might be different from the requested one because of VSAM allocation rules.
- **3**. If BLK is specified for VSAM data sets, TRK is used instead. The final VSAM allocation can be different from the requested one because of VSAM allocation rules.

### **TGTGDS**



TGTGDS specifies in what status, during a data set operation, that DFSMSdss is to place nonpreallocated SMS-managed GDG data sets.

### **DEFERRED**

Specifies that the target data set is to be assigned the DEFERRED status.

#### **ACTIVE**

Specifies that the target data set is to be assigned the ACTIVE status, for example, rolled into the GDG base.

### **ROLLEDOFF**

Specifies that the target data set is to be assigned the rolled-off status.

### SOURCE/SRC

Specifies that the target data set is to be assigned the same status as that of the source data set.

#### Note:

- 1. If the TGTGDS keyword is omitted, the target data set is assigned the DEFERRED status.
- 2. The requested target status of generation data sets must not violate generation data group rules.

### **TOLERATE**




### **ENQFailure**

Specifies that target data sets are to be processed even though shared or exclusive access fails. TOL(ENQF) and FULL or TRACKS are mutually exclusive; you cannot specify these keywords together.

For more information on TOL(ENQF), see Chapter 21, "Data integrity—serialization," on page 561.

### **TRACKS**



### **RESTORE Command**

TRACKS specifies ranges of tracks to be restored (that is, a tracks restore operation). If any of the requested tracks are not in the input file, the restore operation is stopped.

- *c1,h1* Specifies the cylinder and head number of the beginning of the range. Specify hexadecimal numbers as X'c1' or X'h1'.
- *c2,h2* Specifies the cylinder and head number of the end of the range. Specify hexadecimal numbers as X'c2' or X'h2'.

#### Note:

- 1. The *c*2 must be greater than or equal to *c*1.
- 2. If *c*2 equals *c*1, *h*2 must be greater than or equal to h1.

You can enter X'FFFFFF' (or 268435455) as the high cylinder value. This causes DFSMSdss to choose the high cylinder value to be the end of the volume.

DFSMSdss verifies that the range is within the limits of the device. If you do not specify all four values for a range, DFSMSdss provides the missing values unless the omitted value causes a syntax error. No intervening values can be omitted. For example:

### **Specified**

#### Results

None Syntax error

c1 c1,0,c1, maximum head number

*c1,h1 c1,h1,c1*, maximum head number

c1,h1,c2

c1,h1,c2, maximum head number

*c*1,*c*2 Syntax error

,h1 Syntax error

c1,h1,X'FFFFFFF'

c1,h1,maximum cylinder number for the volume, maximum head number

You cannot specify TOL(ENQF) with the TRACKS keyword.

**Data Integrity Note:** It is possible to duplicate a volume serial number during a restore TRACKS operation. Follow the procedure in "Data integrity considerations for full or tracks restore operations" on page 454 to maintain data integrity when restoring a volume with TRACKS restore.

For more information about using the TRACKS keyword during physical processing, see "Physical processing" on page 18.

### **TTRADDRESS**




TTRADDRESS identifies the direct access data sets whose names match the fully or partially qualified names specified (dsn). These direct access data sets are organized by TTR rather than by relative block addressing and are to be processed track by track. The target device track capacity must be equal to or greater than the source.

### Note:

- 1. If a direct access data set is specified by both the RELBLOCKADDRESS and the TTRADDRESS keywords, the data set is not processed. Refer to the RELBLOCKADDRESS keyword for more information.
- 2. The TTRADDRESS keyword takes precedence over the AUTORELBLOCKADDRESS keyword processing for the specified data sets (dsn).

### VOLCOUNT



VOLCOUNT specifies the method DFSMSdss uses to determine the number of volumes (volume count) for allocating the SMS target data set for a logical data set restore of VSAM or non-VSAM data sets.

#### \* (asterisk)

Specifies that DFSMSdss determine the volume count for allocation according to the following conditions:

- If the source data set is a single-volume data set, one volume is allocated.
- If the source data set is a multivolume data set and either a list of volumes is not specified to DFSMSdss through OUTDDNAME or OUTDYNAM or there are no SMS volumes in the list, DFSMSdss allocates the same number of volumes that were in the multivolume source data set.
- If the source data set is a multivolume data set and a volume list is specified through OUTDDNAME or OUTDYNAM, the volume count is the number of SMS volumes in the list.

DFSMSdss does not adjust the final number of candidate volumes after the allocation is complete.

The \* (asterisk) is the default for this keyword.

SRC Specifies that DFSMSdss *rely on the source volume count* to determine the number of volumes to allocate for the target data set as follows:

- If no output volume list is specified, DFSMSdss allocates the same number of volumes that the source data set had.
- If a volume list is specified through OUTDDNAME or OUTDYNAM, the volumes in the list that are SMS-managed must be in the same storage group, and the allocation must be directed to that storage group.

DFSMSdss does not adjust the final number of candidate volumes after the allocation is complete.

- nn represents the number of volumes to be used for SMS data set allocation. Any value between 0 and 59 can be specified with the following conditions:
  - If nn is not zero and a volume list is specified through OUTDDNAME or OUTDYNAM, DFSMSdss allocates either the number of SMS volumes in the volume list or nn, whichever is less.
  - If nn is zero and a volume list is specified through OUTDDNAME or OUTDYNAM, DFSMSdss allocates either the number of SMS volumes in the volume list or the number of volumes that were allocated for the source data set, whichever is less.
  - If a volume list is specified through OUTDDNAME or OUTDYNAM and there are no SMS volumes in the list, or there is no volume list, DFSMSdss allocates either the number of volumes used by the source data set or nn, whichever is more.

DFSMSdss does not adjust the final number of candidate volumes after the allocation is complete.

- ANY Specifies that DFSMSdss use a maximum volume count to allocate the SMS target data set as follows:
  - DFSMSdss initially sets a volume count of 59 for the allocation.
  - If the data set is allocated on more volumes than were used to allocate the source data set, DFSMSdss reduces the number of volumes used to the number of primary volumes needed to satisfy the allocation.
  - If the data set is allocated on the same number or fewer volumes than were used to allocate the source data set, DFSMSdss reduces the number of volumes used to the number of volumes used for allocation of the source data set.


### Note:

- 1. VOLCOUNT does not convert any of the following data sets to multivolume: PDS or PDSE data sets, single-volume data sets whose organization is undefined, or empty non-VSAM, single-volume data sets.
- 2. VOLCOUNT does not change the number of volumes for key-range KSDS data sets.
- 3. Guaranteed space is not honored when VOLCOUNT(ANY) is used.
- 4. VOLCOUNT(ANY) does not support keyed VSAM data sets that have an imbedded index. If VOLCOUNT(ANY) is specified and a data set has an imbedded index, the data set is processed as if VOLCOUNT(\*) were specified.
- 5. VOLCOUNT(ANY) does not support any type of striped data set (physical, sequential, extended, or VSAM). If VOLCOUNT(ANY) is specified and a data set is striped, the data set is processed as if VOLCOUNT(\*) were specified.
- 6. When you specify VOLCOUNT(ANY), the &ANYVOL and &ALLVOL read-only variables are not available to the storage group ACS routine.
- 7. For nonguaranteed-space, striped VSAM data sets: The minimum number of volumes that DFSMSdss allocates is determined by the number of stripes, which is based on the STORCLAS sustained data rate (SDR). DFSMSdss does not consider the number of volumes in the output volume list, or any of the VOLCOUNT specifications. If there are not enough enabled volumes in the STORGRP to support the SDR, DFSMSdss reduces the number of stripes. If there are excess volumes specified, those volumes become nonspecific (\*) candidates.

8. For guaranteed-space, striped VSAM data sets: DFSMSdss allocates the number of volumes that are specified in the output list, regardless of the SDR. (To be striped, the SDR must be greater than zero.) The VOLCOUNT rules described above apply.

You can override VOLCOUNT keyword settings with the options installation exit routine, as described in *z*/*OS DFSMS Installation Exits*.

### WAIT



WAIT specifies to DFSMSdss the length of a wait in seconds and the number of retries to obtain control of a data set.

#### numsecs

Specifies a decimal number from 0 to 255 that designates the time interval, in seconds, between retries.

#### numretries

Specifies a decimal number from 0 to 99 that designates the number of retries to gain control of a data set.

The default for *numsecs,numretries* is (2,2), which specifies two retries at 2-second intervals. If you do not want to wait for a data set, specify 0 for either numsecs or numretries.

**Note:** The WAIT keyword does not control wait/retry attempts for system resources (such as the VTOC and the VVDS). For system resources, the default wait time is 3 seconds and the default retry count is 30. This results in a total wait time of 90 seconds.

For information about controlling the wait/retry attempts for system resources, see "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

### WRITECHECK



WRITECHECK specifies that the data restored is to be verified for successful completion. This keyword increases the overall elapsed time. The default is no WRITECHECK.

**Note:** The WRITECHECK keyword is not supported for extended-format sequential data sets.

## **DFSMSdss RESTORE process**

Table 24 on page 492 describes, in decision table format, DFSMSdss restore actions for physical processing of SMS-managed data sets. The specified RESTORE

### **RESTORE Command**

command keywords and the existence of the data set are shown in the upper half. The actions taken are shown in the lower half.

Table 24. Physical Data Set Restore Actions on SMS-Managed Data Sets

Action	Non-VSAM Physical Restore						VSAM Physical Restore																				
RENAME	N	N	N	N	Y	Y	Y	Y	Y	Y	-	-	-	N	N	Y	-	Y	-	-	-	-	-	N	N	N	N
RENUNC	N	N	N	N	-	-	-	-	-	-	Y	Y	Y	N	N	-	Y	-	Y	Y	Y	Y	Y	N	N	N	N
REPLACE	Y	Y	-	-	N	N	Y	Y	-	-	N	Y	-	N	N	N	Х	N	N	N	Y	Y	-	Y	-	N	-
REPLACEU	-	-	Y	Y	N	N	-	-	Y	Y	N	-	Y	N	N	N	Х	N	N	N	-	-	Y	-	Y	N	_
OLD DATA SET EXISTS	Y	N	Y	N	Y	N	Y	N	Y	N	Х	Х	Х	Y	N	Y	Х	Х	Х	Х	Х	Х	Х	Y	Y	Y	N
NEW NAME ON VOLUME	-	_	_	-	N	Х	N	-	N	_	_	_	_	-	-	Y	Y	_	N	Y	N	Y	Х	_	_	_	-
Overlay old data set	Т	_	Т	_	_	_	_	_	_	_	_	_	_	_	_	_	_	_	_	_	_	_	_	Т	Т	_	-
ALLOC with new name on USERVOL and restore	_	_	_	_	Т	_	Т	_	Т	_	Т	Т	Т	_	_	_	_	_	Т	_	Т	_	Т	_	_	_	
ALLOC with old name	-	Т	-	T	_	Т	_	Т	_	Т	_	-	-	-	Т	_	_	-	_	-	-	_	-	_	-	-	Т
Do not restore	-	-	_	-	-	-	_	_	-	-	_	-	_	T	_	T	T	Т	_	Т	_	Т	_	-	_	Т	_

### Legend:

- Y = Yes
- T = Action taken
- N = No
- X = Doesn't matter
- = Not Applicable

Figure 19 on page 493 describes general DFSMSdss actions for both physical and logical restore on non-VSAM data sets. It is not a program flowchart. Use it to clarify the restore actions on non-VSAM data sets under varying conditions.




Figure 19. Restore Actions on Non-VSAM Data Sets. These actions apply to a data set RESTORE command with RENAME, RENAMEUNCONDITIONAL, REPLACE and REPLACEUNCONDITIONAL keywords.

## Assignment of class names by using the RESTORE and COPY commands

In an SMS environment, you can use STORCLAS, MGMTCLAS, NULLSTORCLAS, NULLMGMTCLAS, and BYPASSACS keywords with the RESTORE and COPY commands to influence the class names assigned to a data set. Figure 20 shows how these keywords can influence the storage and management class names of the target data set in a restore or copy operation. However, Figure 20 only addresses how the *management and storage class* names are assigned, not how the *storage group* name is assigned or how volumes are selected.




Figure 20. DFSMSdss Target Class Selection

Notes to Figure 20:

- If you specify BYPASSACS, the source data set's class names or the class names specified with STORCLAS and MGMTCLAS are assigned to the target data set.
   If you do not specify BYPASSACS, ACS uses the source data set's class names, or the class names specified with STORCLAS and MGMTCLAS as input to assign the target data set's class names.
- If you specify NULLSTORCLAS, DFSMSdss passes a null storage class to ACS, which selects a storage class for the data set. If you specify NULLSTORCLAS and BYPASSACS together, the data set becomes non-SMS managed.
- NULLMGMTCLAS can only be used with SMS-managed data sets. Specifying NULLMGMTCLAS and BYPASSACS together causes the removal of the original management class of the data set.

For information about how target volumes are selected during restore and copy functions, see Chapter 6, "Managing availability with DFSMSdss," on page 33.

### **Examples of full and tracks restore operations**

Example 1 shows that DASD volume numbered 111111 will be restored from the first data set of standard label tape volumes called TAPE01 and TAPE02.

The command input to be substituted for a full and tracks restore operation are shown below in Example 1A and 1B respectively. To dump the same volume, see Examples 1, 1A, and 1B of the DUMP command.

### **Example 1: DASD volume-restore operation**

```
//JOB1 JOB accounting information, REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//TAPE DD UNIT=3480, VOL=SER=(TAPE01, TAPE02),
// LABEL=(1,SL), DISP=(OLD, KEEP), DSNAME=USER2.BACKUP
//DASD DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//SYSIN DD *
command input
/*
```

For the command input, see

- "Example 1A: full restore operation,"
- "Example 1B: tracks restore operation,"
- "Example 1C: tracks RESTORE—restore to different tracks" on page 496.

.

### **Example 1A: full restore operation**

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD) PURGE
```

### **Example 1B: tracks restore operation**

```
RESTORE TRACKS(1,0,1,5) INDDNAME(TAPE) -
OUTDDNAME(DASD) PURGE
```

### **Example 1C: tracks RESTORE—restore to different tracks**

```
//JOBTRKS
          J0B
                accounting information, REGION=nnnnK
          EXEC PGM=ADRDSSU
//STEP1
//TAPE
                UNIT=3480, VOL=SER=TAPE04,
          DD
// LABEL=(1,SL),DISP=(OLD,KEEP),DSN=USER2.BACKUP
//SYSPRINT DD
               SYSOUT=A
//SYSIN
          DD
RESTORE INDD(TAPE) OUTDYNAM(338000) -
   TRKS(200,10,200,10) /* INPUT TRK 200,10 ON SOURCE VOL*/ -
   OUTTRKS (100,0)
                      /*RESTORE TO 100,0 ON TARGET VOL */ -
                      /* OK TO OVERLAY THE TRK
         /* EVEN IF UNEXPIRED DATA SET AT THE LOCATION */ -
   PSWD(ABC/WRITPSWD) /* PASSWORD FOR THE DATA SET
```

A track of dump data is restored to a cylinder and head number other than that from which it was dumped. The dump tape (which might have resulted from a full, tracks, or data set dump operation) contains a track dumped from cylinder 200 head 10 that is restored to cylinder 100 head 0.

### Examples of physical data set restore operations

Example 2 specifies that data sets on standard label tape volume TAPE02 are to be restored to DASD volume numbered 111111.

Examples 2A through 2D below complement Examples 2A through 2G in "Examples of physical data set dump operations" on page 427 in any combination. For example, the dump tape produced in Example 2C in "DUMP Command" can be used as the input tape for Example 2A below.

### Example 2: label tape volume RESTORED to DASD

```
//J0B2
          J0B
                accounting information, REGION=nnnnK
          EXEC PGM=ADRDSSU
//STEP1
//SYSPRINT DD
                SYSOUT=A
//TAPE
                UNIT=3480, VOL=SER=TAPE02,
          DD
// LABEL=(1,SL),DISP=(OLD,KEEP),DSNAME=USER2.BACKUP
//DASD1
          DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//SYSIN
          DD
  command input (see Examples 2A, 2B, ... below)
```

For command input, see:

- "Example 2A: using the INCLUDE subkeyword to restore all data sets on a dump tape" on page 497,
- "Example 2B: using the INCLUDE and EXCLUDE subkeywords" on page 497,
- "Example 2C: using the INCLUDE, EXCLUDE, and BY subkeywords" on page 497,
- "Example 2D: with filtering data in a data set" on page 497,
- "Example 2E: using the LOGICALVOLUME and REPLACE keywords" on page 498,
- "Example 2F: using the REPLACE and RENAME keywords" on page 498,
- "Example 2G: using the REPLACE and RENAMEUNCONDITIONAL keywords" on page 498,
- "Example 2H: restore all data sets" on page 498,

• "Example 2I: restore data sets" on page 499.

## Example 2A: using the INCLUDE subkeyword to restore all data sets on a dump tape

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**))
```

### **Example 2B: using the INCLUDE and EXCLUDE subkeywords**

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**) -
EXCLUDE(**.LIST))
```

All data sets are restored, except those ending with a qualifier of LIST.

# Example 2C: using the INCLUDE, EXCLUDE, and BY subkeywords

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**) -
EXCLUDE(**.LIST) -
BY((EXPDT,LE,80045)))
```

All data sets that satisfy the BY subkeyword except those specified in the EXCLUDE subkeyword are restored.

### Example 2D: with filtering data in a data set

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(FILTERDD(A1))
```

**Note to Example 2D:** The following DD statement must be added to the JCL shown in Example 2:

```
//A1 DD DSNAME=USER2.FILTER,DISP=SHR
```

This cataloged data set (USER2.FILTER) contains three card-image records. The information shown below is positioned in columns 2 through 72 of each record:

```
INCLUDE(**) -
EXCLUDE(**.LIST) -
BY((DSCHA,EQ,1))
```

# Example 2E: using the LOGICALVOLUME and REPLACE keywords

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**)) LOGICALVOLUME(111111) -
REPLACE
```

Although the dump tape contains data sets from source volumes 111111 and 222222, only the data sets from source volume 111111 are restored. If preallocated data sets exist on the volume, DFSMSdss replaces them. Unmovable data sets that are not preallocated are not restored.

### Example 2F: using the REPLACE and RENAME keywords

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**)) LOGICALVOLUME(111111) -
REPLACE -
RENAME((USER2),(USER4.**,USER3.**))
```

In the above example, renaming takes place only for data sets that exist on DASD with the old name. Data sets with a first-level qualifier of USER4 are renamed to a first-level qualifier of USER3. The first-level qualifiers of all other data sets are replaced by USER2. Unmovable data sets are not renamed.

# Example 2G: using the REPLACE and RENAMEUNCONDITIONAL keywords

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**)) LOGICALVOLUME(111111) -
REPLACE -
RENAMEUNCONDITIONAL((USER2),(*.PEAR.**,*.PLUM.**), -
(MY.SPECIFIC.DS,YOUR.ANY))
```

RENAMEUNCONDITIONAL is used for movable data sets; REPLACE is used for unmovable data sets. With the RENUNC keyword, movable data sets are renamed whether or not they exist on DASD with the old name. In the example, data sets with a second-level qualifier of PEAR are renamed by using a second-level qualifier of PLUM. MY.SPECIFIC.DS is renamed as YOUR.ANY. The first-level qualifier of all other movable data sets is changed to USER2. Unmovable data sets are not renamed.

### Example 2H: restore all data sets

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
WAIT (1,99) DATASET(INCLUDE(**))
```

Example 2H shows you what to do if the data sets are in use for a short time interval during a restore operation. DFSMSdss waits for a second at a time and retries as many as 99 times if the data set is in use by another job.

### Example 2I: restore data sets

```
RESTORE INDDNAME(TAPE) OUTDDNAME(DASD1) -
DATASET(INCLUDE(**)) TOL(ENQF) WAIT(0,0)
```

In Example 2I, DFSMSdss tries to serialize (ENQ) each data set. If the ENQ fails, DFSMSdss does not wait (WAIT(0,0)), and the data set is processed without serialization or enqueuing (TOL(ENQF)).

### **Examples of logical data set restore operations**

The following are examples of logical data set RESTORE operations.

## Example 1: logical data set RESTORE—output volumes not specified

```
//JOB5 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//TAPE DD UNIT=3480,VOL=SER=TAPE04,
// LABEL=(1,SL),DISP=(OLD,KEEP),DSN=USER3.BACKUP
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
RESTORE INDD(TAPE) -
DS(INCL(USER1.MULTVOL)) -
REPLACE
/*
```

In Example 1, data set USER1.MULTVOL is restored. The location to which it is to be restored is not given. This RESTORE statement also applies when the data set has been scratched inadvertently after the dump operation. A multivolume data set is restored to the volumes from which it was dumped, provided the data set is preallocated on the output volumes. If it is not preallocated, the data set is restored to the first volume from which it was dumped that has adequate space to restore the data set as a single-volume data set.

The RESTORE statement can be modified as follows to support multiple restores of both single and multivolume data sets from dump tapes:

```
//SYSIN DD *
RESTORE INDD(TAPE) /* RESTORE */-
DS(INCL(USER1.CNTL.**)) /* USER'S CONTROL DATA SETS */-
REPLACE /* OVERLAY DATA SETS IF THEY EXIST */
/*
```

### Example 2: logical restore of an unmovable data set

```
accounting information, REGION=nnnnK
//J0B6
          J0B
          EXEC PGM=ADRDSSU
//STEP1
                UNIT=3480, VOL=SER=TAPE04,
//TAPE
          DD
// LABEL=(1,SL),DISP=(OLD,KEEP),DSN=USER4.BACKUP
//SYSPRINT DD
               SYSOUT=A
//SYSIN
         DD
RESTORE INDD(TAPE) OUTDYNAM(338000) -
  DS(INCL(HIGH.PERF))
               /* TO FORCE RESTORE OF UNMOVABLE DATA SET */
```

In Example 2, the unmovable data set HIGH.PERF does not currently exist on volume 338000. However, this data set did exist on volume 338000 at the time of the dump. You want to restore it to volume 338000 and would prefer it be restored to the location it originally occupied. However, the location where this data set would normally be restored is occupied by other data sets. So, you restore the data set to another place on the volume because you specify the FORCE keyword. The data set is marked as unmovable on volume 338000 because of one of the following situations:

- You do not want DFSMShsm to move it to an unlike device type.
- You do not want the data set to be relocated by a DEFRAG operation for performance reasons.
- It was allocated as an ABSTR data set for performance reasons.

## Example 3: logical data set dump, followed by a restore to an unlike device

```
//J0B1
           JOB accounting information, REGION=nnnnK
//STEP1
           EXEC PGM=ADRDSSU
//TAPE
           DD UNIT=3480, VOL=TAPE01,
// LABEL=(1,SL),DISP=(NEW,CATLG),DSNAME=USER2.BACKUP
//SYSPRINT DD SYSOUT=A
//SYSIN
           DD
DUMP DATASET(INCL(USER2.OLDDS)) -
     OUTDD (TAPE)
//J0B2
           JOB accounting information, REGION=nnnnK
//JOB2 JOB accounting //STEP1 EXEC PGM=ADRDSSU
//SYSPRINT DD SYSOUT=A
//TAPE DD UNIT=3480, VOL=TAPE01,
// LABEL=(1,SL),DISP=(OLD,KEEP),DSNAME=USER2.BACKUP
         DD UNIT=3380, VOL=(PRIVATE, SER=222222), DISP=OLD
//DASD
         DD *
RESTORE DATASET(
   INCLUDE(USER2.OLDDS) ) -
  INDDNAME(TAPE) -
   OUTDDNAME(DASD) -
   RENAME (*.OLDDS, *.NEWDS)
```

In the first part of example 3, DFSMSdss dumps a cataloged data set (USER2.OLDDS) from the source volume to an IBM standard label dump tape (TAPE01). Next, DFSMSdss restores USER2.OLDDS from TAPE01 to a 3380 target volume (DASD volume 222222). The RENAME keyword is used to change the name of the data set to USER2.NEWDS.

# **Example 4: dump and restore for storage management subsystem (SMS) conversion**

This initial part of "Example 4: dump and restore for storage management subsystem (SMS) conversion" dumps all the single-volume data sets on the non-SMS volume 338001 to TAPE01 with the DELETE option. The DELETE and PURGE keywords are required to avoid duplications in the restore operation.

```
//SYSPRINT DD SYSOUT=*
//DTAPE01 DD DISP=(OLD,KEEP),DSN=V338001.USER3.BACKUP,
// LABEL=(1,SL),UNIT=3480,VOL=SER=TAPE01
//SYSIN DD *
RESTORE DS(INC(**)) -
STORCLAS(SC01MJA1) -
INDDNAME (DTAPE01)
/*
```

This second part of "Example 4: dump and restore for storage management subsystem (SMS) conversion" restores all of the data sets that were dumped in the first half of this example. Because no output volume is specified, most of the data sets will be allocated on SMS volumes throughout the system. The STORCLAS keyword indicates that the storage administrator wants the data sets to have a storage class of SC01MJA1. The ACS routines might or might not assign the target data sets that the storage class specified. All data sets that are not converted to SMS (ACS STORCLAS routine returns a null storage class) will be restored to the original volume.

## Example 5: using the RENAME keyword to restore a VSAM data set

```
//JOB3 JOB accounting information,REGION=nnnnK
//STEP1 EXEC PGM=ADRDSSU
//TAPE DD UNIT=3480,VOL=SER=TAPE04,
// LABEL=(1,SL),DISP=(OLD,KEEP),DSN=USER3.BACKUP
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
RESTORE INDD(TAPE) OUTDYNAM(338000) -
DS(INCL(PARTS.VSAM1)) -
RENAME(*.VSAM1,*.VSAM2) -
CATALOG
/*
```

### **RESTORE Command**

A VSAM key-sequenced data set, PARTS.VSAM1, is restored from a logical dump tape in this example. It is renamed as PARTS.VSAM2 and cataloged in the standard order of search. The cluster's components, PARTS.VSAM1.DATA and PARTS.VSAM1.INDEX, are also renamed.

### Example 6: using the RECATALOG keyword

```
//J0B4
          J0B
                accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=ADRDSSU
          DD UNIT=3480, VOL=SER=TAPE04,
//TAPE
// LABEL=(1,SL),DISP=(OLD,KEEP),DSN=USER3.BACKUP
//SYSPRINT DD
               SYSOUT=A
//SYSIN
          DD
RESTORE INDD(TAPE) OUTDYNAM((338001),(338002)) -
  DS(INC(PARTS.**)) /* OR DS(INC(**))
  PCTU(80)
  RECATALOG (USERCAT2)
  TGTALLOC(SOURCE)
```

In "Example 6: using the RECATALOG keyword," data sets with a first-level qualifier of PARTS were dumped logically. All are restored to volume 338001 and cataloged in catalog USERCAT2. These data sets were on volume 338000 at the time of dump. If the data sets do not fit on volume 338001, a spill volume 338002 is specified. To ensure that the data sets on volume 338001 can be extended, 20% of the total space on volume 338001 is to be left as free space (PCTU(80)). TGTALLOC(SOURCE) specifies that the data sets are to be restored with the same allocation type they had when they were dumped.

## Chapter 18. Syntax—auxiliary commands

This section describes the following **auxiliary** commands that you can use to further refine DFSMSdss processing:

- Writing to the Operator:
  - write-to-operator (WTO) command
  - write-to-operator with reply (WTOR) command
- Scheduling Tasks:
  - SERIAL command
  - PARALLEL command
- Controlling Task Processing:
  - SET command
  - IF-THEN-ELSE command sequence
  - EOJ command

### Writing to the operator for DFSMSdss

Use either the WTO or the WTOR command to direct a message to the system console. DFSMSdss prefixes the WTO and WTOR messages with a message ID of ADR111I and ADR112A, respectively.

When DFSMSdss encounters either a WTO or WTOR command, it waits until the last-requested function command completes before issuing the WTO or WTOR command.

### WTO command

The WTO command lets you write an ADR111I message to the system console that does not request a reply from the operator. The message cannot be greater than 247 characters. You must enclose the message within quotation marks. The command syntax is:



DFSMSdss assigns the following routing codes to the WTO message:

- 2 Master console information
- 11 Programmer information

DFSMSdss assigns the following descriptor code to the WTO message:

6 Job status

### WTOR command for DFSMSdss

The WTOR command lets you write an ADR112A message to the system console. The ADR112A message requests that the operator perform some action, and then issue a reply. You can use WTOR, for example, to request that the operator mount a required volume or quiesce a data base before your DFSMSdss job continues to process. The WTOR message cannot be greater than 114 characters. You must enclose the message within quotation marks. The command syntax is:

### Syntax—Auxiliary Commands

DFSMSdss assigns the following routing code to the WTOR message:

Master console action

DFSMSdss assigns the following descriptor code to the WTOR message:

Action that is required

### Scheduling tasks

You can use the SERIAL or PARALLEL commands to schedule tasks. The SERIAL or PARALLEL command must precede the commands to be executed in the SERIAL or PARALLEL mode.

### SERIAL command for DFSMSdss

The SERIAL command lets you re-initiate serial task scheduling (only one task at a time) after you have used parallel task scheduling. Tasks are processed in the order in which they appear in the input stream.

If neither the SERIAL nor PARALLEL command has been issued, SERIAL is the default. The command syntax is:



### PARALLEL command for DFSMSdss

The PARALLEL command initiates parallel task scheduling wherein multiple tasks are processed concurrently. When you use parallel processing, commands may not process in the order in which they appear in the input stream. The PARALLEL command is effective only when the required system resources (virtual storage, DASD, or tape volumes) are available. If there are resource conflicts (multiple tasks that use the same DASD or the same tape volume) or if there is not enough virtual storage that is available for all of the tasks to run concurrently, some tasks can be delayed until the resources are available (other tasks end).

DFSMSdss attempts to delay the initiation of additional tasks if there are insufficient available resources to initiate the tasks. DFSMSdss is not able to accurately assess which additional resources that a task might later require. If you attempt to run too many tasks in parallel for the available resources, it can result in unpredictable failures. In such cases, the user must establish a safe upper boundary on the number of tasks that can be supported as parallel tasks.

When you switch between SERIAL and PARALLEL modes, DFSMSdss waits for the completion of all previously scheduled tasks before switching. If DFSMSdss is in PARALLEL mode, an IF statement ensures that all prior commands are processed. The command syntax is:



### Controlling task processing

With the SET, IF-THEN-ELSE, and EOJ commands, you can direct DFSMSdss through a logical path in your command sequence, based on the condition (return) codes of previously completed operations. In addition, you can temporarily set patch bytes with the PATCH parameter of the SET command.

### SET command—setting condition codes and patch bytes

As an alternative to setting flags in ADRPATCH (a module in the DFSMSdss load module ADRDSSU), you can customize certain DFSMSdss functions by temporarily setting patch bytes during DFSMSdss processing through a SET PATCH command.

The SET command also allows you to set the LASTCC and MAXCC variables to any value from 0 to 16, inclusive. By doing so, you can influence the logical path that DFSMSdss takes in the command sequence following the SET command.

You can set the following condition codes with the SET command. Use an IF-THEN-ELSE command sequence to test for these condition codes.

- The function was processed as expected. Informational messages may have been issued.
- A problem occurred, but processing continued. The result may not be exactly what you wanted, but no permanent harm was done. A warning message was issued.
- A function did not process, began processing but ended prematurely, or the job ran without processing all requested functions. An error message is issued. If an abend occurs in any of the DFSMSdss subtasks, the return code is set to 8.
- The job did not process. No functions were processed.
- A function processed and left at least one volume or data set in an unusable condition. For example, a full-volume dump operation ended prematurely, leaving the output tape in an unusable condition.

If you are running a batch job, the condition codes that are tested in the IF-THEN-ELSE command sequence, and that can be set by the SET command, cannot be passed from one job step to the next. However, the final maximum condition code is passed to the MVS system when DFSMSdss returns control to the system at the completion of step processing. **Do not use SET LASTCC before the first function command.** 

You can determine the condition code of the last-requested operation (LASTCC) and the maximum code of all completed operations (MAXCC) with an IF command. When an IF MAXCC or SET MAXCC command is encountered, DFSMSdss waits for all previously requested function commands to complete before the highest return code is determined. Also, when an IF LASTCC or SET LASTCC command is encountered, DFSMSdss waits for the last-requested function command to complete before the return code is determined. After the return code is determined and if the condition code is tested and satisfied, DFSMSdss ends the command or commands following the THEN keyword. If the tested condition is not satisfied, DFSMSdss bypasses the command or commands following the THEN keyword.

### SET command for DFSMSdss

The syntax of the SET command is:



### Syntax—Auxiliary Commands

The SET command allows you to customize certain DFSMSdss functions by temporarily setting patch bytes. You can also influence the logical path that DFSMSdss takes in the command sequence that follows the SET command. A SET command that occurs within an unprocessed THEN or ELSE clause is not processed.

#### **PATCH**

Specifies that DFSMSdss set the patch byte, at offset offset, to the value specified with value.

Your installation can limit the use of the SET PATCH command with the RACF FACILITY-class profile STGADMIN.ADR.PATCH. You need READ access authorization to that profile to use the SET PATCH command.

### offset

Specifies, in hexadecimal, the value for the patch byte offset. The maximum offset that you can specify is X'0FFF', and the minimum offset that you can specify is X'08'.

Specifies, in hexadecimal, the value that DFSMSdss assigns to the patch byte at the specified offset. The value must be in the range X'00' to X'FF'.

Specifies that the MAXCC be set to a new condition-code value. Setting MAXCC does not affect the value of LASTCC.

Specifies that the LASTCC be set to a new condition-code value. If the value assigned to LASTCC is higher than the value of MAXCC, MAXCC is also set to the higher value.

### number

Specifies the value assigned to MAXCC or LASTCC. The maximum value that can be assigned is 16; a higher value is reduced to 16.

**Examples of the SET command:** The examples that follow show the use of the SET command.

To set the patch byte at offset X'08' to X'FF', specify the following: SET PATCH 8 = FF

To set the patch byte at offset X'44' to X'25', specify the following: SET PATCH 44 = 25

To set the last condition code established to 12, specify the following: SET LASTCC=12

To replace the highest condition code established in processing so far with 8, specify the following:


SET MAXCC=8

### IF-THEN-ELSE command sequence for DFSMSdss—using condition codes

Condition codes are used to set up the IF-THEN-ELSE statements. LASTCC specifies a comparison to the last condition code and MAXCC specifies the maximum condition code for comparison.

### **IF-THEN-ELSE** command sequence

The syntax of the IF-THEN-ELSE command sequence is:



**IF** Specifies that a comparison is to be made. The outcome determines which logical path (in your command sequence) DFSMSdss takes.

#### LASTCC

Specifies that LASTCC (condition code of the last-requested function, such as COMPRESS, CONVERTV, COPY, COPYDUMP, DEFRAG, DUMP, PRINT, RELEASE, RESTORE) be compared to a specified number.

#### MAXCC

Specifies that MAXCC (maximum condition code of all completed operations) be compared to a specified number. MAXCC is initialized to zero upon entry to DFSMSdss.

#### **REPLY**

Specifies that DFSMSdss compare the operator response to the last SYSIN command stream to the text specified with the *text* variable of the REPLY keyword.

Op Specifies an operator that describes a comparison that DFSMSdss will make. For example, you may have specified a returned condition code with either the LASTCC or MAXCC keyword. You can compare this value to the value of the number variable that you specify after the specific operator. You can also compare the operator's response to a WTOR command to the text that you specify with the text variable of the REPLY keyword. The compare operator can perform any one of six possible comparisons:

EQ or =
Equal to

LE or <=
Less than or equal to

LT or <
Less than

GT or >
Greater than

GE or >=
Greater than or equal to

NE or ¬=

Not equal to

number

Specifies the decimal integer that is to be compared with MAXCC or LASTCC. Values greater than 16 are reduced to 16.

### Syntax—Auxiliary Commands

text

Specifies the text that is to be compared with the operator's response to the WTOR command. You must enclose the text string within quotation marks.

#### THEN

Specifies that a single command or a group of commands (enclosed by DO and END) is to be processed if the tested condition is satisfied. THEN can be followed by another IF command.

#### **ELSE**

Specifies that a single command or a group of commands (enclosed by DO and END) is to be processed if the tested condition is not satisfied. ELSE can be followed by another IF command. The ELSE clause cannot be on the same line as the THEN clause nor on the same line as the continuation of the THEN clause.

**DO** Specifies that the group of commands that follows is to be treated as a single unit, that is, to be processed as a result of a single IF command. The set of commands is ended by END. A command following a DO must begin on a new line.

#### **END**

Specifies the end of a set of commands initiated by the nearest unended DO. END must be on a line by itself.

### Creating a null command

If THEN or ELSE is not followed by a continuation character or by a command on the same line, the result is a null command. A semicolon after the THEN or ELSE keyword also results in a null command. A null command specifies that no action is taken if the IF clause is satisfied (a null THEN command) or if the IF clause is not satisfied (a null ELSE command).

```
To specify a null THEN command, specify:
```

```
IF ... THEN or IF ... THEN; ELSE ...
```

To specify a null ELSE command, specify:

```
IF ... THEN ... or IF ... THEN ... ELSE;
```

### Continuation rules for IF-THEN-ELSE command sequencing

The following continuation rules apply for the IF-THEN-ELSE command sequencing.

1. IF (condition) must be followed by a THEN on the same line or a continuation of that line.

```
Examples:
```

```
IF LASTCC = 0 THEN COPYDUMP ...
or
IF LASTCC = 0 -
    THEN COPYDUMP ...
```

2. THEN must be followed by a command or DO on the same line or a continuation of that line.

#### Examples:

```
IF LASTCC = 0 -
THEN -
COPYDUMP ...
```

```
Or

IF LASTCC = 0 -
THEN DO
COPYDUMP
PRINT ...
FND
```

3. ELSE must be the first word on a line and no continuation character should be used on the preceding line.

```
Example:

IF LASTCC = 0 -
THEN
COPYDUMP ...
ELSE -
PRINT ...
```

### **Nesting IF commands**

An IF command in a THEN or ELSE clause is a nested IF command. The maximum level of nesting is 10, starting with the first time you specify IF.

Within a nest of IF commands, the innermost ELSE clause is associated with the innermost THEN clause, the next innermost ELSE clause with the next innermost THEN clause, and so on. If there is an IF command that does not require an ELSE clause, use a null ELSE clause (see "Creating a null command" on page 508), unless the nesting structure does not require one. If a nesting structure does not require a null ELSE clause, the DFSMSdss job stream tells you.

## Examples of controlling task processing for the IF-THEN-ELSE command

The following are examples of controlling task processing for the IF-THEN-ELSE command.

**Example 1:** Nested IF commands are used to determine whether a COPYDUMP, EOJ, or PRINT command is to be processed:

```
IF LASTCC > 4 -
THEN IF MAXCC < 12 -
THEN COPYDUMP ...
ELSE EOJ
ELSE IF LASTCC = 4 -
THEN
ELSE PRINT...
```

If the value of LASTCC is greater than 4, the value of MAXCC is to be tested. If the value of MAXCC is less than 12, the COPYDUMP command is processed, Otherwise, the EOJ command is processed. If LASTCC is 4, no action is taken. If LASTCC is less than 4, the PRINT command is processed.

**Example 2:** Nested IF commands are used to determine whether a COPYDUMP or a PRINT command is to be processed:

```
IF LASTCC > 4 -
THEN IF MAXCC < 12 -
THEN COPYDUMP ...
ELSE
ELSE IF LASTCC = 4 -
THEN PRINT ...
```

### Syntax—Auxiliary Commands

If the first IF clause finds that LASTCC is greater than 4 and the second IF command finds that MAXCC is 12 or greater, no function command is processed. The null ELSE command specifies that the next ELSE corresponds to the first THEN.

### Common continuation errors

The continuation rules, described in Chapter 15, "Specifying DFSMSdss commands," on page 249, must be followed carefully when auxiliary commands, comments, or blank records appear in your input. You must also be careful not to inadvertently specify a null clause when continuing auxiliary commands.

The following examples show common continuation errors.

### Error example 1:

```
IF LASTCC = 0 -
 THEN
    PRINT ...
```

A continuation character (hyphen) is missing after THEN; consequently, a null THEN clause is assumed. The PRINT command is unconditionally processed.

### Error example 2:

```
IF LASTCC = 0 -
 THEN -
   COPYDUMP ...
    /* ALTERNATE PATH */
 ELSE -
PRINT ...
```

Because no continuation character (hyphen) follows the comment, a null ELSE clause is assumed. ELSE is not matched with THEN, and an error message is issued. The PRINT command is ignored. Notice the correct use of the continuation character on the other lines.

### Error example 3:

```
PRINT INDD( - /*COMMENT*/
 DDN1)
```

The DDN1 on the second line is ignored and nothing is printed because characters other than blanks appear after the continuation character (hyphen).

### EOJ command—ending your DFSMSdss step

With the end-of-job (EOJ) command, you can end your DFSMSdss step after the currently processing operation or scheduled tasks are completed. The command syntax is:

▶►--E0J-

## Chapter 19. DFSMSdss stand-alone services

This topic, which describes the Stand-Alone Services function, is intended for the storage administrator, the system programmer, or anyone who runs the Stand-Alone Services program.

You can use Stand-Alone Services to perform either a full-volume or a tracks restore from dump tapes produced by DFSMSdss. The Stand-Alone Services function offers the following benefits:

- Provides user-friendly commands to replace the previous control statements
- Supports IBM 3494 and 3495 tape libraries and 3590 tape subsystems
- Supports IPLing from a DASD volume, in addition to tape and card readers
- Allows you to predefine the operator console to be used during Stand-Alone Services processing

### Preparing to run the stand-alone services program

The Stand-Alone restore function is a single-purpose program designed to allow the system programmer to restore vital system packs during disaster recovery without needing to rely on a z/OS environment. Stand-Alone Services runs independently from a system environment either as a "true" stand-alone system or under a VM system.

This topic helps you to prepare your environment before you IPL and run the Stand-Alone Services program. Information is provided about running Stand-Alone Services in different processor operating modes, running with a predefined console, setting up tape library and device options, and using command syntax and processing options.

The Stand-Alone Services program operates on an IBM System/390® processor in either S/390 mode or S/370 mode. The Stand-Alone Services program can run on a processor that is in BASIC or LPAR mode, or you can run the Stand-Alone Services program in a virtual machine under VM.

The Stand-Alone Services program operates in extended control (EC) mode and requires 2MB of real storage.

**Virtual Machine (VM) Note:** To specify EC mode while the Stand-Alone Services program is running under VM/370, enter:

CP SET ECMODE ON

## Running stand-alone services in 370 mode

The following conditions apply to Stand-Alone Services operations in 370 mode:

- Tape libraries are not supported by Stand-Alone Services in 370 mode.
- The initial program load (IPL) device and the console must be attached to the same processor you IPLed from (when there are two or more processors).
- For DASD and tape devices:
  - In 370 mode, Stand-Alone Services does not issue Assign or Unassign commands for tape devices, or Device Reserve or Device Release commands for DASD devices.

#### Stand-Alone Services

- The user must ensure that all devices to be used by Stand-Alone Services are not accessed by other systems during IPL and while Stand-Alone Services operations are in process.
- Potential interference from other devices can occur as follows:
  - When the Stand-Alone Services is IPLed and loaded with the operator console not predefined, a Wait PSW is loaded with the rightmost bytes containing X'FFFFFF'. The Stand-Alone Services program waits for the operator to identify the operator console. The first interrupt presented at this time is expected to be a console and is treated as such.
  - When the operator console is predefined and a problem is detected while attempting initial communication with the predefined console, Stand-Alone Services loads a Wait PSW with the rightmost bytes containing X'DDDDDD', giving the operator an opportunity to identify a console (other than the predefined console) to be used as the operator console.

Other devices can generate interrupts that interfere with Stand-Alone Services operations. If this happens, determine which device is causing the interference and follow your installation's procedures to prevent the device from interrupting until the Stand-Alone Services operation is complete.

### Running stand-alone services in XA or ESA mode

The following conditions apply to Stand-Alone Services operations in XA or ESA mode:

- For DASD and tape devices:
  - In XA or ESA mode, Stand-Alone Services issues Assign and Unassign commands for tape devices, and Device Reserve and Device Release commands for DASD devices (if the command is supported by the device).

VM Note: When running Stand-Alone Services under VM, if the Stand-Alone Services program does not run to completion or is unable to free the device, an Assign or Reserve condition may be left outstanding.

- The user must ensure that the devices to be used by Stand-Alone Services are not accessed by other systems while Stand-Alone Services IPL and operations are in progress.
- Potential interference from other devices can occur as follows:
  - When the Stand-Alone Services is IPLed and loaded with the operator console not predefined, a Wait PSW is loaded with the rightmost bytes containing X'FFFFFF'. The Stand-Alone Services program waits for the operator to identify the operator console. The first interrupt presented at this time is expected to be a console and is treated as such.
  - When the operator console is predefined and a problem is detected while attempting initial communication with the predefined console, Stand-Alone Services loads a Wait PSW with the rightmost bytes containing X'DDDDDD', giving the operator an opportunity to identify a console (other than the predefined console) to be used as the operator console.

Other devices can generate interrupts that interfere with Stand-Alone Services operations. If this happens, determine which device is causing the interference. If the interrupting device is not on the same channel path ID (CHPID) as the devices you are using for Stand-Alone Services processing, configure that CHPID offline, re-IPL the Stand-Alone Services program, and configure the CHPID back online after processing is complete. If the interrupting device is on the same CHPID as the devices you are using for Stand-Alone Services processing, follow your installation's procedures to prevent the device from interrupting until after the operator console has been identified.

### Running stand-alone services with a predefined console

Use the OPERCNSL keyword of the BUILDSA command to predefine the console when creating the Stand-Alone Services program. The OPERCNSL keyword allows you to specify the address of the device to be used as the operator console, or you can specify OPERCNSL(SERV) to use an ES/9000 service console.

The device must also be a valid device within the configuration that is running the Stand-Alone Services program. DFSMSdss performs limited validation of the OPERCNSL keyword during the BUILDSA processing. This is because the Stand-Alone Services program may be run with a system configuration different from the one that is used to build the core image with the BUILDSA command. (The core image is the executable module that is loaded into the processor's storage during IPL).

After it is IPLed, Stand-Alone Services attempts to use the predefined device as the operator console instead of waiting for the first interrupt to identify the operator console. If a problem with the predefined device is detected, the processor enters a wait-state with the rightmost bytes of the PSW containing "DDDDDD". This PSW indicates that Stand-Alone Services is unable to use the predefined device and is waiting for the operator to identify another console to be used as the operator console. If this happens, do the following:

- 1. Determine the cause of the problem with the predefined device and take steps to correct the problem. Some of the possible reasons for a problem being detected are listed below.
- Generate an interrupt on a different console that you can use as the operator console.

The following are some of the reasons for a problem being detected with the predefined console:

- An error has occurred during the Stand-Alone Services program's initial communication with the predefined console.
- The console address may have been incorrectly specified when the Stand-Alone Services program IPL-able core image was built. For example, the address that was specified with the OPERCNSL keyword of the BUILDSA command does not exist in the configuration in which the Stand-Alone Services program is being IPLed.
- The device at the address specified with the OPERCNSL keyword cannot be identified as a supported operator console.
- If the console was predefined to be the service console, the necessary features may not exist on the processor for Stand-Alone Services to communicate with the console.

### Using a tape library

This topic explains how to use the IBM 3494 and 3495 tape libraries to IPL Stand-Alone Services and restore your dump data set tapes, and how to use the tape library menu options.

#### Note:

- 1. Stand-Alone Services supports IBM tape libraries in XA or ESA mode only.
- 2. Tape drives to be used for Stand-Alone Services must remain offline to other systems.
- 3. The IPL tape must be mounted and ready prior to performing the IPL.

### Stand-Alone Services

The Stand-Alone Services RESTORE and TAPECNTL commands are supported by devices within IBM 3494 and 3495 tape libraries. Table 25 shows the options available when you use a tape library to IPL the core image or restore from dump tapes. Stand-Alone Services can use the tape library in different ways depending on the features that exist on the tape library.

You cannot use the DFSMSdss Stand Alone Restore program with a tape encrypted through an encryption capable tape drive. If you attempt to do so, DFSMSdss issues message ADRY3501I to indicate that the dump data set resides on an encrypted tape and thus, cannot be read with the Stand Alone Restore program. DFSMSdss also issues message ADRY509D to prompt the operator to continue or end the function.

Similarly, you cannot use the DFSMSdss BUILDSA command to build a stand-alone image on a hardware encrypted tape. If encryption is to be used in the encryption-capable tape drive, DFSMSdss fails your request with message ADR992E.

### IPLing and restoring from a tape library

Use one of the options shown in Table 25 to either IPL the Stand-Alone Services program or to restore data from dump data set tapes.

Table 25. Stand-Alone Services Options when Using an IBM 3494 or 3495 Tape *Library.* Procedures referred to in this table appear later in this section.

	Can You Perform the Task Using an IBM Tape Library with:										
Task ↓	No "Setup Stand-Alone Device" Feature?	"Setup Stand-Alone Device" Feature Only?	Both "Setup Stand-Alone Device" and "Transient Mount" Features?								
IPL the Core image	No.	Only for tapes <b>inside</b> the library. Use Procedure A.	For tapes <b>inside</b> the library, use Procedure A. For tapes <b>outside</b> the library, use Procedure B.								
Restore from Dump Tapes	Only for tapes inside the library. Use the TAPEVOLSER keyword of the RESTORE command.	Only for tapes inside the library. Either use Procedure A or use the TAPEVOLSER keyword of the RESTORE command.  Only one method can be used for a single invocation of the RESTORE command.	For tapes inside the library, either use Procedure A or use the TAPEVOLSER keyword of the RESTORE command. For tapes outside the library, use Procedure B.  Only one method can be used for a single invocation of the RESTORE command.								

Note: When the "Setup Stand-Alone Device" feature is used to mount tapes, Stand-Alone Services treats the tape drive as if the drive is not part of a tape library.

### Identifying procedures to mount and demount tapes using the IBM Tape Library Stand-Alone Device setup features

The following procedures to mount and demount the Stand-Alone Services IPL tape and dump data set tapes are referenced within Table 25. Use Procedure A for tapes that reside inside the library. Use Procedure B for tapes that reside outside the library.

Note: When both the IPL tape and the dump data set tapes are mounted from the input station (Transient Mount), the same tape drive must be used for both the IPL tape and the dump data set tapes, rather than using different tape drives.

### **PROCEDURE A**

Use this procedure for tapes residing **inside** the library.

### Mounting —

Mount tapes using the Library Manager Console "Setup Stand-Alone Device" window.

- 1. Select the Mount a single volume option.
- 2. Type the device type.
- 3. Type the volume serial number.
- 4. Click Enter.
- 5. Repeat steps 1–3 for each tape that you want to mount.

**Requirement:** Mount the first dump data set tape prior to IPLing the Stand-Alone Services program when separate tape drives are used for the IPL tape and the dump data set tapes.

### Demounting —

Demount and unload tapes using the Library Manager Console "Setup Stand-Alone Device" window or use the TAPECNTL command. (These instructions apply only to tapes that are not unloaded by Stand-Alone Services [for example, the IPL tape]).

- 1. Select the **Demount a single volume** option.
- 2. Type the device type.
- 3. Click Enter.

#### PROCEDURE B

Use this procedure for tapes residing **outside** the library.

#### Mounting —

Mount tapes using the Library Manager Console "Setup Stand-Alone Device" window.

- 1. Select the Mount from Input Station option.
- 2. Type the device type.
- 3. Type the volume serial number.
- 4. Click Enter.
- 5. Repeat steps 1–3 for each tape that you want to mount.

Requirement: Mount the first dump data set tape prior to IPLing the Stand-Alone Services program when separate tape drives are used for the IPL tape and the dump data set tapes.

### Demounting —

When the IPL tape is the only tape that is mounted from the input station, unload and demount the tape after the Stand-Alone Services Restore operation has completed. Do this by canceling the mount from the input station using the Library Manager Console.

For additional information about tape library operations, refer to the appropriate IBM Tape Library operator's guide.

### Using an automatic cartridge loader

A tape drive with an automatic cartridge loader can be set to manual mode or auto mode. When the loader is set to manual mode, you must manually remove the tape and mount subsequent tapes when Stand-Alone Services has unloaded the tape in the drive and is waiting for a subsequent tape to be mounted.

When the loader is set to auto mode, you can premount the tapes in the order that they will be needed. When Stand-Alone Services unloads the tape in the drive, the cartridges continue to feed and load without requiring intervention.

### Controlling command sequence processing

You can control Stand-Alone Services command processing by using SET and IF-THEN-ELSE command sequences. For more information about these commands, see "Controlling task processing" on page 504.

### IPLing and running the Stand-Alone Services Program

This topic contains an overview of the Stand-Alone Services process, the procedure to IPL Stand-Alone Services, and specific information about the RESTORE and TAPECNTL commands.

Figure 21 on page 517 shows an overview of the Stand-Alone Services data restoration process.




Figure 21. Stand-Alone Services Restore Process Overview

The following is an overview of the steps necessary to implement the Stand-Alone Services program:

- 1. Prepare for Stand-Alone Services by setting up the environment as described in "Preparing to run the stand-alone services program" on page 511, and creating a Stand-Alone Services IPL-able core image with the BUILDSA command. The BUILDSA function is not part of Stand-Alone Services, yet it is necessary before Stand-Alone Services can be IPLed in a stand-alone environment. The BUILDSA command is described in "BUILDSA command for DFSMSdss" on page 271.
- 2. **IPL** the Stand-Alone Services program from your specified tape, DASD, or card reader device.
- 3. **Restore** your dumped volumes with the RESTORE command. The RESTORE command performs a full-volume or tracks restore from a DFSMSdss-formatted dump tape.
  - Use the TAPECNTL command to rewind and unload a tape under Stand-Alone Services control rather than perform this function manually.

### IPLing Stand-Alone Services

This topic lists the steps to IPL the Stand-Alone Services program. The programming status word (PSW) wait-state codes (encountered during Stand-Alone Services processing) are found in "Interpreting wait-state codes" on page 520. An example of the Stand-Alone Services system IPL is included in "IPL example" on page 519.

To IPL from the Stand-Alone Services core image (created with the BUILDSA command), proceed as follows:

### 1. Load the Stand-Alone Services Program.

Load Stand-Alone Services from the processor's IPL console by specifying the IPL address for the device (card, tape, or DASD) that contains the IPL-able core image and then, by performing a Load Clear operation (also referred to as an IPL Clear).

### 2. Select the Operator Console.

When the Stand-Alone Services program has finished loading, one of the following conditions exist:

- If the Stand-Alone Services core image was created without specifying the OPERCNSL keyword, then the processor enters a wait-state with the rightmost bytes of the PSW containing "FFFFFF". Press the Enter key on the operator console you are using. The first interrupt presented is expected to be a console and is treated as such.
- If the Stand-Alone Services core image was created with the OPERCNSL keyword specified, then Stand-Alone Services attempts to use the device address specified by OPERCNSL as the operator console, rather than waiting for the first interrupt. See "Running stand-alone services with a predefined console" on page 513 for more information.

### 3. Specify the Input Device.

After the operator console is identified, the following message is displayed: ADRY005E DEFINE INPUT DEVICE, REPLY 'dddd,ccuu' or 'CONSOLE'

To specify the operator console as the input device, enter CONSOLE or a null line. To specify a different device type, enter dddd,ccuu, where dddd is either the device type or card, and ccuu is the unit address. For example, to select a 3505 card reader at address 502, enter:

```
card, 502
```

The input device can be one of the supported console devices or a card reader device.

### 4. Specify the Message Output Device.

After the input device is identified, the following message is displayed: ADRY006E DEFINE OUTPUT DEVICE, REPLY 'dddd,ccuu' or 'CONSOLE'

To specify the operator console as the output device for operator communication, enter CONSOLE or a null line. To specify a different device type, enter dddd,ccuu, where dddd is either the device type or prnt, and ccuu is the unit address. For example, to select a 3800 print subsystem at address 510, enter:

```
prnt,510
```

The output device can be a supported console device or a supported printer

### 5. Specify the correct date and time, if needed.

Stand-Alone Services automatically picks up the time and date from the processor's time-of-day (TOD) clock, usually in the Greenwich Mean Time (GMT) format. When the TOD clock is incorrect or is not set, the following message is displayed:

ADRY015E SUPPLY TODAY'S DATE, REPLY 'MM/DD/YY'

When you have entered the correct date in the format indicated, the following message is displayed:

ADRY016E SUPPLY TIME OF DAY, REPLY 'HH:MM:SS'

Enter the correct time in the format indicated. If you press Enter without specifying a date or time, the value is set to zero.

At this point the IPL is complete. You can now enter Stand-Alone Services commands from the specified input device. Multiple commands can be entered without requiring a re-IPL of the Stand-Alone Services program.

Note: Operator messages such as ADRY003D are sent to the operator console, not the specified output device.

## IPL example

In the following example, the operator console is defined as both the input device and output device. System messages are highlighted in **bold** followed by the user's response. The example shows how more than one command can be entered without requiring a re-IPL.

```
ADRY005E DEFINE INPUT DEVICE, REPLY 'DDDD, CCUU' OR 'CONSOLE'
ENTER INPUT/COMMAND:
{The Enter key is pressed}
ADRY006E DEFINE OUTPUT DEVICE, REPLY 'DDDD, CCUU' OR 'CONSOLE'
ENTER INPUT/COMMAND:
{The Enter key is pressed}
SA/XA/ESA 5650-ZOS DFSMSDSS STAND-ALONE V2.01.0
TIME: 16:36:23 08/19/13
ENTER INPUT/COMMAND:
restore frmdv(tape) frmadr(faf) toadr(f4a) vfy(tstb04)
 RESTORE FRMDV(TAPE) FRMADR(FAF) TOADR(F4A) VFY(TSTB04)
ADRY0001I FUNCTION COMPLETED, HIGHEST CONDITION CODE WAS 0
          16:38:05
                      08/19/13
ENTER INPUT/COMMAND:
restore frmdv(tape) frmadr(faf) toadr(f4a) -
RESTORE FRMDV(TAPE) FRMADR(FAF) TOADR(F4A) -
ENTER INPUT/COMMAND:
vfy(tstb04)
VFY (TSTB04)
ADRYO0011 FUNCTION COMPLETED, HIGHEST CONDITION CODE WAS 0
          16:39:48
                      08/19/13
ENTER INPUT/COMMAND:
```

## Interpreting wait-state codes

The following programming status word (PSW) wait-state codes can occur during the Stand-Alone Services IPL:

#### Code Explanation

- **000033** A program check occurred while Stand-Alone Services was being loaded. Contact your software service representative.
- **000044** The IPL device is not operational. Contact your hardware service representative. If the IPL device is a tape drive, try to IPL from another tape drive.
- 000055 An I/O error occurred on the IPL device or channel while Stand-Alone Services was being loaded. Contact your hardware service representative to correct the cause of the problem.
- **000066** The IPL loader is unable to determine if the entire Stand-Alone Services core image has been loaded. This could be due to a software or hardware error. Determine the cause of the problem and contact the appropriate service representative.
- **000077** The IPL loader is unable to locate the SYS1.ADR.SAIPLD.V*volser* data set on the IPL volume.

**000088** The device type being used to IPL is not a supported DASD device for IPLing the Stand-Alone Services.

## 0000AE

An external interrupt occurred while Stand-Alone Services was being loaded. Contact your software service representative.

#### 0000AF

A supervisor call instruction (SVC) interrupt occurred while Stand-Alone Services was being loaded. Contact your software service representative.

## 0000E2

A machine check has occurred. Contact your hardware service representative.

#### 00BCBC

An attempt was made to IPL a processor that is in BC mode. IPL on a processor that supports EC mode. When you IPL from a VM user ID, set it to EC mode. This PSW is only loaded if you are IPLing from card or tape.

11111 Stand-Alone Services is waiting for an I/O interrupt. If the processor stops with this code loaded it may be necessary to re-IPL and rerun the command. Contact your hardware service representative if the problem persists.

888888 A temporary wait for a service-signal interrupt.

999999 A temporary wait for a service-signal interrupt.

### **BBBBBB**

Stand-Alone Services is waiting for the operator to enter the input in response to a prompting message on the service console.

### **DDDDDD**

Stand-Alone Services has detected an error related to the predefined console, and is waiting for the operator to identify another console to be used as the operator console. Possible reasons for the error with the predefined console and actions to take are listed in "Running stand-alone services with a predefined console" on page 513.

## EE4990

Stand-Alone Services cannot find a required module. Refer to message ADRY4990I for more information.

#### **EEEE**nn

The processor is in a wait-state. The error is indicated by *nn* as follows:

#### nn Indicates:

- An SVC interrupt has occurred. Run the SADMP\* service aid to dump the contents of real storage to tape, and contact your software service representative.
- A program interrupt has occurred. Run the SADMP\* service aid to dump the contents of real storage to tape, and contact your software service representative.
- There is insufficient main storage. Stand-Alone Services requires 2MB of storage.
- An I/O error has occurred.
- Stand-Alone Services is unable to open a data set or access a device, possibly because the device type is not supported.

#### **Stand-Alone Services**

- 18 Stand-Alone Services cannot send an operator message because the console is either not defined or is unavailable.
- 19 An end-of-data routine is missing. Run the SADMP\* service aid to dump the contents of real storage to tape, and contact your software service representative.
- **1A** The predefined console is not attached or is not operational. Possible reasons for this error are listed in "Running stand-alone services with a predefined console" on page 513.
- 1B Stand-Alone Services is unable to communicate with the predefined service console. This may be due to an error, or because the necessary features do not exist on the processor to communicate with the predefined console.

Note: See z/OS MVS Diagnosis: Tools and Service Aids for information on creating a stand-alone dump with the AMDSADMP (SADMP) service aid.

#### EECC03

A condition code 3 (not operational) has been received when attempting to communicate with the service console. Contact your hardware service representative.

#### **EECCCC**

An error occurred while trying to communicate with the service console. This can result from a hardware or a software problem.

#### F1F1F1

Waiting for an I/O interrupt while Stand-Alone Services is being loaded.

#### **FFFFFF**

Stand-Alone Services is waiting for the operator to identify the operator console. Generate an interrupt from the console that is to be used as the operator console.

# RESTORE—restoring a formatted dump tape

Use the RESTORE command to perform either a full-volume or a tracks restore from dump tapes produced by DFSMSdss without the use of a system environment.

The RESTORE command can restore from tape volumes created by a full-volume or tracks dump, or it can restore a track or tracks from the first logical volume of a physical data set dump. It cannot restore from tapes created by a DFSMSdss logical dump, from a DFSMSdss tracks dump using the CPVOLUME keyword, or from dump tapes produced by other utilities.

With the RESTORE command you specify both the source tape volume (containing the dump data set) and the DASD target volume. Use either IBM standard label or nonlabeled tapes as the source tape volumes (dump tapes) for the Stand-Alone Services restore operation. If the volume serial number of the DASD target volume is different from the volume serial number of the original DASD source volume, the restore operation changes the DASD target volume serial number to that of the DASD source volume.


When IPLing from tape, the data to be restored can be mounted on a tape drive other than the IPL tape drive. Alternatively, a single tape drive can be used to mount the tape to be IPLed and the tape to be restored.

The device type of the DASD source volume used for the system dump must match the device type of the receiving volume used in a Stand-Alone Services restore operation. However, dump data from a smaller capacity (fewer cylinders) device can be restored to a larger capacity (more cylinders) device of the same device type.

**Note:** When data is restored from a smaller capacity device to a larger capacity device, the free space information becomes invalid. The free space information in the VTOC is rebuilt when the next data set is allocated on the volume.

## **RESTORE** command syntax

The syntax of the Stand-Alone RESTORE command is:



See "Command syntax" on page 249 for command and comment formatting specifics

### Required parameters

#### **FROMDEV**

Specifies the device type that the dump data set resides on. Eligible device names are 3400 and TAPE. When either 3400 or TAPE is specified, Stand-Alone Services attempts to determine the device type from the self-description information. If the device self-description information indicates a supported device type, Stand-Alone Services uses the returned device type for processing. When a device does not support self-description, Stand-Alone Services processes the device differently depending on whether 3400 or TAPE is specified. Abbreviations: FRMDEV and FRMDV.

3400 specifies device types 3420, 3422, and 3430. If the device type cannot be determined from the self-description information, Stand-Alone Services processes the device as a 3400-type device.

**TAPE** specifies all other supported tape devices. If the device type cannot be determined from the self-description information, Stand-Alone Services processing ends.

#### **FROMADDR**

Specifies the address of the device that the dump data set resides on. You can specify a 3-digit or 4-digit address. Abbreviations: FRMADDR and FRMADR.

#### **TOADDR**

Specifies the address of the DASD target device to be restored. The device type must be the same as the device type of the volume originally dumped. You can specify a 3-digit or 4-digit address. Abbreviation: TOADR.

#### **VERIFY** (volser)

Specifies that the volume serial number that is currently on the DASD target volume must be verified before restoring the data. Specify either VERIFY or NOVERIFY, not both.

Initialize DASD volumes with a readable volume label and VTOC before restoration. Abbreviation: VFY.

#### **NOVERIFY**

Specifies that no action be taken to either verify the volume serial number, or to verify that any volume serial number exists. When NOVERIFY is specified, a prompting message is issued for the user to reply with permission to continue. Specify either VERIFY or NOVERIFY, not both. Abbreviations: NOVFY and NVFY.

## Optional keywords

FULL Specifies that the full volume be restored. The dump data set must be a DFSMSdss full-volume physical dump. The default is FULL.

#### **STARTTRK**

Specifies that the designated range of tracks be restored. The dump data set can be a full-volume physical dump, a tracks dump, or a physical data set dump. Specify the STARTTRK keyword with a tracks dump or a physical data set dump. STARTTRK is not valid when FULL is specified.

Specify the track in the form (ccccccc,h), where cccccc is the cylinder number and h is the head number. You can specify the cylinder and head numbers in either decimal or hexadecimal (for example, X'AC',X'E' for hexadecimal or 172,14 for decimal). Leading zeros are not required. The STARTTRK keyword is processed as follows:

- When the ENDTRK keyword is not specified, the ending track is set to the last track on the volume.
- When the starting track value is higher than the ending track value, an error message is issued and the restore operation ends.
- When the starting track value exceeds the volume limits, an error message is issued and the restore operation ends.

Abbreviations: STRTRK and STRK.

#### **ENDTRK**

Specifies the ending track to be restored when STARTTRK is specified. This keyword is not valid when FULL is specified.

Specify the track in the form (ccccccc,h), where cccccc is the cylinder number and h is the head number. You can specify the cylinder and head numbers in either decimal or hexadecimal (for example, X'AC',X'E' for hexadecimal or 172,14 for decimal). Leading zeros are not required. The ENDTRK keyword is processed as follows:

 When the STARTTRK keyword is specified and the ENDTRK keyword is not specified, the ending track is set to the last track on the volume.

- When the ending cylinder value exceeds the volume limits, the ending cylinder value is set to the last cylinder on the volume, and a warning message is issued.
- When the ending head value exceeds the volume limits (exceeds the last head in a cylinder), the ending head value is set to the last head on the ending cylinder. In addition, a warning message is issued.
- When the starting track value is higher than the ending track value, an error message is issued and the restore operation is ended.

Abbreviation: ETRK.

#### READCHECK

Specifies that a read-back check of the restored data be performed. READCHECK is the default. Abbreviations: READCHK, RDCHECK, RDCHK, and READ.

## **NOREADCHECK**

Specifies that a read-back check of the restored data *not* be performed. Abbreviations: NOREADCHK, NREADCHK, and NREAD.

### **TAPEVOLSER** (tserial)

Specifies the tape volume serial numbers of the tapes to be mounted by Stand-Alone Services when the tapes are in an IBM tape library. Volumes are mounted by Stand-Alone Services in the order in which they are specified.

The maximum number of tape volume serial numbers that can be specified is 32. All of the specified tape volumes must be part of the same dump data set that is used for the restore.

The TAPEVOLSER keyword is ignored if the FROMDEV keyword does not specify a valid tape drive in a tape library.

Do not specify the TAPEVOLSER keyword when the tapes are mounted from the Library Manager Console with the Setup Stand-Alone Device Pop-up Window. See "Using a tape library" on page 513 for information about tape libraries. Abbreviations: TAPEVOL and TPVOL.

#### FILE (nnnn)

Specifies the relative position, from the beginning of the tape volume, where the dump data set begins. Allowable values are from 1 to 9999. When the FILE keyword is not specified, the default value is 1. Leading zeros are not required. If the specified file number does not exist on the tape, unpredictable results can occur. For example, on 3400 tape devices with tape reels, an incorrectly specified file number can cause the tape to run off the end of the reel.

## **RESTORE** command examples

In the following example, device address 2FAF is a 3490 tape drive with a tape mounted that contains the dump data set to be restored. Device address 4791 is a 3380 DASD with volume serial number D3380K. Before writing on the volume, the RESTORE command verifies that the DASD at address 4791 has volume serial number D3380K. The full volume is restored.

RESTORE FRMDV(TAPE) FRMADR(2FAF) TOADR(4791) VFY(D3380K)

In the following example, device address F01 is a 3420 tape drive with a tape mounted that contains the dump data set to be restored. Device address 9B9 is a

#### **Stand-Alone Services**

9345 DASD with volume serial number TS9345. Before writing on the volume, the RESTORE command verifies that the DASD at address 9B9 has volume serial number TS9345. The range of tracks to be restored is cylinder 0, head 0 through the end of the volume.

```
RESTORE FRMDV(3400) FRMADR(F01) TOADR(9B9) VFY(TS9345) STRK(0,0)
```

In the following example, device address F77 is a 3480 tape drive with a tape mounted that contains the dump data set to be restored on file 3 of the tape. Device address F4A is a 3390 DASD. The NOVERIFY keyword prompts the operator for permission to write on the device at address F4A.

```
RESTORE FRMDV(TAPE) FRMADR(F77) TOADR(F4A) NVFY FILE(3)
```

In the following two examples, device address F77 is a 3480 tape drive with a tape mounted that contains the dump data set to be restored. Device address 9B9 is a 9345 DASD with volume serial number TS9345. Before writing on the volume, the RESTORE command verifies that the DASD at address 9B9 has volume serial number TS9345. The range of tracks to be restored is from cylinder 200, head 5 through cylinder 205, head 14. The first example specifies the tracks in decimal:

```
RESTORE FRMDV(TAPE) FRMADR(F77) TOADR(9B9) VFY(TS9345) -
STRK(200,5) ETRK(205,14)
```

The second example specifies the tracks in hexadecimal:

```
RESTORE FRMDV(TAPE) FRMADR(F77) TOADR(9B9) VFY(TS9345) -
STRK(X'C8',X'5') ETRK(X'CD',X'E')
```

In the following example, device address FDD is a tape drive in a 3495 Tape Library, and the tape volume with volume serial number BCD103 contains the dump data set to be restored. Device address F4A is a 3390 DASD. The NOVERIFY keyword of the RESTORE command prompts the operator for permission to write on the device at address F4A. Stand-Alone Services mounts the tape volume with volume serial number BCD103 on the tape drive with address FDD. The range of tracks to be restored is cylinder 0, head 0 through cylinder 5, head 5.

```
RESTORE FRMDV(TAPE) FRMADR(FDD) TOADR(F4A) NVFY -
TAPEVOL(BCD103) STRK(0,0) ETRK(5,5)
```

In the following example, device address FDD is a tape drive in a 3495 Tape Library, and the tape volumes with volume serial numbers BCD101 and BCD102 contain the dump data set to be restored. Volume BCD101 is the first volume in the sequence, and BCD102 is the second volume. Device address 791 is a 3380 DASD. The NOVERIFY keyword of the RESTORE command prompts the operator for permission to write on the device at address 791. Stand-Alone Services mounts the tape volumes on the tape drive with address FDD. Volume BCD101 is mounted first, and when the end of the tape is reached volume BCD102 is mounted.

```
RESTORE FRMDV(TAPE) FRMADR(FDD) TOADR(791) NVFY -
TAPEVOL((BCD101) (BCD102))
```

# TAPECNTL—rewinding and unloading a tape


Use the TAPECNTL command to either rewind, or rewind and unload a tape.

Stand-Alone Services gives you the ability (with the REWIND and UNLOAD keywords) to rewind and unload tapes under Stand-Alone Services control rather than doing so manually.

The TAPECNTL command supports devices that are part of IBM 3494 and 3495 Tape Libraries.

# TAPECNTL command syntax

The syntax of the TAPECNTL command is:



See "Command syntax" on page 249 for command and comment formatting specifics.

# Required keywords

### **DEVTYPE**

Specifies the tape device type that the TAPECNTL operation is to be performed against. Eligible device names are 3400 and TAPE. When either 3400 or TAPE is specified, Stand-Alone Services attempts to determine the device type from the self-description information. If the device self-description information indicates a supported device type, Stand-Alone Services uses the returned device type for processing. When a device does not support self-description, Stand-Alone Services processes the device differently depending on whether 3400 or TAPE is specified. Abbreviation: DEV.

3400 specifies device types 3420, 3422, and 3430. If the device does not support self-description, Stand-Alone Services may not be able to determine if the device is a tape drive. Stand-Alone Services issues the rewind or unload instruction to the device anyway. When the device is not a tape drive, unpredictable results may occur.

TAPE specifies all other supported tape devices. Stand-Alone Services does not issue rewind or unload instructions to the device when Stand-Alone Services cannot determine the device type from the self-description.

#### **UNITADDR** (ccuu)

Specifies the unit address of the device against which the TAPECNTL operation is performed. You can specify a 3-digit or 4-digit address. Abbreviations: UNIT and ADDR.

### **REWIND**

Specifies a rewind operation. Specify either the REWIND keyword or the UNLOAD keyword, not both. Abbreviation: REW.

#### **UNLOAD**

Specifies that a rewind and unload operation be performed. If the tape drive is in an IBM tape library, the tape is demounted if necessary. Abbreviation: UNL.

## TAPECNTL command examples

In the following example, the TAPECNTL command rewinds the tape mounted in the 3490 tape drive at address 2FAF:

TAPECNTL DEV(TAPE) UNIT(2FAF) REW

In the following example, the TAPECNTL command rewinds and unloads the tape mounted in the 3480 tape drive at address F77:

TAPECNTL DEV(TAPE) UNIT(F77) UNL

In the following example, the TAPECNTL command rewinds and unloads the tape mounted in the 3420 tape drive at address F01:

TAPECNTL DEV(3400) UNIT(F01) UNL

# Building the IPL-able core image

This topic describes how to use the BUILDSA command to build the Stand-Alone Services IPL-able core image. The core image is the executable module that is loaded into the processor's storage during the IPL and load process.

## **BUILDSA** function

The BUILDSA function is not part of Stand-Alone Services, yet it is necessary before Stand-Alone Services can be IPLed in a stand-alone environment. The DFSMSdss BUILDSA command and examples are presented in "BUILDSA command for DFSMSdss" on page 271.

# Understanding BUILDSA command authorization levels

Your ability to use the BUILDSA command is determined by your level of access authorization to source (input) data sets and target (output) data sets or volumes used by the BUILDSA operation. Storage administrators with any of the following access levels may use the BUILDSA command:

- Without special authorization
- DASDVOL-access authority to a volume
- · DFSMSdss authorization

# Using BUILDSA without special authorization

To use the BUILDSA command, you must have the following data-set-level authorization to build the IPL-able core image for card or tape:

- READ access to the input data sets used by the SYS1.SADRYLIB target library
- UPDATE access to the output card or tape data sets

Without special authorization, you cannot create an IPL-able core image for DASD. Even though you may have UPDATE or ALTER access to the output SYS1.ADR.SAIPLD.V*volser* data set, you are not authorized to update cylinder 0 head 0 of the DASD volume.

## Using BUILDSA with DASDVOL-access authorization

To use the BUILDSA command for IPL(DASD), you must have the following access:

- READ access to the input data set (SYS1.SADRYLIB)
- UPDATE access at the DASDVOL level for each DASD volume on which you create an IPL-able core image

## Using BUILDSA with the ADMINISTRATOR keyword

Instead of having DASDVOL update access to volumes for IPL(DASD), you can act as a DFSMSdss-authorized storage administrator for the BUILDSA command by specifying the ADMINISTRATOR keyword.

The FACILITY-class profile STGADMIN.ADR.STGADMIN.BUILDSA for the BUILDSA command ADMINISTRATOR keyword lets you build the Stand-Alone Services IPL-able core image without having UPDATE access to the output data sets or UPDATE access to a DASD volume when you create a core image for IPLing from DASD. You must still have access at the data set level for the input data set.

See the ADMINISTRATOR keyword in "Explanation of BUILDSA command keywords" on page 272 for more information.

# Chapter 20. Data security and authorization checking

This section describes the data security protection and access authorization checks done by DFSMSdss. The DFSMSdss functions available to a user depend on the access authorizations as defined by:

### User and group profiles

Define the authorized users of a RACF-protected system. The user or group identifier (ID) used for access-authority checking must be defined to RACF.

## Data set and general resource profiles

Protect the resources in a RACF-protected system and identify the access levels that users have to those resources.

DFSMSdss supports data-security protection and access-authorization checking through the system authorization facility (SAF), Resource Access Control Facility (RACF), and system services such as catalog management services and allocation. The phrase "RACF-protected" implies that SAF and RACF (or equivalent) are installed and active.

DFSMSdss uses the SAF interface and checks to ensure that RACF at the 1.8.1 level or later is installed and active. If an equivalent to RACF is used, either it must set the same level information that DFSMSdss checks, or your installation must use the DFSMSdss installation options exit to tell DFSMSdss that SAF with a RACF equivalent is installed. The proper level of RACF must be installed for the data-security features to work as described. The primary features and their levels of RACF are listed below:

Feature	Required Level of RACF
Generic profile handling:	RACF 1.5 or later
DASDVOL access authority:	RACF 1.6 or later
FACILITY class authority:	RACF 1.7 or later
Erase-on-scratch:	RACF 1.7 or later
Group data set creation:	RACF 1.8.1 or later
Storage class and management class:	RACF 1.8.1 or later

**Related reading:** For information about the installation options exit, see *z/OS DFSMS Installation Exits*. For information about data security and RACF, see *z/OS Security Server RACF Security Administrator's Guide*.

# Effects of SPECIAL, OPERATIONS, and DASDVOL

The SPECIAL and OPERATIONS attributes and DASDVOL-access authority can affect the results when you use DFSMSdss to access and process data sets.

## **SPECIAL**

When you use DFSMSdss, the SPECIAL attribute does not give you the authority to define or rename discrete profiles during a copy, move, or restore of user data sets that you do not own. This is because DFSMSdss uses the DEFINE function of SAF and RACF and the ALTER function of catalog management services to define

and rename discrete profiles on your behalf. Instead of the system-SPECIAL attribute, you need the system-OPERATIONS attribute to define or rename discrete profiles for user data sets that you do not own.

## **OPERATIONS**

If you have the system-OPERATIONS attribute, you have authority to the protected resources in resource classes such as DATASET, DASDVOL, and TAPEVOL. You are limited to the access specified in the access list if either:

- Your current connect group (or any connect group when list-of-groups checking is active) is in the access list of a resource profile.
- Your user ID is in the access list.

As a user with the system-OPERATIONS attribute, you have full control over data sets, and you can do the following:

- Copy, reorganize, catalog, and scratch (delete) data sets
- Perform input and output operations on protected tape volumes
- · Define profiles for group data sets to which you are not connected
- Create user data sets and data sets in groups to which you are not connected. However, if your ID is in the access list, you need at least UPDATE access.

You need the system-OPERATIONS attribute to define or rename discrete profiles when you use DFSMSdss, even if you are acting as a DFSMSdss-authorized storage administrator (see "DFSMSdss storage administrator" on page 541). DFSMSdss can define or rename discrete profiles during copy or restore operations. However, the OPERATIONS attribute does not necessarily let you perform all DFSMSdss functions:

- If you have group-OPERATIONS, your authority is restricted to the resources within the scope of the group.
- The data set to be processed may be a data set over which you have no authority. For example, your user ID only has READ access to a data set that you want to copy and delete.
- A copy of a group data set may be disallowed because you are connected to the group and thus not authorized to define a discrete profile for the data set.
- Access can be denied due to security-level, security-category, or security-label checking.

## DASDVOL

DASDVOL is supported directly for volume-level operations, physical operations for both SMS-managed and non-SMS-managed data sets, and logical operations for non-SMS-managed data sets. With DASDVOL-access authority to a volume, you can perform DFSMSdss operations as described in "Volume access and DASDVOL" on page 543 and "DASDVOL limitations" on page 545. When you do so, DFSMSdss bypasses access checking to the data sets and catalogs on that volume.

You have DASDVOL-access authority to one or more DASD volumes if all of the following are true:

- · DASDVOL class is active.
- · Profiles for the DASD volumes are defined in the DASDVOL class.
- You have the level of access needed for the function you are trying to perform.

Instead of DASDVOL-access authority, your installation can authorize you to act as a storage administrator for one or more DFSMSdss operations. See "DFSMSdss storage administrator" on page 541 for details.

**Note:** The system programmer or storage administrator uses ICKDSF to format tracks, write a volume label, and create a VTOC. The system programmer or storage administrator needs to have RACF DASDVOL authority to do that. No one needs DASDVOL authority to allocate space on volumes. The system controls space on SMS volumes by other means such as ACS routines, storage group definitions, and Interactive Storage Management Facility (ISMF) commands.

# General data security information

This section contains information on the following topics:

- "Protecting resources and data sets"
- · "Protecting the usage of DFSMSdss"
- "Password protection" on page 534
- "Protected user and group data sets" on page 535
- "Generic and discrete profile considerations" on page 536
- "Security-level, category, and label checking" on page 537
- "Protect-all and always-call" on page 537
- "Standard naming conventions" on page 537
- "DFSMSdss temporary data set names" on page 538
- "Discretely protected multivolume data set" on page 539
- "Erase-on-scratch" on page 540
- "SMS-managed data set protection" on page 540
- "Logging" on page 540

# Protecting resources and data sets

A security administrator or resource owner can control access to resources by creating a discrete profile, which protects one resource, or a generic profile, which protects one or more resources. Each profile has a defined, universal access level and an access list that permit user and group IDs specific levels of access authority. When profiles control resources, DFSMSdss usage can be restricted.

# Protecting the usage of DFSMSdss

Your installation can put DFSMSdss in a protected library to restrict its use. Your installation can also limit the use of certain DFSMSdss commands, functions, and keywords by defining resource profiles in the FACILITY class and restricting access to those profiles. To use a protected command, function, or keyword, you need READ access authority to the applicable profile.

Table 26 lists those keywords and functions, and their associated RACF FACILITY class profiles. For information about the ADMINISTRATOR keyword, see "FACILITY class profiles for the ADMINISTRATOR keyword" on page 542.

*Table 26. DFSMSdss FACILITY Class Profiles.* This table maps the DFSMSdss keywords and functions to their associated FACILITY class profiles.

Keyword or Function	Profile Name
BYPASSACS with COPY	STGADMIN.ADR.COPY.BYPASSACS
BYPASSACS with RESTORE	STGADMIN.ADR.RESTORE.BYPASSACS

Table 26. DFSMSdss FACILITY Class Profiles (continued). This table maps the DFSMSdss keywords and functions to their associated FACILITY class profiles.

Keyword or Function	Profile Name
CGCREATED	STGADMIN.ADR.CGCREATE
CONCURRENT with COPY	STGADMIN.ADR.COPY.CNCURRNT
CONCURRENT with DUMP	STGADMIN.ADR.DUMP.CNCURRNT
CONSOLIDATE	STGADMIN.ADR.CONSOLID
CONVERTV	STGADMIN.ADR.CONVERTV
DEFRAG	STGADMIN.ADR.DEFRAG
DELETECATALOGENTRY with RESTORE	STGADMIN.ADR.RESTORE.DELCATE
FCCGFREEZE with COPY	STGADMIN.ADR.COPY.FCFREEZE
FCSETGTOK with COPY	STGADMIN.ADR.COPY.FCSETGT
FCTOPPRCPRIMARY with COPY	STGADMIN.ADR.COPY.FCTOPPRCP
FCTOPPRCPRIMARY with DEFRAG	STGADMIN.ADR.DEFRAG.FCTOPPRCP
FlashCopy with COPY	STGADMIN.ADR.COPY.FLASHCPY
FlashCopy with CONSOLIDATE	STGADMIN.ADR.CONSOLID.FLASHCPY
FlashCopy with DEFRAG	STGADMIN.ADR.DEFRAG.FLASHCPY
IMPORT with RESTORE	STGADMIN.ADR.RESTORE.IMPORT
INCAT(catname) with COPY	STGADMIN.ADR.COPY.INCAT
INCAT(catname) with DUMP	STGADMIN.ADR.DUMP.INCAT
INCAT(catname) with RELEASE	STGADMIN.ADR.RELEASE.INCAT
NEWNAMEUNCONDITIONAL with DUMP	STGADMIN.ADR.DUMP.NEWNAMEU
PROCESS(SYS1) with COPY	STGADMIN.ADR.COPY.PROCESS.SYS
PROCESS(SYS1) with DUMP	STGADMIN.ADR.DUMP.PROCESS.SYS
PROCESS(SYS1) with RELEASE	STGADMIN.ADR.RELEASE.PROCESS.SYS
RESET with DUMP	STGADMIN.ADR.DUMP.RESET
RESET with RESTORE	STGADMIN.ADR.RESTORE.RESET.YES
SET PATCH	STGADMIN.ADR.PATCH
TOLERATE(ENQF) with COPY	STGADMIN.ADR.COPY.TOLERATE.ENQF
TOLERATE(ENQF) with DUMP	STGADMIN.ADR.DUMP.TOLERATE.ENQF
TOLERATE(ENQF) with RESTORE	STGADMIN.ADR.RESTORE.TOLERATE.ENQF
ZCOMPRESS with DUMP	STGADMIN.ADR.DUMP.ZCOMPRESS

**Related reading:** For more information about FACILITY class profiles, see *z/OS* Security Server RACF Security Administrator's Guide.

# **Password protection**

DFSMSdss supports password checking at the data set level, but not the catalog level. If a data set is password-protected and RACF-protected, access to the data set is determined only through RACF-authorization checking (password checking is bypassed).

Data set passwords in the DFSMSdss input command do not appear in the SYSPRINT data set listing. However, if your job abnormally ends, those passwords may appear in any resultant dump. To prevent this, you can put the passwords in a data set that is referred to with a DD statement.

# Protected user and group data sets

DFSMSdss does authorization checks to ensure that you have the authority to access data sets. Your ability to access and protect a data set is affected by whether the data set is a user data set or a group data set.

#### User data set

The high-level qualifier of the name of a user data set is a RACF-defined user ID. As a RACF-defined user, you can protect your own data sets. However, when you use DFSMSdss to discretely protect a data set for another user, you need the system-OPERATIONS attribute.

Usually, you can use DFSMSdss to create new user data sets if you own them or have ALTER access to them through a data set profile or an entry in the global access checking table. You can also create a new user data set in any of the following situations:

- You are acting as a DFSMSdss-authorized storage administrator through the ADMINISTRATOR keyword.
- You have DASDVOL-access authority to the non-SMS-managed volume that the data set is being created on.
- You have the system-OPERATIONS attribute, and you have not been explicitly denied access to the data set.
- The system has *always-call*, the data set name is protected by a generic profile, and you do not have Automatic Data Set Protection (ADSP).
- The data set is not protected by a generic profile, and you do not have ADSP.

**Related reading:** For more information about *always-call*, refer to "Protect-all and always-call" on page 537. For more information about ADSP, refer to "Automatic data set protection (ADSP) attribute" on page 537.

## Group data set

The high-level qualifier of the name of a group data set is a RACF-defined group ID. As a RACF-defined user, you can RACF-protect a group data set under any of these conditions:

- You have JOIN, CONNECT or CREATE authority in the group.
- You have the group-SPECIAL attribute in the group that owns the user profile.
- You have the system-OPERATIONS attribute, and you are not connected to the group.

You can create new group data sets with the DFSMSdss COPY or RESTORE command in the following situations:

- You are acting as a DFSMSdss-authorized storage administrator through the ADMINISTRATOR keyword.
- You have DASDVOL-access authority to the non-SMS-managed volume that the data set is being created on.
- You have the OPERATIONS attribute, and you have not been explicitly denied access to the data set.

- The system has always-call, the data set name is protected by a generic profile, you have ALTER-access authority to the data set profile, and you do not have ADSP. Instead of ALTER access, you can have CREATE authority in the group and UPDATE access to the data set.
- The data set is not protected by a generic profile, and you do not have ADSP.

# Generic and discrete profile considerations

A generic or a discrete data set profile can protect a data set. The type of profile affects DFSMSdss functions, especially copy, dump, and restore.

# Generic profiles

Generic profiles can be used to protect existing data sets without turning on the RACF-indicator flag in the data set VTOC entry for a non-VSAM data set or in the catalog entry for a VSAM data set. Generic profiles can be used to permit access to data sets, deny access to data sets, and control who can create data sets. A small number of generic profiles can be used to protect many data sets.

Generic profile checking for the DATASET class must be activated by the RACF SETROPTS GENERIC(DATASET) command. An entry in the global access checking table can let a user access a data set that the generic data set profile does not. For more information, see "Global access checking table" on page 537.

## Discrete profiles

A discrete profile should be used to protect a data set only if the data set has a unique security requirement from any other resource. You can protect data sets with discrete profiles when you use the DFSMSdss COPY or RESTORE command if you have the authority to define a discrete profile to protect that data set.

When a data set is protected with a discrete profile, an indicator is set in the VTOC entry for a non-VSAM data set, in the catalog entry for a VSAM data set, or in the tape volume profile for the tape volume that contains a tape data set. This condition is called RACF-indicated.

The following are special considerations that apply to discrete profiles:

- If the data set is scratched, RACF deletes the discrete profile.
- If you rename a data set to your high-level qualifier, the data set and the discrete profile are renamed, and the owner information of the profile is changed to your user ID.
- If you rename a data set to a high-level qualifier other than your own, the owner of the high-level qualifier becomes the owner of the data set.

# Discrete and generic profile checking

For RACF-indicated data sets, RACF searches first for a discrete profile, and then, if one is not found, for a generic profile. If neither is found, access is denied. If a data set is not RACF-indicated, the data set is RACF-protected only if there is a covering generic profile. The search is done in the following order:

- 1. Discrete profile if the data set is RACF-indicated.
- 2. Fully-qualified generic profile.
- 3. Other generic profiles from the most specific to the least specific profile name.

# Global access checking table

Your installation can use entries in the global access checking table to permit, but not deny, access to data sets. Only data set profiles can be used to deny access to data sets. Each entry in the table should have a corresponding generic profile to ensure consistent processing results.

## Automatic data set protection (ADSP) attribute

If you have the ADSP attribute, RACF automatically defines a discrete profile whenever you create a permanent DASD or tape data set that is not already protected. For a tape data set, TAPEDSN and TAPEVOL must be active. If you have the ADSP attribute, you can create and protect data sets:

- · Whose names begin with your user ID.
- Whose high-level qualifier belongs to a RACF group in which you have CREATE or higher authority. Besides CREATE in the group, you also need UPDATE access to the data set when you use DFSMSdss to copy or restore a data set.

# Security-level, category, and label checking

DFSMSdss does not perform any explicit security-level, security-category, or security-label (SECLABEL) checking. For example, SECLABELs are not dumped or restored unless they are embedded within the data itself such as zFS data sets. However, DFSMSdss and the system services it uses (such as allocation) call RACF to make authorization checks that can result in access being denied because of a mismatch between the security level, security category, or security label of the resource and that of your user ID.

# Protect-all and always-call

If protect-all has been activated, you can access a data set only through a data set profile or through an entry in the global access checking table. When always-call is in effect, RACF is called whenever a data set is accessed or DASD space is allocated. When RACF is called because of always-call (and not because of RACF-indication), it only checks generic profiles and the global access checking table. If protect-all is not in effect and RACF cannot find an appropriate data set profile or entry in the global access checking table, RACF accepts the request by default. Be aware of the following conditions:

- Always-call is in effect if the data sets are cataloged.
- Data sets that are not RACF-indicated, but which are protected by generic
  profiles and always-call, are not protected if they are transferred to another
  system that does not have RACF, always-call, and appropriate generic profiles.
- VSAM data sets are protected only by the RACF profile for the cluster name. Profiles for the index- and data-component names are ignored, as are the profiles associated with any PATHs or with the cluster's alternate indexes (AIXs).

# Standard naming conventions

By default, RACF expects a data set name to consist of at least two qualifiers, with the high-level qualifier either a RACF-defined user or group ID. Single-qualifier data set names, especially for DASD data sets, affect your ability to manage or protect your data sets. For example:

- Data set name filtering is less usable for selecting data sets to be processed.
- DFSMSdss definitions of discrete data set profiles fail due to lack of correct prefix information.

 Your installation has trouble protecting the temporary data set names that DFSMSdss uses.

# DFSMSdss temporary data set names

DFSMSdss must allocate temporary data sets to perform certain functions such as copy and restore. The high-level qualifiers of those data set names can be protected, and your installation must ensure that these temporary data sets can be allocated.

### Message data set

Allocated by DFSMSdss to store messages. DFSMSdss prints messages by task, rather than intermixing them. This data set is deleted when DFSMSdss completes the operation. System-generated temporary names are used.

### Special DEFRAG data set—

Allocated by DFSMSdss to contain information about the DASD extents that are being moved. The data set name is in the following format:

SYS1.DFDSS.DEFRAG.xxxxxxxx.volser.DUMMY

where xxxxxxx represents 8 bytes of X'FF', and volser is the volume serial number of the volume being defragmented. The data set is deleted when the DEFRAG or CONSOLIDATE operation ends successfully.

If the operation is interrupted (for example, if DFSMSdss is canceled), the data set is left on the volume. To delete the data set, repeat the DEFRAG or CONSOLIDATE operation. Before doing so, observe the following considerations:

- You might need to convert an index VTOC (IXFORMAT) volume to non-indexed VTOC (OSFORMAT) before rerunning the DEFRAG or CONSOLIDATE operation. Otherwise, the volume free space values might be incorrect.
- Use the hexadecimal qualifier to prevent the deletion of this data.

#### Temporary copied data sets

Allocated by DFSMSdss when a copy is performed and deleted when the copy is completed.

The format of the temporary name depends on the number of qualifiers of the data set that is being copied:

Number of qualifiers (n)	Temporary name
1	dsnhlq.Atidasid. <i>chmmsstt</i>
2	First 2 qualifiers.Atidasid.chmmsstt
> 2	First 3 qualifiers.Atidasid.chmmsstt

The next to last qualifier Atidasid is: a combination of a fixed "A" character, a task id (tid), and an address space id (asid).

The last qualifier is *chmmsstt* where *c* is:

- Т Target cluster name
- D Target data component name
- Ι Target index component name
- U Source cluster name

- **E** Source data component name
- J Source index component name
- P Source path name
- **Q** Target path name

and hmmsstt is the time stamp information in low-order hours digits (h), minutes (mm), seconds (ss), and hundredths of a second (tt).

**Note:** In the course of copying data sets, DFSMSdss renames the source data set using the above conventions. Whenever DFSMSdss renames a data set that is protected by RACF to a temporary name, a RACF profile must exist for the temporary data set name.

### Temporary copied catalogs

Allocated by DFSMSdss when it copies a catalog. When DFSMSdss copies a catalog, two temporary data sets are used.

First, DFSMSdss allocates a temporary data set into which records are temporarily exported with the following name format:

CATHLQ.EXPORT.Thmmsstt

· where,

#### **CATHLO**

First three high-level qualifiers of the catalog being copied

hmmsstt

Time-stamp information in low-order hours digits (h), minutes (mm), seconds (ss), and hundredths of a second (tt)

Second, DFSMSdss allocates a temporary catalog with the following name format:

CATHLQ.Thmmsstt

· where,

#### **CATHLO**

First four high-level qualifiers of the catalog that is being copied

hmmsstt

Time-stamp information in low-order hours digits (h), minutes (mm), seconds (ss), and hundredths of a second (tt)

### Dummy data set

Allocated by DFSMSdss when copying or restoring volumes and an indexed VTOC needs to be rebuilt or the volume free-space values need to be recalculated. The data set name is in the following format:

SYS1.VTOCIX.DSS.TEMP.volser

where volser is the volume serial number of the volume being restored. Allocation of this data set is never successful because DFSMSdss uses dummy allocation values.

# Discretely protected multivolume data set

To create a discrete profile for a multivolume, non-VSAM, DASD data set, you must define each volume of the data set to RACF. When the data set is extended to another volume or deleted from a volume, that volume's serial number is automatically added to or deleted from the data set profile.

## Erase-on-scratch

When the erase indicator is set in a DASD data set profile, the tracks of any scratched or released data set extents that are part of the protected DASD data set are erased. Erase-on-scratch is supported for the following DFSMSdss commands:

- DUMP with DELETE
- · COPY with DELETE
- DEFRAG
- RELEASE

When DFSMSdss deletes a data set or moves data extents, the original tracks are erased if the erase indicator is set. This also applies during a copy or restore when preallocated data sets are deleted and reallocated.

# SMS-managed data set protection

A data set profile may contain a DFP segment. The DFP segment contains a RESOWNER field, which may be used to specify the owner of an SMS-managed data set that is protected by the data set profile. If a new SMS-managed data set is allocated, the user or group ID in the RESOWNER field must have at least READ access to any MGMTCLAS and STORCLAS profile used in the allocation when:

- Your installation has activated the RACF general resource classes MGMTCLAS and STORCLAS.
- Profiles have been defined in those classes to protect against unauthorized usage of an SMS management class name or a storage class name.

If RESOWNER is not specified when the data set is allocated, the user or group ID that matches the high-level qualifier is used as the data set owner. Regardless of who owns an SMS-managed data set, you can select different default values for MGMTCLAS and STORCLAS by using those parameters with the COPY or RESTORE command. When you do, RACF checks to ensure that the data set owner, rather than you, is authorized to use the specified MGMTCLAS and STORCLAS. The user or group ID must not be revoked.

Storage class and Management class authorization checking can be bypassed for logical and physical data set restore and physical data set copy processing by using the ADRPATCH Serviceability Aid with the ADMINISTRATOR keyword.

Related reading: For more information about using the ADRPATCH Serviceability Aid, see Chapter 14, "DFSMSdss patch area," on page 217.

# Logging

DFSMSdss automatically supports RACF logging as follows:

- Logging of DASDVOL-access checks is allowed for successful authorizations only. Unsuccessful attempts are not logged because the user can still gain access at the data set catalog level.
- Logging of access checking for data sets occurs as specified in the applicable data set profile. However, because catalog management services are used, DFSMSdss does not fully control logging for VSAM data sets.
- Logging of access to the FACILITY class profiles for DFSMSdss is allowed as defined for those profiles.
- DFSMSdss does not control logging of RACF DEFINE requests. DEFINE requests are made to define discrete profiles and to determine if a user has CREATE authority in a group.

- · Logging of access-level checks for a catalog occurs only once.
- Logging cannot be disabled by specifying RACFLOG=NO in the PARM statement of a DFSMSdss job. The only way to turn off logging is through the DFSMSdss installation options exit.

# **DFSMSdss storage administrator**

Your installation can use DASDVOL access authority to designate users who can act as DFSMSdss storage administrators. DASDVOL access authority lets you perform any DFSMSdss function against the data sets on that volume. However, DASDVOL access is not supported for logical operations against SMS-managed data sets. Further, DASDVOL access authority must be granted in every volume for all the data sets for which you are the storage administrator.

DFSMSdss provides an alternative to DASDVOL access authority. Your installation can define special FACILITY class profiles to let you act as a DFSMSdss-authorized storage administrator.

# ADMINISTRATOR keyword

To act as a DFSMSdss-authorized storage administrator, specify the ADMINISTRATOR keyword on the appropriate DFSMSdss command. DFSMSdss-initiated access checking to data sets and catalogs is bypassed. If you are not authorized to use the ADMINISTRATOR keyword, the command ends with an error message.

Note that certain authorization checking to RACF for data sets is unavoidable, regardless of whether the ADMINISTRATOR keyword is specified. For example, checks that are necessary to determine whether a data set has a defined RACF profile, or authorization checks that are initiated by callable services or utilities that DFSMSdss invokes such as Catalog and IEBCOPY, cannot be bypassed.

To use the ADMINISTRATOR keyword, all of the following must be true:

- · FACILITY class is active.
- Applicable FACILITY class profile is defined.
- You have READ access to that profile.

As a DFSMSdss-authorized storage administrator, your authority is for both physical and logical operations. For example, a DFSMSdss-authorized storage administrator for the COPY command can copy tracks, a full volume, or data set without having access to the individual data sets or their catalogs.

DFSMSdss tries to define a discrete profile when you copy a discretely-protected data set or when you use the MENTITY keyword. The authority to do so is not given to you by the DFSMSdss ADMINISTRATOR support. For example, to define or rename a discrete profile for a user data set that you do not own, you also need the system-OPERATIONS attribute. The ADMINISTRATOR support also does not give you authority to bypass checking for MGMTCLAS and STORCLAS authority.

Storage class and Management class authorization checking can be bypassed for logical and physical data set restore and physical data set copy processing by using the ADRPATCH Serviceability Aid in conjunction with the ADMINISTRATOR keyword.

Related reading: For more information about the ADRPATCH Serviceability Aid, see Chapter 14, "DFSMSdss patch area," on page 217.

# FACILITY class profiles for the ADMINISTRATOR keyword

The following are the names and descriptions of the FACILITY class profiles for the ADMINISTRATOR keyword.

#### STGADMIN.ADR.STGADMIN.COMPRESS

Lets you compress data sets without having UPDATE access authority to those data sets.

#### STGADMIN.ADR.STGADMIN.CONSOLID

Lets you perform a CONSOLIDATE operation without having READ access to the data sets that are moved. You can call RACF to determine if erase-on-scratch processing for a given data set must be done.

#### STGADMIN.ADR.STGADMIN.COPY

Lets you copy data sets without having access authority to the source (READ) or target (UPDATE or ALTER) data sets and their catalogs. This profile does not give you the authority to rename a data set.

#### STGADMIN.ADR.STGADMIN.COPY.DELETE

Lets you copy or copy and delete data sets without having access authority to the source (ALTER) or target (UPDATE or ALTER) data sets and their catalogs. This profile does not give you the authority to rename a data set.

#### STGADMIN.ADR.STGADMIN.COPY.RENAME

Lets you copy or copy and rename data sets, through the RENAMEUNCONDITIONAL keyword, without having access authority to the source (READ) or the target (ALTER) data sets and their catalogs. This profile does not give you the authority to delete a data set.

### STGADMIN.ADR.STGADMIN.DEFRAG

Lets you perform a DEFRAG operation without having READ access to the data sets that are moved. RACF can still be called for DFSMSdss to determine if erase-on-scratch processing for a given data set must be done.

#### STGADMIN.ADR.STGADMIN.DUMP

Lets you dump data sets without having READ access to the data sets. This profile does not give you the authority to delete a data set.

### STGADMIN.ADR.STGADMIN.DUMP.DELETE

Lets you dump or dump and delete data sets without having ALTER access to the data sets and their catalogs.

#### STGADMIN.ADR.STGADMIN.PRINT

Lets you print data without having READ access to the data sets containing the data to be printed.

### STGADMIN.ADR.STGADMIN.RELEASE

Lets you release unused space without having UPDATE access to the data sets.

#### STGADMIN.ADR.STGADMIN.RESTORE

Lets you restore data without having READ, UPDATE, or ALTER access to source and target data sets and their catalogs. This profile does not give you the authority to rename a data set.

### STGADMIN.ADR.STGADMIN.RESTORE.RENAME

Lets you restore or restore and rename data sets, through the RENAME or

RENAMEUNCONDITIONAL keyword, without having READ, UPDATE, OR ALTER access to source and target data sets and their catalogs.

# DFSMSdss volume, data set and catalog access authority

DFSMSdss checks your access authority to the volume before it performs any data set access-authorization checking. You have the required volume-level authority whenever any of the following is true:

- NOPASS was specified on the PPT statement of the SCHEDxx parmlib member for the ADRDSSU or user program which calls ADRDSSU. ADRDSSU (or its caller) is coded in the PGM parameter of the EXEC statement and should be authorized.
- Bypass authorization checking is requested by the DFSMSdss installation authorization exit. This exit cannot be used to bypass authorization checking initiated by utilities such as IEBCOPY that are invoked by DFSMSdss.
- You have the required DASDVOL access authority for the function you are trying to perform.
- You are acting as a DFSMSdss-authorized storage administrator.

For SMS-managed data sets, access authorization to create, update, or delete data sets also authorizes you to create, update, or delete entries in user catalogs. However, to add or delete any entry for an SMS-managed data set in a protected master catalog, you also need UPDATE access to the master catalog. To add or delete any non-SMS entry in any protected catalog, you need UPDATE access to the catalog.

Figure 22 on page 544 shows the major decisions that are made to determine if you are authorized to perform a function against a data resource. The figure does not represent the actual program flow in DFSMSdss.

**Related reading:** For more information about DFSMSdss use of utilities, see "Moving data sets with utilities" on page 105.

# Volume access and DASDVOL

You can use DFSMSdss to perform volume-level operations such as a full-volume dump. Instead of requiring you to have sufficient access authority to each data set on the volume, DFSMSdss supports DASDVOL access authority.

## **Data Security**




Figure 22. DFSMSdss Data Security Decisions

# **DASDVOL** access authority

When you have the required level of DASDVOL authority to a volume, as shown in Table 27 on page 545, you can perform maintenance operations such as dump, restore, scratch and rename of the data sets on that volume regardless of your

access authority to those data sets. DFSMSdss lets you catalog, re-catalog, and uncatalog the data sets on the volumes to which you have DASDVOL authority, even if you do not have RACF authority to the specific catalog. You also have access to the catalogs on the volumes to which you have DASDVOL access authority, regardless of the particular RACF definition for that catalog.

When you restore a data set, DASDVOL access checking is determined as follows:

- The volume serial number of the source volume from which the data set was originally dumped, regardless of the current status of that data set or volume.
- The volume serial number of the volume on which the data set is being restored. This volume (or volumes) may not be the same as the source volume.

*Table 27. DASDVOL Access Authority.* This table shows the DASDVOL-access authorities needed to perform volume and data-set-level functions.

Func	tion	DA	DASDVOL Access Needed		
Command	Volume	FULL	TRACKS	Data Set	
COMPRESS	Source	N/A	N/A	UPDATE	
CONSOLIDATE	Source	N/A	N/A	UPDATE	
CONVERT	N/A	N/A	N/A	N/A	
COPY	Source	READ	READ	READ	
	Target	ALTER	ALTER	UPDATE	
COPY with	Source	N/A	N/A	ALTER	
DELETE	Target	N/A	N/A	UPDATE	
COPYDUMP	N/A	N/A	N/A	N/A	
DEFRAG	Source	N/A	N/A	UPDATE	
DUMP	Source	READ	READ	READ	
DUMP with DELETE	Source	N/A	N/A	ALTER	
PRINT	Source	N/A	READ	READ	
RELEASE	Source	N/A	N/A	UPDATE	
RESTORE	Source	N/A	N/A	READ	
	Target	ALTER	ALTER	UPDATE	

#### **DASDVOL limitations**

DASDVOL access authority is not supported for logical operations on SMS-managed data sets, nor does it let you define discrete profiles. For DFSMSdss to define or rename discrete profiles, you need the authority to do so.

While DASDVOL access authority to a non-SMS-managed volume lets you move, copy, dump, or delete a catalog, you do not automatically have access to the data sets that are cataloged in it. Also, for certain operations (such as CONVERTV on an SMS-managed data set), an authorization check is performed to see if the data set owner is authorized to use the applicable MGMTCLAS and STORCLAS routines. This is true even if you have DASDVOL access authorization.

For more information about discrete profiles, see "Copy and data set profile considerations" on page 550 and "Restore and data set profile considerations" on page 557.

## Data set access authorization levels

Access to a data set is controlled by a data set profile which permits or denies access. Access-authorization checking to data sets is performed if you do not have the required volume-level authority, the volume is unprotected, or DFSMSdss is unable to determine the protection status of the volume.

If the data set and its catalog are unprotected, no authorization is required to read, update, delete, rename, move, or scratch the data set. For protected data sets, the following access authorization may be required to perform DFSMSdss functions:

- · Password specification is required. If the data set is password-protected and not RACF-protected, you must specify the appropriate password to read, update, delete, rename, move, or scratch the data set.
- · The data set is RACF-protected. Your ability to perform operations is determined by your access-authorization level:

#### **NONE**

denies you access to the data set.

**READ** lets you read the data set, and even make a copy of it, provided you have authority to create or replace the target data set.

#### **UPDATE**

lets you modify (update) an existing RACF-protected data set. UPDATE access does not let you delete, rename, move, or scratch a data set.

#### ALTER

lets you read, update, delete, rename, move, or scratch a RACF-protected data set.

ALTER access lets you create a user or group data set. CREATE authority in the group and UPDATE access also lets you create a new group data set.

The level of access authority you need to access data sets is also dependent on the following:

- Whether the data set is SMS-managed or not.
- Whether a catalog entry for the data set is added (cataloged) or deleted (uncataloged).
- Whether the catalog is an integrated catalog facility catalog.
- Whether the catalog is RACF-protected.

DFSMSdss supports VSAM data sets only if they are cataloged in an integrated catalog facility catalog. For VSAM data sets, access authorization is determined solely by your authority to access the base-cluster name: Data set profiles are ignored for any data component, index component, alternate index (processed as part of a sphere) or PATH.

# Protected catalogs

DFSMSdss only supports RACF-protection of catalogs; catalog passwords are never checked.

# Catalog access authority

DFSMSdss supports cataloged non-VSAM and VSAM data sets in an integrated catalog facility catalog.

For more information about the access authority you need, see "Access authorization for DFSMSdss commands" on page 547.

## Non-SMS versus SMS authorization

Access authorization requirements differ for SMS-managed data sets and non-SMS-managed data sets.

### SMS-managed data sets:

Access to SMS-managed data sets gives you access to the user catalog for the data sets. However, for a RACF-protected master catalog, you also need UPDATE-access authority to add or delete an SMS-managed data set entry. DASDVOL-access authority is not supported for logical operations.

### Non-SMS-managed data sets:

Besides access authority for data sets, you need UPDATE access to RACF-protected user or master catalogs to add or delete an entry in the catalog.

# System operator authorization, special data set types

Some system and VSAM data sets accept authorization from the system operator when RACF or password checking cannot be performed. Unless you are using DFSMSdss with special authorization, such as DASDVOL or the ADMINISTRATOR keyword, system-operator authorization is required in order for you to update the following:

- Volume table of contents (VTOC)
- VTOC index data set
- VSAM volume data set (VVDS)
- · Checkpoint/restart data set.

The system operator is only prompted for the first data set encountered in one of the above classes for the DFSMSdss command that is being processed. The reply given is used for that command invocation for all other data sets of that type on the volume.

# Access authorization for DFSMSdss commands

This section covers the following commands:

- CGCREATED
- COMPRESS
- CONSOLIDATE
- CONVERTV
- COPY
- COPYDUMP
- DEFRAG
- DUMP
- PRINT
- RELEASE
- RESTORE

The tables in this section can help you determine if you have sufficient access authority to use the DFSMSdss commands. The access authority you need depends on what you are trying to do. For example:

• If the data set is SMS-managed and you have access to the data set, you have access to its user catalog.

- If you have ALTER access to the data set, you can copy and delete (or dump and delete) the data set.
- If the source data set is cataloged, you may need UPDATE or ALTER access to its catalog if the data set is going to be deleted, uncataloged, or cataloged.
- To replace an existing data set using the COPY or RESTORE command, you need UPDATE access to the data set.
- If you are doing a restore with rename, ALTER-access authority lets you create a new user or group data set. If the data set belongs to a group, CREATE authority in the group and UPDATE access to that group data set name also lets you create that group data set.
- To restore a data set, you need READ access to a data set with the same name as the one that was dumped. You also need either UPDATE or ALTER access to the target data set.
- If the target data set is going to be discretely protected, and you do not own the data set, you need additional authority to define a discrete profile. This is true even if you are acting as a DFSMSdss-authorized storage administrator for the COPY or RESTORE command.
- To copy or dump a master catalog, you need ALTER access if you are not acting as a DFSMSdss storage administrator. This level of access is needed because the master catalog may contain passwords.
- · If you are acting as a DFSMSdss storage administrator, you have access to the applicable data sets and catalogs.

# **CGCREATED**

Anyone can use the CGCREATED command. However, your installation can limit usage of the CGCREATED command by use of a RACF FACILITY class profile if:

- RACF FACILITY class is active.
- The FACILITY class profile STGADMIN.ADR.CGCREATE has been defined. Then need READ access authorization to that profile to use the CGCREATED command.

## **COMPRESS**

To compress partitioned data sets on a specified volume, either you need DASDVOL-access authority to the volume or UPDATE access authority to the data sets, or you must be acting as a DFSMSdss-authorized storage administrator.

## CONSOLIDATE

To use the CONSOLIDATE command to relocate data extents on a DASD volume, you need DASDVOL-access authority to that volume or READ-access to the data sets that are relocated. Otherwise, only unprotected data sets are relocated.

As part of the CONSOLIDATE operation, DFSMSdss creates a work data set (SYS1.DFDSS.DEFRAG.xxxxxxxx.volser.DUMMY), which is deleted after successful completion of the CONSOLIDATE function. If the CONSOLIDATE operation is prematurely ended, rerun the CONSOLIDATE function to clean up this data set.

## CONVERTV

Anyone can use the CONVERTV command. However, your installation can limit usage of the CONVERTV command by use of a RACF FACILITY class profile if:

· RACF FACILITY class is active.

The FACILITY class profile STGADMIN.ADR.CONVERTV has been defined.
 Then need READ access authorization to that profile to use the CONVERTV command.

To convert a volume to SMS-managed, the user and group IDs of the owners of all the data sets on that volume must be RACF-defined, and they must not be revoked.

# **COPY**

Table 28, which shows the access authority needed to perform the copy function, is based on the following assumptions:

- The data set is a user data set.
- Both the data set and the catalog are RACF-protected.
- If the data set is going to be cataloged in the master catalog, then you need UPDATE access to that catalog.

Table 28 also applies to group data sets. To create a new group data set, you need one of the following:

- UPDATE access to the catalog when a non-SMS-managed group data set is unprotected, but the catalog is RACF-protected.
- CREATE in the group and UPDATE access to the data set.
- ALTER access to the data set and be a member of the group that owns the data set. To discretely protect a group data set, you need additional authority such as CREATE in the group.

*Table 28. Access Authority for the DFSMSdss COPY Command.* This table shows the minimum access levels required to perform a COPY command.

SC	URCE DATA S	ET	TARGET DATA SET		
	Non-SMS		Non-SMS		
With	Access Level		Preallocated	Access	s Level
DELETE	Data Set	Catalog	Target	Data Set	Catalog
NO	READ	Automatic	NO	ALTER	UPDATE
NO	READ	Automatic	YES	UPDATE	Automatic
YES	ALTER	Automatic	NO	ALTER	UPDATE
YES	ALTER	Automatic	YES	UPDATE	Automatic
	Non-SMS		SMS		
With	Access	Level	Preallocated	Access Level	
DELETE	Data Set	Catalog	Target	Data Set	Catalog
NO	READ	Automatic	NO	ALTER	Automatic
NO	READ	Automatic	YES	UPDATE	Automatic
YES	ALTER	Automatic	NO	ALTER	Automatic
YES	ALTER	Automatic	YES	UPDATE	Automatic
	SMS		Non-SMS		
With	Access	s Level	Preallocated	Access Level	
DELETE	Data Set	Catalog	Target	Data Set	Catalog
NO	READ	Automatic	NO	ALTER	UPDATE
NO	READ	Automatic	YES	UPDATE	Automatic

Table 28. Access Authority for the DFSMSdss COPY Command (continued).	This table
shows the minimum access levels required to perform a COPY command.	

SC	SOURCE DATA SET			RGET DATA S	ET
YES	ALTER	Automatic	NO	ALTER	UPDATE
YES	ALTER	Automatic	YES	UPDATE	Automatic
	SMS		SMS		
With	Access	s Level	Preallocated Access Level		Level
DELETE	Data Set	Catalog	Target	Data Set	Catalog
NO	Data Set READ	Catalog Automatic	Target NO	Data Set ALTER	Catalog Automatic
			- C		
NO	READ	Automatic	NO	ALTER	Automatic

#### Note:

- 1. "Automatic" means that you have automatic access to the user catalog if you can access the data sets.
- 2. In the course of copying data sets, DFSMSdss will rename the source data set using the conventions described under DFSMSdss Temporary Data Set Names. (See "Temporary copied data sets" on page 538 under Temporary Copied Data Sets.) Whenever DFSMSdss renames a RACF protected data set to a temporary name, a RACF profile must exist for the temporary data set name.

# COPY and deleting data sets

For SMS-managed data sets, ALTER access lets you delete the data set. For non-SMS-managed data sets, either ALTER access to the data set or ALTER access to the catalog and READ access to the data set lets you copy and delete the data set. The ability to delete and uncatalog a data set with READ access to the data set and ALTER access to the catalog lets you move a data set without having ALTER access to the data set. You only need UPDATE access to the catalog to delete an unprotected, non-SMS-managed data set.

### Copy and data set profile considerations

When you copy a RACF-indicated data set, DFSMSdss performs special target data set processing. A predefined, discrete profile is not used to check your access authority unless the data set is already RACF-indicated.

Copy and data set profiles: If a data set is protected by a generic or discrete profile when it is copied, DFSMSdss tries to ensure that the target data is also protected (see Table 29). To do so, DFSMSdss uses the RACF DEFINE function or the catalog ALTER function. You need authority to define or rename discrete profiles, even if you are acting as a DFSMSdss-authorized storage administrator.

Table 29. DFSMSdss COPY Command and RACF Profiles. This table summarizes how DFSMSdss defines discrete profiles to protect the target set.

COPY	with:	Source Data Set	RACF	Profile:
RENAME	DELETE	Protected?	Source	Target
NO	NO	NO	None	As predefined
NO	NO	GENERIC	No change	As predefined
NO	NO	DISCRETE	No change	DEFINE
NO	YES	NO	None	As predefined

Table 29. DFSMSdss COPY Command and RACF Profiles (continued). This table summarizes how DFSMSdss defines discrete profiles to protect the target set.

COPY	with:	Source Data Set	RACF	Profile:
RENAME	DELETE	Protected?	Source	Target
NO	YES	GENERIC	No change	As predefined
NO	YES	DISCRETE	DELETE	DEFINE
YES	NO	NO	None	As predefined
YES	NO	GENERIC	No change	MENTITY
YES	NO	DISCRETE	No change	DEFINE
YES	YES	NO	None	As predefined
YES	YES	GENERIC	No change	MENTITY
YES	YES	DISCRETE	DELETE	DEFINE

#### Terms defined:

None The data set remains unprotected.

#### As predefined

DFSMSdss does not ensure that the target data set is RACF-protected. If a covering data set profile is not already predefined, the data set may be unprotected.

#### No change

The data set profile that is protecting the source data set remains unchanged.

#### **DEFINE**

A discrete profile is defined by DFSMSdss.

#### **DELETE**

The data set and the discrete profile are deleted.

#### **MENTITY**

If the target data set is not RACF-protected by a generic or discrete profile and MENTITY is specified, DFSMSdss defines a discrete profile. Otherwise, no profile is defined.

**COPY and the MENTITY keyword:** By default, when DFSMSdss defines a discrete profile to protect a copied data set, it uses the discrete profile of the source data set as a model. The MENTITY keyword lets you specify a different data set profile as the model. Besides the model profile, you can also specify a volume serial (through MVOLSER). If you do so, specify the volume serial number of the volume containing the non-VSAM model entity or the volume containing the catalog in which the VSAM model entity is cataloged.

Use the MENTITY keyword of the COPY command when one of the following is true:

- The source data set is RACF-protected by a generic profile, but the target data set name is unprotected.
- The source data set is RACF-protected by a discrete profile, but you wish to use a different data set profile as the model for defining a new discrete profile.

**COPY and define discrete profile summary:** Table 30 on page 552 summarizes the circumstances during copy operation when a discrete profile is defined, when MENTITY is effective, when the target data set is RACF-indicated, and when

## **Data Security**

related messages are issued. To define discrete profiles for data sets that you do not own, you need additional authorization such as the system-OPERATIONS attribute or CREATE in the group.

Table 30. DFSMSdss Copy and Define Discrete Profile Summary. This table summarizes what happens when DFSMSdss defines discrete profiles for a copy operation.

Protection		MENTITY	Define	RACF	Warning
Source	Target	Specified?	Profile?	Indicated?	Message?
None	None	Yes	No	No	No
None	None	No	No	No	No
None	Generic	Yes	No	No	No
None	Generic	No	No	No	No
None	RACF	Yes	No	Yes	No
None	Indicated	No	No	Yes	No
Generic	None	Yes	Yes	Yes	No (W)
Generic	Generic None	No	No	No	Yes
Generic	Generic	Yes	No	No	No
Generic	Generic	No	No	No	No
Generic	RACF	Yes	No	Yes	No
Generic	Indicated	No	No	Yes	No
RACF	None	Yes	Yes	Yes	No (W)
Indicated	None	No	Yes (C)	Yes	No (E)
RACF	Generic	Yes	Yes	Yes	No (W)
Indicated	Generic	No	Yes (C)	Yes	No (E)
RACF	RACF	Yes	No	Yes	No
Indicated	Indicated	No	No	Yes	No

#### Terms defined:

- Yes (C) If there is a discrete profile for the source data set, a discrete profile is defined for the target data set.
- No (W) If the define of the discrete profile fails and the copy is successful, then the target data set is left as RACF-indicated and a warning message is issued. This is true even if DELETE is specified.
- No (E) If the define of the discrete profile fails and DELETE is specified, then the copy is unsuccessful and an error message is issued.
  - If the define of the discrete profile fails and DELETE is not specified, then the target data set is left as RACF-indicated and a warning message is issued.

Protection states after a copy or move: When a data set is copied or moved, the protection state of the target depends on the initial protection states of the source and the target data sets, whether MENTITY was specified, and whether discrete profiles are predefined. The following conditions may exist:

## The source data set is unprotected.

The target data set may or may not be protected after the copy. A discrete profile is not defined by DFSMSdss, even if you specify MENTITY.

#### The source data set is protected but not RACF-indicated.

The target data set may or may not be protected after the copy:

- If the target data set is not already protected and MENTITY is not specified, the data set remains unprotected. If you do specify MENTITY, DFSMSdss defines a discrete profile:
  - If the define is successful, the target data set is RACF-indicated. It is accessible according to the access list for the model profile that was used.
  - If the define is unsuccessful, the target data set remains RACF-indicated. It may be inaccessible until a data set profile is successfully defined.
- If the target data set is already protected because it is RACF-indicated or RACF-protected, DFSMSdss does not define a discrete profile (even if you specify MENTITY). The target data set is accessible according to the access list of a predefined, protecting, data set profile.

## The source data set is RACF-indicated.

The target data set is RACF-indicated after the copy:

- If the target data set is not RACF-indicated and if either there is a discrete profile for the source or MENTITY is specified, DFSMSdss defines a discrete profile:
  - If the define is successful, the data set is RACF-indicated. It is accessible according to the access list for the model profile that was used.
  - If the define is unsuccessful and MENTITY was specified or DELETE was not specified, the data set is RACF-indicated. It may be inaccessible until a data set profile is successfully defined.
  - If the define is unsuccessful and DELETE was specified (without MENTITY), the copy or move is unsuccessful. The target data set is deleted, and the source data set is kept.
- If the target data set is already RACF-indicated, a discrete profile is not defined by DFSMSdss (even if you specify MENTITY or DELETE). The target data set remains RACF-indicated.

## Other COPY command considerations

To copy or move a data set that is discretely protected, you need authority to define discrete profiles because the move operation temporarily renames the data set and the discrete profile.

## **COPYDUMP**

The access authority you need to the input and output dump data sets depends on many factors not under DFSMSdss control because access-authorization checking is performed by Open/Close/End-of-Volume (O/C/EOV) processing. The primary considerations are as follows:

- You need READ access if the input dump data set is protected.
- You need either UPDATE or ALTER access if the output dump data set is protected.
- You may need UPDATE access to the catalog if the output data set is going to be cataloged.

## **DEFRAG**

To use the DEFRAG command to relocate data extents on a DASD volume, you need DASDVOL-access authority to that volume or READ-access to the data sets that are relocated. Otherwise, only unprotected data sets are relocated.

As part of the DEFRAG operation, DFSMSdss creates a work data set (SYS1.DFDSS.DEFRAG.xxxxxxxx.volser.DUMMY), which is deleted after successful completion of the DEFRAG function. If the DEFRAG operation is prematurely ended, rerun the DEFRAG function to clean up this data set.

## **DUMP**

The access authority you need to the output dump data set depends on many factors not controlled by DFSMSdss because access-authorization checking is done by O/C/EOV. The primary considerations are as follows:

- You need access to a protected dump data set with:
  - ALTER access to create it.
  - UPDATE access if it is already allocated.
  - CREATE authority in the group and UPDATE access if it is a group data set.
- · You may need UPDATE access to a catalog if the dump data set is going to be cataloged.
- You may have sufficient authority to the dump data set if you have the system-OPERATIONS attribute.
- You also need access authority to the data sets that are going to be dumped as shown in Table 31.

Table 31 is for the following conditions:

- Both the data set and the catalog are RACF-protected.
- You have the indicated level of access authority to the data set.
- The data set is cataloged in a user catalog.

Table 31. Access Authority for the DFSMSdss DUMP Command. This table shows the minimum access levels required to perform a DUMP command.

SMS-Managed Data	With DELETE?	Access	ccess Level:	
Set?		Source Data Set	Catalog	
NO	NO	READ	Automatic	
NO	YES	ALTER	UPDATE	
YES	NO	READ	Automatic	
YES	YES	ALTER	Automatic	

Note: "Automatic" means that you have automatic access to the catalog if you can access the data set.

## **Dumping and deleting data sets**

For SMS-managed data sets, ALTER access to the data set lets you delete a data set. If the data set is cataloged in the master catalog, you also need UPDATE access to the catalog.

For non-SMS-managed data sets, you need one of the following to dump and delete a data set:

- ALTER access to a protected data set.
- READ access to a protected data set and ALTER access to a protected catalog.
- UPDATE access to a protected catalog if the data set is unprotected.
- DASDVOL-access authority to the volume containing the data set.
- Authority to specify DELETE as a DFSMSdss-authorized storage administrator.

## **PRINT**

To use the PRINT command, you need either DASDVOL-access authority at the READ level or READ access to the data sets.

## RELEASE

To use the RELEASE command, you need either DASDVOL-access authority at the UPDATE level or UPDATE access to the data sets.

### RESTORE

The access authority you need to restore a data set from an input dump data set depends on many factors not controlled by DFSMSdss because access-authorization checking to the input dump data set is performed by O/C/EOV processing. The primary considerations are as follows:

- You need at least READ access to the dump data set if the dump data set is protected.
- You may need READ access to the catalog if the dump data set is cataloged.
- You may have sufficient authority to the dump data set if you have the system-OPERATIONS attribute.
- You also need access authority to the source and target data sets and their catalogs as shown in Table 32.

#### Restore and access authorization

When a data set is either restored or both restored and renamed, DFSMSdss tries to verify that you have READ access to a DASD data set with the same name as the data set that was dumped. This is done to ensure that an unauthorized person is not allowed to restore and rename one of your data sets. For example, the restore described below would be unsuccessful:

- Data set USER1.PERSONAL.PAYHIST is RACF-protected so that USER2 cannot read it.
- Data set USER1.PERSONAL.PAYHIST is dumped.
- USER2 tries to restore USER1.PERSONAL.PAYHIST as USER2.TEST.DATA.

When you restore a data set, your authority to read that data set is checked using the current data set profiles rather than the data set profiles that were defined when the data set was dumped:

- If a discrete profile is predefined for the source data set name, it is used regardless of the current state of the data set.
- Otherwise, if a generic profile is defined, it is used.
- If neither a discrete nor a generic profile is defined, you are given access. However, for VSAM data sets that are already cataloged and RACF-indicated, access is denied in this situation.
- For VSAM data sets, if the catalog no longer exists or the data set is no longer cataloged, only generic-profile checking is performed.

*Table 32. Access Authority for the DFSMSdss RESTORE Command.* This table shows the minimum access-levels required to perform a RESTORE command.

SOURCE DATA SET			TARGET DATA SET		
Non-SMS			Non-SMS		
RENAME or	Access Level Data Set Catalog		Preallocated	Access	s Level
RENAMEU			Target	Data Set	Catalog

Table 32. Access Authority for the DFSMSdss RESTORE Command (continued). This table shows the minimum access-levels required to perform a RESTORE command.

SOURCE DATA SET			TA	RGET DATA S	ET	
NO	No check	No check	NO	ALTER	UPDATE	
NO	No check	No check	YES	UPDATE	Automatic	
YES	READ	Automatic	NO	ALTER	UPDATE	
YES	READ	Automatic	YES	UPDATE	Automatic	
	Non-SMS			SMS		
RENAME or	Access	s Level	Preallocated	Access	Level	
RENAMEU	Data Set	Catalog	Target	Data Set	Catalog	
NO	No check	No check	NO	ALTER	Automatic	
NO	No check	No check	YES	UPDATE	Automatic	
YES	READ	Automatic	NO	ALTER	Automatic	
YES	READ	Automatic	YES	UPDATE	Automatic	
	SMS		Non-SMS			
RENAME or	Access Level		Preallocated	Access Level		
INDIVIDE OF			] I leallocated			
RENAMEU	Data Set	Catalog	Target	Data Set	Catalog	
				Data Set ALTER	Catalog UPDATE	
RENAMEU	Data Set	Catalog	Target			
RENAMEU NO	Data Set No check	Catalog No check	Target NO	ALTER	UPDATE	
NO NO	Data Set  No check  No check	Catalog  No check  No check	NO YES	ALTER UPDATE	UPDATE Automatic	
NO NO YES	Data Set  No check  No check  READ	Catalog No check No check Automatic	NO YES NO	ALTER UPDATE ALTER	UPDATE Automatic UPDATE	
NO NO YES	Data Set No check No check READ READ SMS	Catalog No check No check Automatic	NO YES NO	ALTER UPDATE ALTER UPDATE SMS	UPDATE Automatic UPDATE	
NO NO YES YES	Data Set No check No check READ READ SMS	Catalog No check No check Automatic Automatic	NO YES NO YES	ALTER UPDATE ALTER UPDATE SMS	UPDATE Automatic UPDATE Automatic	
NO NO YES YES  RENAME or	Data Set  No check  No check  READ  READ  SMS  Access	Catalog No check No check Automatic Automatic	NO YES NO YES Preallocated	ALTER UPDATE ALTER UPDATE SMS Access	UPDATE Automatic UPDATE Automatic	
NO NO YES YES RENAME or RENAMEU	Data Set  No check  No check  READ  READ  SMS  Access  Data Set	Catalog No check No check Automatic Automatic  Level Catalog	NO YES NO YES Preallocated Target	ALTER UPDATE ALTER UPDATE SMS Access Data Set	UPDATE Automatic UPDATE Automatic  Level Catalog	
NO NO YES YES  RENAME or RENAMEU NO	Data Set  No check  No check  READ  READ  SMS  Access  Data Set  No Check	Catalog No check No check Automatic Automatic S Level Catalog No check	NO YES NO YES Preallocated Target NO	ALTER UPDATE ALTER UPDATE SMS Access Data Set ALTER	UPDATE Automatic UPDATE Automatic  Level Catalog Automatic	

### Note:

- 1. "No check" means that no check is made.
- 2. "Automatic" means that you have automatic access to the catalog if you can access the data sets.

Table 32 on page 555 is based on the following assumptions:

- The data set is a user data set.
- Both the data set and the catalog are RACF-protected.
- · You have the indicated access authority to the source and target data sets.
- If an SMS-managed data set is going to be cataloged in the master catalog, you have UPDATE access to that catalog.

Table 32 on page 555 also applies to group data sets. To create a group data set by restoring it, you need one of the following:

- UPDATE access to the catalog for unprotected, non-SMS, group data sets. For unprotected, SMS-managed data sets, you automatically have access to the user catalog.
- CREATE authority in the GROUP and UPDATE access to the data set.
- ALTER access to the data set and be a member of the group that owns the data set. To discretely protect a group data set, you need additional authority such as CREATE in the group.

# Restore and data set profile considerations

If the data set being restored was RACF-indicated when it was dumped, DFSMSdss does special target data set processing.

**Restore and the MENTITY keyword:** You can restore a data set and use the MENTITY keyword to request that DFSMSdss is to define a data set profile when one of the following is true:

- The data set to be restored was RACF-protected by a generic profile when it was dumped, and the target data set name is unprotected.
- The data set to be restored was RACF-indicated when it was dumped, and the target data set name is either unprotected or it is only protected by a generic profile.

DFSMSdss uses the data set profile specified by the MENTITY keyword, and any volume serial specified with MVOLSER, as a model to define a discrete profile to protect the target data set. If MVOLSER is not specified, the volume serial is one of the following:

- The volume on which a non-VSAM data set resides.
- The volume that contains the catalog for a VSAM data set.

To define discrete profiles for data sets that you do not own, you need additional authorization such as the system-OPERATIONS attribute or CREATE in the group.

**Restore and physical data sets:** DFSMSdss provides limited support for defining discrete profiles during physical restore of a data set:

- For VSAM data sets, a discrete profile is never defined.
- For non-VSAM data sets, a discrete profile is only defined if MENTITY is specified and the data set was RACF-indicated when it was dumped.

**Restore and define discrete profile summary:** Table 33 summarizes the circumstances during a restore when MENTITY is effective, when a discrete profile is defined, when the target data set is RACF-indicated, and when related messages are issued.

*Table 33. DFSMSdss Copy and Define Profile Summary.* This table summarizes when DFSMSdss defines discrete profiles for a copy operation.

Protection		MENTITY	Define	RACF	Warning
Source	Target	Specified?	Profile?	Indicated?	Message?
None	None	Yes	No	No	No
None	None	No	No	No	No
Nama	Canania	Yes	No	No	No
None	Generic	No	No	No	No
Nama	RACF	Yes	No	Yes	No
None	Indicated	No	No	Yes	No

Table 33. DFSMSdss Copy and Define Profile Summary (continued). This table summarizes when DFSMSdss defines discrete profiles for a copy operation.

Prote	ection	MENTITY	Define	RACF	Warning
Source	Target	Specified?	Profile?	Indicated?	Message?
Generic	None	Yes	Yes	Yes	No (W)
Generic	None	No	No	No	Yes
Generic	Generic	Yes	No	No	No
Generic	Generic	No	No	No	No
Generic	RACF	Yes	No	Yes	No
Generic	Indicated	No	No	Yes	No
RACF	Nama	Yes	Yes	Yes	No (W)
Indicated	None	No	No	Yes	Yes
RACF	Generic	Yes	Yes	Yes	No (W)
Indicated	Generic	No	No	Yes	Yes
RACF	RACF	Yes	No	Yes	No
Indicated	Indicated	No	No	Yes	No

**Note:** "No (W)" means that if the define of the discrete profile fails, the restore is successful, but the target data set remains RACF-indicated. A warning message is issued.

**Protection states after a restore:** When a data set is restored, the protection state of the target depends on the initial protection states of the source and the target data sets, whether MENTITY is specified, and whether discrete profiles are predefined. The following conditions may exist:

#### The data set was unprotected when it was dumped.

The target data set may or may not be protected after the restore. Even if you specify MENTITY, a discrete profile is not defined.

### The data set was generically protected when it was dumped.

The target data set name may or may not be protected after the restore:

- If the target data set is not already protected and MENTITY is not specified, the data set remains unprotected. If MENTITY is specified, a discrete profile is defined:
  - If the define is successful, the data set is RACF-indicated. It is accessible according to the access list for the model profile that was used.
  - If the define is unsuccessful, the data set remains RACF-indicated. It may be inaccessible until a data set profile is successfully defined.
- If the target data set is already protected, a discrete profile is not defined (even if you specify MENTITY). The target data set is accessible according to the access list of a predefined, protecting, data set profile.

#### The source data set was RACF-indicated when it was dumped.

The target data set is RACF-indicated after the data set is restored:

- If the target data set is not already RACF-indicated and if MENTITY is not specified, a discrete profile is not defined. If MENTITY is specified, DFSMSdss defines a discrete profile:
  - If the define is successful, the data set is accessible according to the access list for the model profile that was used.

- If the define is unsuccessful, the data set may be inaccessible until a data set profile is successfully defined.
- If the target data set is already RACF-indicated, a discrete profile is not defined by DFSMSdss (even if you specify MENTITY). The target data set remains RACF-indicated.
- DFSMSdss gives you the ability to change its default operation. Through
  the ADRPATCH Serviceability Aid, DFSMSdss logical restore can be
  instructed not to turn on the RACF indicator for the target data set when
  the source data set was RACF-indicated at dump time. The MENTITY
  keyword is not specified and the target data set is protected by a generic
  profile.

**Related reading:** For more information about changing the DFSMSdss default operation, see Chapter 14, "DFSMSdss patch area," on page 217.

## RESTORE command and the IMPORT keyword

By default, anyone can use the IMPORT keyword of the RESTORE command to bypass access checking of source data sets. You still need access authorization to create or update the target data sets and catalogs. Your installation may limit use of the IMPORT keyword as previously discussed in "Protecting the usage of DFSMSdss" on page 533.

# Chapter 21. Data integrity—serialization

DFSMSdss uses **volume serialization** and **data set serialization** functions to ensure that data sets are not modified during the processing of DFSMSdss commands. Volume serialization is accomplished by using the RESERVE macro. Data set serialization is accomplished by using the ENQ macro and the DFSMSdss DYNALLOC function. In the case of shared DASD, volume serialization ensures that data sets are not being added, deleted, renamed, or extended from either the same processor or other processors.

You can control volume serialization with the enqueue installation exit routine. This allows other programs to access volumes while DFSMSdss is running. Volume serialization, however, cannot be overridden.

DFSMSdss supports data sets that are always open, or open for long periods of time, with **backup-while-open serialization**.

DFSMSdss supports backup-while-open processing for DFSMStvs and for two types of database applications: Customer Information Control System (CICS) and information management system (IMS).

CICS support includes both RLS CICS and non-RLS CICS backup-while-open.

DFSMStvs supports backup-while-open with or without CICS, as "Backup-while-open data sets (CICS and DFSMStvs)" on page 571 describes.

DFSMSdss also supports backup-while-open serialization for IMS data sets for:

- Indexed VSAM data sets, such as KSDS
- Non-indexed VSAM data sets, such as ESDS
- Non-VSAM data sets, such as OSAM

### Related reading: For more information about

- Enqueue installation exit routine, see *z/OS DFSMS Installation Exits*.
- RLS CICS and non-RLS CICS backup-while-open support, see "Backup-while-open data sets (CICS and DFSMStvs)" on page 571.
- IMS backup-while-open support, see "Backup-while-open data sets (IMS)" on page 575.
- DFSMStvs, see z/OS DFSMStvs Planning and Operating Guide and z/OS DFSMStvs Administration Guide.

## Volume serialization

For volume serialization, DFSMSdss issues the RESERVE macro against the volume to prevent direct access device storage management (DADSM) functions (such as addition, deletion, extension, or renaming of data sets) from changing the VTOC entries during DFSMSdss processing. The RESERVE is issued before processing is begun on a particular volume, and released when processing is completed, during the following operations:

- DUMP (except logical)
- CONSOLIDATE
- COPY (except logical)
- RESTORE (except logical and physical data set)

## **Data Integrity—Serialization**

- PRINT (except data set)
- DEFRAG

**Note:** Be aware that volume serialization (RESERVE performed against the volume) does not ensure integrity at the data set level. For example, in the case of a physical full volume dump, data sets are not serialized and the data sets could change while the DUMP is being taken.

Note that you can use the DFSMSdss enqueue installation exit to request that DFSMSdss only reserve the VTOC for the duration of VTOC access during the following operations:

- Full, tracks, and physical data set DUMP
- · Full and tracks COPY
- Tracks PRINT

In addition, DFSMSdss issues the RESERVE macro against a volume while updating information in the VTOC, such as the RACF-defined flag and the data-set-changed flag. DFSMSdss also issues the RESERVE macro against a volume while accessing the information in the VTOC to perform data set selection during the following operations:

- Logical DUMP with input volumes specified
- · Logical COPY with input volumes specified
- CONVERTV
- COMPRESS
- RELEASE

Related reading: For more information about the enqueue installation exit routine, see z/OS DFSMS Installation Exits.

# Avoiding lockout

The VTOC is locked to prevent activity on the VTOC at the volume level during the copy, defrag, dump, print (tracks) or restore (tracks and full) functions. These functions may require access to the catalogs for the data sets on the volume. A lockout can result between DFSMSdss and another job on the same system that has already locked the catalog but needs the VTOC for a DADSM function. To avoid this lockout, you should not run any jobs (for example, Access Method Services jobs) that require control of both the catalog and the VTOC while DFSMSdss is executing.

The remainder of this section provides intended programming interfaces.

When an application program attaches a DFSMSdss dump or restore task and a task that invokes dynamic allocation to allocate a data set (for example, logical restore operation) or invokes DADSM to scratch a data set, the two tasks could lock each other out. To avoid this lockout, DFSMSdss uses the following ENQ scheme:

- Before DFSMSdss invokes DADSM SCRATCH, an exclusive ENQ is requested for the resource with a major name of ADRLOCK and a minor name of the volume serial number (padded with blanks to 8 bytes).
- Before DFSMSdss invokes dynamic allocation to allocate a new data set on a specific volume, a shared ENQ is requested for the resource with a major name of ADRLOCK and a minor name of the volume serial number (padded with blanks 8 bytes). If this is a nonspecific dynamic allocation request, an exclusive ENQ with the resource with a major name of ADRLOCK and a minor name of NONSPEC is requested.

- If an application program invokes a DFSMSdss FULL dump operation and plans
  on attaching another DFSMSdss logical restore task, the application should
  request the first resource in exclusive mode (ADRLOCK, volser). The application
  should request the second resource in shared mode (ADRLOCK, NONSPEC)
  before attaching the FULL DUMP command task. Multiple dumps can be active
  in the same address space, and a logical restore request will not lock out that
  task.
  - If an application program issues a DADSM request, the application must enqueue on ADRLOCK/volser in a shared ENQ or ADRLOCK/NONSPEC in an exclusive ENQ.

#### Note:

- When DFSMSdss is invoked with JCL, lockout does not occur because DFSMSdss allocates a volume before invoking DADSM. If a FULL DUMP command has the volume enqueued and a restore task has been applied against the same volume, the restore task is held until the volume is available.
- 2. Only non-SMS, non-VSAM DADSM requests require serialization.

# The WAIT option

DFSMSdss lets you change the WAIT/RETRY values for system resources.

**Related reading:** For more information about WAIT/RETRY, see "Controlling the wait/retry time for serialization of system resources (PN11523)" on page 219.

## Data set serialization

This section describes the ENQUEUE and SERIALIZATION options for data set serialization, the WAIT option, and provides an example of RESERVE-ENQUEUE processing.

# **Enqueuing—ENQ**

The following material describes enqueue options for data set serialization. Enqueues are done on the data set name for the data set copy, data set dump, data set restore, defragment, print, compress, and release operations to prevent multiple, simultaneous updates to the same data set.

The SHARE option has unique properties when applied to the following commands:

- For the RESTORE command, SHARE applies to non-VSAM data sets only.
- For the DUMP and COPY commands, SHARE applies to non-VSAM data sets and VSAM data sets that are defined with share options other than (1,3) and (1,4).

If you do not specify the SHARE option, DFSMSdss tries to provide the highest level of data integrity by defaulting to exclusive enqueuing. The command is in a wait state for *X* seconds if the enqueue fails. WAIT specifies *X* (numsecs, numretries), and retries the enqueue. If the wait-enqueue sequence fails after *Y* retries (where WAIT specifies *Y* (numsecs, numretries)), data set processing ends.

In the case of a multistep job where the initiator holds a shared enqueue on the data set, DFSMSdss upgrades the enqueue to exclusive unless SHARE is specified. The initiator holds the exclusive enqueue until the last step in the job that references the data set has completed.

## **Data Integrity—Serialization**

If you specify the SHARE keyword, DFSMSdss tries an enqueue for share. If it fails, it goes through the same logic as if SHARE had not been specified. If the retries all fail, processing ends for the data set.

You can specify TOLERATE(ENQFAILURE) in addition to the default, ENQ, or the SHARE option. If TOLERATE(ENQFAILURE) is specified, DFSMSdss attempts to get the specified level of enqueue, exclusive or share. If the enqueue fails after the specified or default number of retries, DFSMSdss processes the data set without an enqueue. Specify TOLERATE(ENQFAILURE) if you are willing to tolerate the exposure of not having data integrity in order to force the successful completion of that particular data set operation. This is particularly useful when an installation has duplicate data sets (different data sets with the same name but on different volumes) and you want to run DFSMSdss on a data set on one volume while the data set with the same name is being used by the system or another job on a different volume.

Note: Because of ENQ contention, SYSPRINT data sets should not be allocated on volumes being processed. TOLERATE(ENQFAILURE) cannot apply to data movements that involve the use of utilities.

Table 34 shows the data set enqueue options.

TOLERATE(ENOFAILURE) can be used on VSAM and non-VSAM data sets.

Table 34. Data Set Enqueue Options for Non-VSAM Data Sets Specified on DFSMSdss Commands

Options	None	SHARE	TOLERATE(ENQFAILURE)	SHARE and TOLERATE(ENQFAILURE)
Type of enqueue attempted	Exclusive	Share	Exclusive	Share
If enqueue is successful	Process	Process	Process	Process
If enqueue is not successful	Do not process	Do not process	Process without enqueue	Process without enqueue

# **Dumping HFS data sets**

The serialization mechanism operates differently depending on whether you are performing a logical dump or a physical dump. Whether or not you mount the data set before you dump it affects serialization also.

## Logical dump

The serialization mechanism used during a logical dump of a mounted HFS data sets consists primarily of the SYSZDSN enqueue macro and the BPX1QSE quiesce macro. A shared SYSZDSN enqueue provides serialization if a data set that you want to dump is not mounted for update. To mount an HFS data set for update, z/OS UNIX System Services (z/OS UNIX) must obtain an exclusive enqueue on the SYSZDSN. The shared enqueue on the SYSZDSN prevents z/OS UNIX from mounting the data set for update during the dump.

If you mount an HFS data set for update before you dump it, DFSMSdss issues the BPX1QSE macro to prevent updates to the data set for the duration of the dump. For non-shared file systems, you must run the DFSMSdss dump job on the same system where the data set is mounted for update. For shared file systems, you can run the DFSMSdss dump job from any system in the sysplex.

DFSMSdss can honor the DELETE keyword for an HFS data set during logical dump only if the data set is unmounted. For delete processing, the data set must be enqueued exclusively.

## Physical dump

DFSMSdss relies on a SYSDSN enqueue for physical dump operations. By default, DFSMSdss attempts an exclusive SYSDSN enqueue during physical dump. As long as the data set is not mounted at dump time, the exclusive enqueue on the SYSDSN provides sufficient serialization. If the data set is mounted before the physical dump job begins, z/OS UNIX will have a shared enqueue on the SYSDSN. DFSMSdss will therefore not be able to obtain an exclusive SYSDSN enqueue.

Avoid performing a physical dump of mounted HFS data sets because quiesce is not available during a physical dump. If you specify either the SHARE or TOL(ENQF) keyword during a physical dump, the internal control information and data inside the HFS can change during the dump. This can result in a dumped data set that contains an HFS data set that might not be usable after you have restored it. If you must physically dump a data set that is in use, use TOL(ENQF) instead of SHARE. With TOL(ENQF), you receive a return code of four, along with a warning message, if serialization was not adequate during the dump.

**Guideline:** Exercise caution when you use TOL(ENQF) during a physical dump of HFS data sets. Unlike other types of data sets, if an HFS is updated during a physical dump with TOL(ENQF), a subsequent restore can likely result in an unusable data set.

## zFS data sets

The serialization mechanism operates differently depending on whether you are performing a physical operation or a logical operation. Serialization is also affected if the data set is mounted.

#### Logical dump

The serialization mechanism used during a logical dump of zFS data sets consists primarily of the SYSDSN enqueue macro, SYSVSAM enqueue macros and the zFS quiesce macro. A shared SYSDSN enqueue and SYSVSAM enqueues provide serialization if a data set that you want to dump is not mounted

If a zFS data set is mounted before you dump it, the data set can still be quiesced. The quiesce action prevents updates to the data set for the duration of the dump.

## Physical dump

DFSMSdss relies on a SYSDSN and SYSVSAM enqueues for physical dump operations. By default, DFSMSdss attempts exclusive enqueues during physical dump. As long as the data set is not mounted at dump time, the exclusive enqueues provide sufficient serialization. If the data set is mounted before the physical dump job begins, z/OS UNIX will have the zFS data set allocated and opened. Allocation and open processing will have obtained SYSDSN and SYSVSAM enqueues. DFSMSdss will therefore not be able to obtain the exclusive enqueues.

Physical dump of mounted zFS data sets is not recommended because quiesce is not available during a physical dump. If you specify the TOL(ENQF) keyword during a physical dump, the internal control information and data inside the zFS can change during the dump. This can result in a dumped data set that contains a zFS data set that might not be usable after you have restored it.

## Physical data set copy

Physical data set copy operations require DFSMSdss to obtain the SYSDSN and VSAM enqueues for the source data set. In order to allow this type of serialization the zFS will need to be unmounted from all systems.

Physical data set copy of mounted zFS data sets is not recommended because quiesce is not available during a physical copy. If you specify the TOL(ENQF) keyword during a physical data set copy, the internal control information and data inside the zFS can change during the copy. This can result in a data set copy that is unusable.

# Dynamic allocation (DYNALLOC)

DYNALLOC is an option for the data set DUMP, data set COPY, data set RESTORE, data set PRINT, DEFRAG, COMPRESS, and RELEASE commands. It allows serialization of data sets across processors with shared DASD, with JES3, and with the interface between dynamic allocation and JES3 enabled. Dynamic allocation is used by DYNALLOC to serialize data sets. Processing time increases because overhead is involved in dynamic allocation and serialization across multiple processors.

If you use DYNALLOC to serialize data sets (as opposed to ENQ) the job run time increases. If you use INDYNAM instead of DD statements to allocate DASD volumes you do not appreciably increase run time and coding of JCL, and command input is easier.

DFSMSdss does not honor DYNALLOC for HFS source data sets for either logical data set copy or logical data set dump.

# Enqueuing versus dynamic allocation of data sets

For data set operations, the default method of serializing usage of data sets is to enqueue on the data set name. If the DYNALLOC keyword is coded in the control cards, the time taken to serialize is much greater than that taken by using the ENQ macro. So use DYNALLOC keyword judiciously. Use it only on a JES3 system if the interface between the allocation function and JES3 is not disabled. If the interface is disabled, then the end result of serialization using ENQ is the same as using dynamic allocation; ENQ takes much less time to serialize data sets.

When you use DYNALLOC keyword, the selected data sets are allocated to DFSMSdss. If some data sets are allocated to the system, they can only be processed by DFSMSdss with DYNALLOC if SHARE is also specified. Table 36 on page 568 provides more information on data set serialization.

# Read/Write serialization scheme

Table 35 shows the serialization scheme used by all operations, except COPYDUMP, for read/write access.

Table 35. Read/Write Access Serialization Scheme

			ENQ Control, Exclusive (E) or	
	Major Name	Minor Name	Share (S)	ENQ Scope
For Source HFS Data Sets:	•			

Table 35. Read/Write Access Serialization Scheme (continued)

	EN	IQ Names	ENQ Control, Exclusive (E) or	
	Major Name	Minor Name	Share (S)	ENQ Scope
followed by:	ADRDSN SYSZDSN	Data set name  Data set name	E (see Note 1) S (see Note 1) E (see Note 2) S (see Note 2)	STEP SYSTEMS
For zFS Data Sets:			<i>b</i> (see 1188 <b>2</b> )	
On the component during logical data set DUMP or COPY operations:	SYSVSAM	See Note 3	E (see Note 5) S (see Note 5)	SYSTEMS
On the component during physical data set DUMP operations:	SYSVSAM	See Note 3	E (see Note 1) S (see Note 1)	SYSTEMS
On the component during other operations:	SYSVSAM	See Note 3	Е	SYSTEMS
On the cluster during logical DUMP or COPY operations: followed by:	ADRDSN	Cluster name	E (see Note 1) S (see Note 1) E (see Note 5) S (see Note 5)	STEP
	SYSDSN	Cluster name	(-50 - 1000 0)	SYSTEM
On the cluster during other operations:	ADRDSN	Cluster name	E (see Note 1) S (see Note 1) E (see Note 1)	STEP
followed by:	SYSDSN	Cluster name	S (see Note 1)	SYSTEM
For Non-VSAM Data Sets:				
followed by:	ADRDSN SYSDSN	Data set name  Data set name	E (see Note 1) S (see Note 1) E (see Note 1) S (see Note 1)	STEP SYSTEM
For GDG Data Sets:			•	1
On the GDG base:	ADRDSN	GDG base name	E (see Note 1)	STEP
followed by:	SYSDSN	GDG base name	S (see Note 1) E (see Note 1) S (see Note 1)	SYSTEM
On each GDG data set:	ADRDSN	Data set name	E (see Note 1) S (see Note 1)	STEP
followed by:	SYSDSN	Data set name	E (see Note 1) S (see Note 1)	SYSTEM
For VSAM Data Sets:	1	1	1	
On each component during data set DUMP or COPY operations:	SYSVSAM	See Note 3	E (see Note 1) S (see Note 1)	SYSTEMS
On each component during other operations:	SYSVSAM	See Note 3	Е	SYSTEMS
On the cluster:	ADRDSN	Cluster name	E (see Note 1)	STEP
followed by:	SYSDSN	Cluster name	S (see Note 1) E (see Note 1) S (see Note 1)	SYSTEM
For Integrated Catalog Facilit	y Catalogs:	I		
In addition to the above VSAM data set information:	SYSIGGV2	Catalog name	E	SYSTEMS

## **Data Integrity—Serialization**

Table 35. Read/Write Access Serialization Scheme (continued)

	ENQ Names		ENQ Control, Exclusive (E) or	
	Major Name	Minor Name	Share (S)	ENQ Scope
On the volume:	SYSVTOC	Volume serial number	Е	SYSTEMS
For VVDS Data Sets:				
On each data set: Input access: Output access:	SYSZVVDS	SYS1.VVDS.Vvolser	S E	SYSTEMS

#### Note:

- If the selected control for the ENQs is EXCLUSIVE or SHARE, the SHARE keyword determines the type of control. If SHARE is *not* specified, exclusive control of the data set is obtained. Whereas, if SHARE is specified, shared control of the data set is obtained.
  - If shared control is obtained for a VSAM data set because the SHARE keyword was specified, other programs are able to obtain read access, but not write access, to the data set, while it is being processed. The SHARE keyword is honored for VSAM data sets only during DUMP and COPY processing, and only for VSAM data sets that are defined with SHARE options other than (1,3) or (1,4).
- 2. For a source HFS data set, DFSMSdss ignores DYNALLOC. If you specify DELETE, then DFSMSdss attempts to get an exclusive SYSZDSN enqueue. If you do not specify DELETE, then DFSMSdss attempts to get a shared SYSZDSN enqueue.
- 3. If DYNALLOC is used:
  - For a source HFS data set, DFSMSdss ignores DYNALLOC.
  - For non-VSAM data sets and GDG bases, instead of ENQ, the data set is dynamically allocated automatically, with a disposition of OLD if SHARE is not used; otherwise, SHARE is the disposition.
  - For VSAM data sets, in addition to the ENQ on the components, the cluster is allocated dynamically just as for non-VSAM data sets.
- 4. The minor name used for enqueuing VSAM components consists of the following: component name, catalog name, L1, L2, L3, A (where L1 is the total length of the minor name, L2 is the component name length, and L3 is the catalog name length).
  - On a data set DUMP, data set RESTORE, data set COPY, and DEFRAG operation, an enqueue is performed once with the character A=I and iteratively with A=O.
- 5. If you specify DELETE, then DFSMSdss attempts to get exclusive control of the zFS. If you do not specify DELETE, then DFSMSdss attempts to get a shared control of the zFS.

**Programming Interface information:** Although the ENQ on the major name ADRDSN is mostly intended to coordinate access to data sets between multiple DFSMSdss commands, it might be necessary for application programs that invoke DFSMSdss to make use of the ENQ; data sets that are serialized by the application program using dynamic allocation or an ENQ on the major name SYSDSN could be processed by DFSMSdss unless the application uses the ENQ on ADRDSN.

Table 36. Resource Serialization

Function	Data Set Type	Volume Serializ VTOC		Data Set Level Serialization (ENQ or DYNALLOC)
COMPRESS	Non-VSAM	Yes	N/A	DSName
CONSOLIDATE	Non-VSAM VSAM	Yes Yes	N/A Yes	DSName Component and Cluster Names
CONVERTV	Non-VSAM	Yes	N/A	DSName

Table 36. Resource Serialization (continued)

Function	Data Set Type	Volum Seriali VTOC		Data Set Level Serialization (ENQ or DYNALLOC)
Data Set COPY	Non-VSAM	Yes	N/A	DSName
	VSAM	Yes	Yes	Component and Cluster Names
DEFRAG	Non-VSAM	Yes	N/A	DSName
	VSAM	Yes	Yes	Component and Cluster Names
Full DUMP	Non-VSAM	Yes	N/A	N/A
	VSAM	Yes	Yes	N/A
Data Set DUMP	Non-VSAM	Yes	N/A	DSName
	VSAM	Yes	Yes	Component and Cluster Names
Data Set PRINT	Non-VSAM	Yes	N/A	DSName
	VSAM	Yes	Yes	Component Name
Tracks PRINT	N/A	Yes	N/A	N/A
RELEASE	Non-VSAM	Yes	N/A	DSName
	VSAM	Yes	Yes	Component and Cluster Names
Full RESTORE	Non-VSAM	Yes	N/A	N/A
	VSAM	Yes	Yes	N/A
Data Set RESTORE	Non-VSAM	N/A	N/A	DSName
	VSAM	N/A	Yes	Component and Cluster Names

#### Notes

- Refer to "Backup-while-open data sets (CICS and DFSMStvs)" on page 571 for more information on resource serialization.
- VSAM data sets must be cataloged in an integrated catalog facility catalog.
- N/A means not applicable.

# **WAIT** option

This option allows you to specify how long, in seconds, DFSMSdss is to wait for a resource and the number of times DFSMSdss is to retry, should an ENQ or RESERVE fail. The default is WAIT(2,2).

This means DFSMSdss is to retry twice at 2-second intervals. The WAIT keyword does not apply to system resources such as the VTOC and the VVDS.

For a data set copy or logical data set dump operation, the WAIT option has a different meaning for serializing data sets when multiple data sets are to be processed and WAIT(0,0) is not specified. Multiple passes are made through the list of data sets that are selected. On each pass, those data sets that can be serialized without waiting for the resource and that were not processed before are processed. At the end of a pass, if none of the data sets could be processed without waiting for a resource, then, in the next pass, at the first occurrence of a data set that was not processed a WAIT is issued.

That data set and the remainder of the list is processed if possible. The above procedure is repeated until all data sets are processed or the WAIT limits are reached.

## **Data Integrity—Serialization**

For example, if WAIT(3,10) is specified and 5 data sets are left to be processed, up to 10 passes are made. On each pass, the first unprocessed data set is waited upon for 3 seconds. Thus, only a 30-second maximum is ever waited, not 150 (5 times 3 times 10).

For system resources, such as the VTOC and the VVDS data set, the default is WAIT(3,30). This means DFSMSdss is to retry 30 times at 3 second intervals, resulting in a total wait time of 90 seconds.

# An example of RESERVE-ENQUEUE processing

If you were to enter the following:

```
DUMP INDD(IN1) OUTDD(OUT1) -
DATASET(INCLUDE(MY.DUMP.DATASET1, MY.DUMP.DATASET2)) -
WAIT(5,2) -
SHARE
```

The following would result:

- 1. DFSMSdss issues a RESERVE command on SYSVTOC (this is the default)
  - If the reserve operation fails, DFSMSdss retries thirty times at 3-second intervals, assuming that the installation has not changed the default for system resources.
  - If the RESERVE command is successful, DFSMSdss continues.

If either of the data set was a VSAM or SMS-managed data set, the VVDS would also be serialized by DFSMSdss. If VVDS serialization fails, none of the data sets are dumped.

- 2. DFSMSdss issues a shared enqueue on data set name. If the shared enqueue fails, DFSMSdss retries two times at 5-second intervals.
  - If the shared enqueue is successful:
    - DFSMSdss adds the data set name to the list to be dumped.
    - DFSMSdss loops back to the beginning of this step until an enqueue is tried for all data sets.
  - If the shared enqueue fails, DFSMSdss:
    - Issues a message indicating that the data set failed serialization, and does not process the data set.
    - Loops back to the beginning of this step until an enqueue is tried for all data sets.
- 3. After an enqueue is tried for all specified data sets and at least one was successful, DFSMSdss:
  - Dumps the VVDS (if an integrated catalog facility data set was selected) and the VTOC and dequeues the VTOC.
  - Dequeues VVDS if it was enqueued.
  - Dumps each data set that was successfully enqueued.
  - Dequeues the enqueued data sets.
  - Issues message indicating which data sets were successfully processed.

Note: If you specify TOLERATE(ENQFAILURE) option with the DUMP command and the installation options exit routine does not override it, the VTOC is not dequeued until all the data tracks for all the data sets are dumped.

# Backup-while-open data sets (CICS and DFSMStvs)

DFSMSdss supports backup-while-open serialization, which can perform backup of data sets that are open for update for long periods of time. It can also perform a logical data set dump of these data sets even if another application has them serialized. Backup-while-open is a better method than using SHARE or TOLERATE(ENQFAILURE) for dumping Customer Information Control System (CICS) VSAM file-control data sets that are in-use and open for update. When you dump data sets that are designated by CICS as eligible for backup-while-open processing, data integrity is maintained through serialization interactions between CICS (data base control program), CICSVR (forward-recovery program), VSAM record management, DFSMSdfp, and DFSMSdss. When you dump data sets that are designated by DFSMStvs as eligible for backup-while-open processing, data integrity is maintained through serialization interactions between DFSMStvs, VSAM record management, DFSMSdfp, and DFSMSdss.

Although the BWO(TYPECICS) parameter applies to both CICS and DFSMStvs, DFSMStvs enables you to back up a data sets while they are open whether or not you are running CICS.

Figure 23 shows the backup-while-open serialization for dumping CICS data sets that are open for update. Backup-while-open processing also ensures that any update activity that may invalidate the dump is detected. Simultaneous recovery or deletion of the data set while it is being dumped is also prevented.




Figure 23. Block Diagram for Backup-While-Open Serialization

In Figure 23, a VSAM file-control data set (7) is allocated for CICS (1) through MVS allocation services (3) using JCL or dynamic allocation methods. This results in serialization through an enqueue on the name of the data set and the resource name SYSDSN (4). When the VSAM data set is opened (3), another level of serialization occurs through an enqueue on the names of the components of the

## Data Integrity—Serialization

VSAM data set and the resource name SYSVSAM (4). For eligible data sets, CICS uses DFSMSdfp (5) to set a status in the backup-while-open indicators (6) in the catalog entry for the data set.

For a dump operation, DFSMSdss (8) attempts to acquire the SYSDSN, SYSVSAM, and backup-while-open (9) enqueues for the data set. When the enqueue on the cluster name of the data set and resource name of BWODSN is acquired, but not the enqueues for both SYSDSN and SYSVSAM, DFSMSdss uses DFSMSdfp to get the backup-while-open indicators, and starts to dump the open data set if it is backup-while-open eligible.

The backup-while-open enqueue is used to prevent more than one DFSMSdss operation, such as a simultaneous dump and restore (10), and to prevent the data set from being deleted while it is being dumped by DFSMSdss.

While the data set is being dumped, a data base application program may update the data set in a manner that invalidates the data set. For example, a control-interval or control-area split may occur. When this happens, VSAM record management uses DFSMSdfp to change the backup-while-open status. When the backup of the open data set is completed, DFSMSdss obtains the current backup-while-open indicators and invalidates the dump of the data set if the indicators are different from when the dump was started. When concurrent copy is used, updates made while the data set is being dumped do not cause the dump to be invalidated.

# Backup-while-open status definition

DFSMSdss interprets backup-while-open status numbers as follows:

#### Status Meaning to DFSMSdss

- 000 Normal serialization and processing techniques are used to dump the data
- 001 CICSVR forward-recovers the data set.
- 010 A control-interval split, control-area split, or extend of the data set was either interrupted before the dump started or is currently in process.
- 011 A control-interval split, control-area split, or an extend of the data set completed successfully. CICS or DFSMStvs closed the data set and there is no mismatch between the base cluster and any alternate index.
- 100 The data set may be dumped while it is open for update.
- 101 The data set was restored and is down-level; CICSVR or DFSMStvs must process it before a database application uses it.
- 110 The data set was updated and a split or extend is completed, which invalidates any dump that was in progress. When concurrent copy is used, the chances of an in-progress-dump being invalidated by a split or extend is significantly reduced.
- 111 The data set is in an indeterminate state.

# Backup-while-open processing

DFSMSdss actions resulting from dumping a data set are based on the following conditions:

 Success or failure to acquire an exclusive enqueue for the resource names of SYSDSN, SYSVSAM, and BWODSN.

- Backup-while-open status before the dump.
- Backup-while-open status indicators after the dump.

When DFSMSdss acquires all of the exclusive enqueues: The data set is not open for update, even though it has a non-zero backup-while-open status. The particular processing action is a direct result of the initial backup-while-open status as follows:

- Status is 000; the data set is dumped. When it is restored, the backup-while-open status is restored as 000.
- Status is 001. The data set is dumped and the backup-while-open status is preserved and restored when the data set is subsequently restored. This data set is in an indeterminate state because of an incomplete forward recovery by CICSVR, which cannot forward-recover the restored data set.
  - DFSMSdss lets you dump and restore this data set for nonstandard recovery purposes. After restoring the data set and correcting all errors in the data set, reset the BWO status to 000 by using CICS-provided methods. The preferred action is for you to restore an earlier dump of the data set and use CICSVR to do forward-recovery processing. This maintains the integrity of the data.
- Status is 010. DFSMSdss did not dump the data set. Take corrective action before using the data set by performing the following actions:
  - Determine if alternate indexes (AIX) are present for the sphere. If they are, do either of the following tasks:
    - Rebuild the AIXs from the base cluster, and reset the BWO status to 000 by using the CICS' methods.
    - Restore an earlier dump of the sphere, and use CICSVR to do forward-recovery processing.
  - If there are no AIXs, the data set is usable, as it is. Reset the BWO status to 000 by using the CICS methods.
- Status is 101. The data set is dumped and the backup-while-open status is preserved and restored when the data set is subsequently restored. This lets you process the data set with CICSVR before a data base application uses it.
- Status is 011, 100, 110, 111. The backup-while-open status is altered to 000 before the data set is dumped. When it is restored, the backup-while-open status is restored as 000.

When DFSMSdss acquires an exclusive enqueue on BWODSN (but not SYSDSN and SYSVSAM): Another program is using the data set or the data set is open. The particular processing action is a direct result of the initial backup-while-open status as follows:

- Status is 000. The data set is not eligible for backup-while-open. The data set is not dumped unless SHARE or TOLERATE(ENQFAILURE) is specified and the necessary conditions for those keywords are met.
- Status is 001, 010, 011, 101, or 111; the data set is not dumped.
- Status is 110; the backup-while-open status is altered to 100 and the data set is dumped.
- Status is 100. The data set is dumped, even though it is already in use (including being open for update by another program). When the data set is restored, the backup-while-open status is set to 101. This ensures that CICSVR or DFSMStvs can process the data set, prior to its use by a data base application. The dump is invalidated if the backup-while-open indicators change while the data set is being dumped. The chances of this invalidation occurring reduce significantly when you use concurrent copy.

# Backup-while-open and concurrent copy

Concurrent copy improves backup-while-open processing by significantly reducing the chances of the invalidation of a backup-while-open dump because of updates to the data set. To use concurrent copy, specify the CONCURRENT keyword when you dump backup-while-open data sets. The following is a comparison of the various kinds of dumps you can ask for:

- Normal dump. Use of the data set must be quiesced. DFSMSdss obtains serialization, dumps the data set, and then releases the serialization. The data set cannot be used for the entire time.
- Concurrent copy dump. Use of the data set must be quiesced. DFSMSdss obtains serialization, performs concurrent copy initialization, releases serialization, and then dumps the data set. DFSMSdss completes concurrent copy initialization within a very short time (compared to the actual time to dump the data set). DFSMSdss can use the data set as soon as the concurrent copy initialization is complete.
- **Backup-while-open dump.** Use of the data set does not need to be quiesced. DFSMSdss dumps the data set without obtaining serialization. The data set can remain in use for the entire time, but update activity can invalidate the dump at any time during the dump.
- Backup-while-open dump using concurrent copy. Use of the data set does not need to be quiesced. DFSMSdss does not obtain serialization. DFSMSdss performs the concurrent copy initialization. DFSMSdss completes concurrent copy initialization within a very short time (compared to the actual time to dump the data set). The data set can remain in use for the entire time. Like the Backup-while-open dump, update activity during the dump can invalidate the dump. However, only update activity that occurs before DFSMSdss performs the concurrent copy initialization can invalidate the dump. The chances of the update activity invalidating the dump are significantly reduced because the concurrent copy initialization completes very quickly.

# TOLERATE (ENQFAILURE) and SHARE considerations

Using TOLERATE(ENQFAILURE) modifies the processing and serialization for backup-while-open data sets. The data sets are dumped when the backup-while-open status is 100, even though none of the enqueues are successfully acquired.

To maintain data integrity and data security, do not specify either SHARE or TOLERATE(ENQFAILURE) when you dump backup-while-open data sets.

An exclusive enqueue on BWODSN resource name for the data set is required for DFSMSdss to alter the backup-while-open status. DFSMSdss only attempts an exclusive enqueue on the BWODSN resource name. Unless the backup-while-open status is already 100, the dump fails even though you specified SHARE or TOLERATE(ENQFAILURE).

# CICS recovery data

CICS maintains recovery data in the form of a date and time-stamp in the catalog entry for backup-while-open data sets. This information is not used or processed by DFSMSdss, but it is dumped and restored to preserve that information for CICSVR. The recovery data is also printed in selected messages to assist you in your recovery efforts.

DFSMStvs maintains recovery data in forward recovery log records. DFSMSdss does not use or process this recovery data. The data is dumped and restored to preserve the information for CICSVR or possibly for another forward recovery utility. The recovery data is also printed in selected messages to assist you in your recovery efforts.

# Backup-while-open data sets (IMS)

DFSMSdss supports backup-while-open processing of IMS data sets by providing for fast replication copies and concurrent copy dumps. IMS requests backup through the application programming interface of DFSMSdss, described in Chapter 22, "Application programming interface," on page 577.

Backup-while-open serialization is applicable to HISAM, SHISAM, and index (primary and secondary) databases.

Backup as an open data set for IMS is triggered through a UIM request, rather than through a backup-while-open status or BWO(TYPEIMS) definition as CICS does.

Specifics of IMS backup-while-open support are outlined in Table 37.

**Note:** During a logical data set dump, you must specify VALIDATE (directly or by default) to ensure that an IMS backup-while-open data set that is dumped while updates are being made can be successfully restored. VALIDATE allows DFSMSdss to validate and correct the data set during the dump process, or to end the dump (with an ADR943E message) if the data set is in an unrecoverable state.

DFSMSdss issues an ADR943E message during logical data set dump if the NOVALIDATE parameter is used with an indexed VSAM data set defined as BWO(TYPEIMS).

Table 37. DFSMSdss Support for IMS Backup-While-Open Data Sets

Topic:	For IMS data sets:
Can non-VSAM data sets be copied or dumped as open data sets?	Yes
Can non-indexed VSAM data sets be copied or dumped as open data sets?	Yes
Must indexed VSAM data sets be specifically designated as being BWO-eligible to be copied or dumped as open data sets?	No
How are indexed VSAM data sets designated as being eligible for update activity detection through a BWO counter?	By defining the data set as BWO(TYPEIMS)
How is backup as an open data set triggered?	Through a UIM request
How is bypassing of enqueues on SYSDSN and SYSVSAM managed?	Automatically

## **Data Integrity—Serialization**

Attention: The user must be aware that COPY with DELETE, DUMP with DELETE, and RESTORE with REPLACE can cause irreparable damage to an IMS data set for the following reasons:

- The enqueue serialization obtained by COPY and DUMP are insufficient to ensure that the data set is not also being used by an IMS application in an environment where GRS (or equivalent) is not being used.
- COPY and DUMP do not provide any special handling for any data set defined as BWO(TYPEIMS).
- RESTORE does not provide any protection against reallocating or overwriting any IMS data set for which RESTORE is able to obtain an enqueue serialization on SYSDSN and SYSVSAM.

# Chapter 22. Application programming interface

This topic provides information that you may need when you use the user interaction modules. General-use programming interface and associated guidance information is contained in this topic. Programming interface information is also included and is explicitly marked.

# Calling block structure

The parameter structure outlined below is shown in block form in Figure 24 on page 580.

#### **ADRDSSU**

The name of the DFSMSdss module main entry point.

## **OPTPTR**

The pointer to the option list and similar to OPTIONADDR described in z/OS DFSMSdfp Utilities. This parameter lets you specify processing options and must be specified even if the list is a null list. If you do not want to specify any parameters to DFSMSdss, this pointer must point to a halfword of binary zeros.

You can invoke DFSMSdss using the standard application interface. This API allows you to specify in the options list those values that you can specify in the EXEC PARM field when you invoke DFSMSdss using JCL. You can also invoke DFSMSdss using the cross memory application interface. The values that you can specify in the options list include those values that can be specified in the EXEC PARM field when invoking DFSMSdss with JCL. Additionally, you can specify values that are specific to the cross memory application interface. For a list of the values that can be specified in the EXEC PARM field when invoking DFSMSdss with JCL, see "How to control DFSMSdss through PARM information in the EXEC statement" on page 254. For a list of the values that are specific to the cross memory application interface, see "Using the cross memory application interface to control DFSMSdss" on page 583.

The first field, called the *option-list length field*, is a halfword field specifying the length of the list (excluding the field itself) as a binary value. If you do not want to specify any options, set the option-list length field to binary zeros. In your JCL for the calling program, if you code parameters (PARM=value) on the EXEC statement, DFSMSdss does not recognize them unless OPTPTR points to them.

The options must comply with the parameter syntax of the DFSMSdss EXEC parameter values. If you do not want to specify subsequent parameters, you can omit them from the list.

#### **DDPTR**

The pointer to the DDNAME list and similar to DDNAMEADDR described in *z/OS DFSMSdfp Utilities*. The DDNAME list provides a way to specify alternate names for the SYSIN and SYSPRINT data sets. The DDNAME list is a variable length field made up of a halfword field followed by unseparated 8-character, left-justified (right padded with blanks) fields. Each 8-character field is reserved for a specific DDNAME. DFSMSdss uses only two of these fields: SYSIN and SYSPRINT. The other fields are

provided as a standard implementation consistent with existing system utility invocation procedures, must be filled with binary zeros, and are ignored by DFSMSdss.

The first field, called the DDNAME-list length field, is a halfword field specifying the length of the list (excluding the field itself) as a binary value for the number 48.

If you do not want to specify an alternate DDNAME for the SYSIN or SYSPRINT data sets, set the DDNAME-list length field to the correct length and set all of the 8-character fields to binary zeros.

If you want to specify an alternate DDNAME for the SYSIN data set, specify this parameter and enter the alternate DDNAME in the fifth 8-character field. Otherwise, enter all binary zeros in the field.

If you want to specify an alternate DDNAME for the SYSPRINT data set, specify this parameter and enter the alternate DDNAME in the sixth 8-character field. Otherwise, enter all binary zeros in the field.

If you do not want to specify subsequent parameters, you can omit them from the list.

#### **PAGEPTR**

The pointer to the page-number list and similar to HDINGADDR described in z/OS DFSMSdfp Utilities. This list provides a way to specify the starting page number for system output on the SYSPRINT data set. The page-number list is a fixed-length 6-byte field made up of a halfword field followed by a 4-byte EBCDIC page count, which specifies the starting page number for DFSMSdss to use for the SYSPRINT data set. If a value is specified both here and in the OPTPTR list, this value is used, and the OPTPTR value is ignored.

The first field, called the page-number-list length field, is a halfword field specifying the length of the list (excluding the field itself) as a binary value. The length is usually 4.

If you do not want to specify a starting page number, set the page-number-list length field to binary zeros. If you want to specify a starting page number, you must specify this parameter and a 4-character page value. If the page number is specified (page-number-list length field is not binary zeros), DFSMSdss resets this field to the current page number upon completion of the present invocation. If the page number is not specified, this field is not changed by DFSMSdss.

If you do not want to specify subsequent parameters, you can omit them from the list.

#### **UIMPTR**

The pointer to the user interaction module (UIM) list. There is no comparable parameter described in *z/OS DFSMSdfp Utilities*. This parameter provides a way to specify the name or address of a vector-implemented exit module that is to interact with DFSMSdss for the various I/O and data set operations. The UIM list is of variable length and consists of a halfword field followed by a 4-byte address or 8-character left-justified (padded on the right with blanks) string field that specifies the address of the UIM entry point or the load module name (located through the normal LINKLIB structure) of the UIM. If you do not want to specify a UIM, do not specify this parameter.

The first field, called the *UIM-list length field*, is a halfword field specifying the length of the list (excluding the field itself) as a binary value. If you do not want to specify an option, set the option-list length field to binary zeros. If the address of the UIM is being passed, it specifies the length as 4, or as 8 if the name of the UIM is being passed.

If you want to specify a UIM, you must specify the name or address of the UIM in the field following the UIM-list length field. See "System programming information" on page 584 for more details on the use of this module.

#### **UAPTR**

The pointer to the user-area list. There is no comparable parameter in *z/OS DFSMSdfp Utilities*. This parameter provides a way to specify the address of an area to be passed to the UIM at each DFSMSdss exit point. The user-area list is of fixed length, consisting of a halfword field called the *user-area-list length field*, and a single 4-byte address that locates the user area starting address.

If you use the user area, the length must be set to 4 and the address of the user area must be specified in a second field.

#### **ASIDPTR**

The pointer to the address-space-identifier list. There is no comparable parameter described in *z/OS DFSMSdfp Utilities*. This optional parameter, which is applicable only when you use ADRXMAIA instead of ADRDSSU, lets you specify an identifier for the address space that ADRXMAIA uses for the DFSMSdss program. The address-space-identifier list is of fixed length, consisting of a halfword field and a single 8-byte character field. The default value, if not set by the application program, is "DFSMSDSS." This value is set to "DSSBATCH" when JCL is used to invoke ADRXMAIA, but can be specified through the ASPACE=*name* PARM field.

ADRXMAIA automatically creates the address space as needed. The identified address space can also be created by the operator START command by specifying an appropriately named PROCLIB member name.

#### **PARAM**

On the ATTACH and LINK macros, the keyword with which you specify the names of the pointers that are passed to DFSMSdss

VL Indicates that the list is variable length. Both the ATTACH and LINK macros require specifying VL=1.




Figure 24. DFSMSdss Application Interface Structure

## **User interactions**

For user interactions to take place, the application must invoke DFSMSdss and must provide a pointer to a user interaction module (UIM) list. DFSMSdss can be invoked by any of the following system macros:

```
ATTACH EP=ADRDSSU,PARAM=(OPTPTR,DDPTR,PAGEPTR,UIMPTR,UAPTR),VL=1
LINK EP=ADRDSSU,PARAM=(OPTPTR,DDPTR,PAGEPTR,UIMPTR,UAPTR),VL=1
CALL (15),(OPTPTR,DDPTR,PAGEPTR,UIMPTR,UAPTR),VL
```

Optionally, to use the DFSMSdss Cross Memory Application Interface, use one of the following system macros:

```
ATTACH EP=ADRXMAIA, PARAM=(OPTPTR, DDPTR, PAGEPTR, UIMPTR, UAPTR), VL=1
LINK EP=ADRXMAIA, PARAM=(OPTPTR, DDPTR, PAGEPTR, UIMPTR, UAPTR), VL=1
CALL (15), (OPTPTR, DDPTR, PAGEPTR, UIMPTR, UAPTR), VL
```

Optionally, to use the DFSMSdss Cross Memory Application Interface and specify an 8-character Address Space name, use one of the following system macros:

```
ATTACH EP=ADRXMAIA, PARAM=(OPTPTR, DDPTR, PAGEPTR, UIMPTR, UAPTR, ASNPTR), VL=1
LINK EP=ADRXMAIA, PARAM=(OPTPTR, DDPTR, PAGEPTR, UIMPTR, UAPTR, ASNPTR), VL=1
CALL (15), (OPTPTR, DDPTR, PAGEPTR, UIMPTR, UAPTR, ASNPTR), VL
```

As shown in Figure 24 on page 580, a pointer to the UIM exit is passed in the parameter list (UIMPTR). User interactions involve:

- · Record management
- · Controlling processing of data sets
- Gathering statistics on DFSMSdss operations

When a UIM exit routine is specified, DFSMSdss processes normally, then at each point in the process (DFSMSdss exit points), the UIM exit routine is called conditionally to allow some types of user operations.

If a DFSMSdss subtask abnormally ends for any reason, it cannot make any further calls to the UIM, including the *function ending* call.

#### Note:

- 1. DFSMSdss runs as an authorized problem program.
- 2. Any program invoking DFSMSdss must also be authorized and in a nonsupervisor state.
- 3. ADRXMAIA is the name of the DFSMSdss Cross-Memory Application Interface module main entry point. Use ADRXMAIA instead of ADRDSSU when DFSMSdss functions are to be executed in a specific address space.
- 4. ADRXMAIA runs as an authorized program and supports both supervisor-state callers and problem-state callers.

# Service considerations

After applying maintenance to any of the DFSMSdss load modules, you cannot update the version of DFSMSdss that is resident in your address space with LLA REFRESH. Instead, you must restart your application, or cause the ADRDSSU or ADRXMAIA load modules to be reloaded. Additionally, if your application uses DFSMSdss Cross Memory services, you must cause the DFSMSdss Cross Memory server address space to shut down in order for the updated ADRDSSU and other load modules to be reloaded.

The server address space will not shut down as long as the original address space that invoked the DFSMSdss Cross Memory services has not been stopped. Once the original address space has been stopped, you should shut down the DFSMSdss Cross Memory server. The server may not shut down if the SRVRTIME parameter with a value of 00:00 was specified to the DFSMSdss Cross Memory client.

The name of the Cross Memory server can be specified with the ASPACE parameter on DFSMSdss Cross Memory services invocations. You should inform users of your application what name was specified. To identify DFSMSdss Cross Memory server address spaces, you can use the SDSF DA (Display Active) panel. Look for address spaces that are executing the ADRXMAIB load module. For information on using SDSF, see SDSF's online help (press PF1).

**Related reading:** For additional information about the various UIM exits, see Chapter 23, "Examples of the application program with the user interaction module (UIM)," on page 625.

# **Cross-memory Application Interface overview**

The DFSMSdss Cross Memory Application Interface is based on a client/server model. IBM products that make use of the DFSMSdss Cross Memory Application Interface include IMS Image Copy (IC2) and DFSMShsm. DFSMSdss also provides a JCL interface for this support.

DFSMSdss Cross Memory support is designed to be invoked using the LINK, CALL, or ATTACH macros. The support may also be invoked with JCL or through system invocations. To use the JCL interface, modify the JCL that is normally used for DFSMSdss batch mode processing to execute program ADRXMAIA instead of program ADRDSSU, for example:

```
//S1 EXEC PGM=ADRXMAIA, PARM='TYPRUN=NORUN'
                in place of
//S1 EXEC PGM=ADRDSSU, PARM='TYPRUN=NORUN'
```

The DFSMSdss Cross Memory Application Interface support provides the capability for client applications to connect to and interact with a separate DFSMSdss server address space using a user-provided Interaction Module (UIM). DFSMSdss processing that is performed on behalf of a connected client application is controlled by one or more jobstep tasks that are executing in the server address space. The DFSMSdss server address space may be created by issuing a START command or may result from the ASCRE macro that is issued by the Cross Memory Application Interface support that is invoked by the client application.

After a DFSMSdss server address space begins execution, module ADRXMAIB is given control by the system, and directs server processing. The server processing that is performed on behalf of a client is referred to as a work thread, and it executes under a unique jobstep task. The jobstep task invokes the ADRDSSU program for each work thread request that the client application makes. A server can concurrently process multiple client work threads for multiple client-connected address spaces. Each work thread is a separate instance of an ADRDSSU jobstep task. Multiple server address spaces may exist and be concurrently processing on behalf of multiple client address spaces.

A client application invokes module ADRXMAIA to utilize the DFSMSdss Cross Memory Application Interface support. When a client application invokes ADRXMAIA, DFSMSdss attempts a connection to the client-identified server address space. If the client-identified DFSMSdss server address space does not exist, the Cross Memory Application Interface invokes the ASCRE macro to create the server. If the client does not provide a server address space identifier, "DFSMSDSS" is used as the default server address space identifier. The JCL interface uses "DSSBATCH" as the default identifier unless the ASPACE parameter supplies it.

You can also create a DFSMSdss server address space using a START command that specifies an appropriately named member in SYS1.PROCLIB. The procedure must invoke module ADRXMAIB. The proclib member name should match the server identifier that is used by client applications or match batch jobs that use the JCL interface that will be connecting to the server that is created.

A DFSMSdss server address space that was created using the ASCRE macro goes into termination mode if there is no more work to do after all connected client applications terminate. There is a delay period prior to a server termination. Any connection request during this delay period causes the server to revert to processing mode to process the work threads that are associated with the connecting clients.

DFSMSdss server address spaces remain active as long as a client remains active unless the operator MODIFY command informs the server that it should stop processing after all current work threads are completed, for example F DFSMSDSS.DSSBATCH, STOP or F DSSBATCH, STOP.

A DFSMSdss server that is started with a START command does not enter termination mode when all work is completed. You must use the MODIFY command to stop it.

# Using the cross memory application interface to control DFSMSdss

You can control DFSMSdss through PARM Information in the EXEC Statement by using the Cross Memory Application Interface. The EXEC statement for DFSMSdss, when invoking DFSMSdss with the Cross Memory Application Interface, can contain PARM information that is used by the client and server, as well as the ADRDSSU program itself. The same values that can be specified in the EXEC PARM field in the JCL for ADRDSSU can also be specified in the EXEC PARM field for ADRXMAIA.

### SRVRTIME=([minutes]{:seconds})

The SRVRTIME parameter specifies the amount of time the server address space should wait to shut down after the last piece of work has finished. If the Cross Memory Application Interface is invoked again, specifying this particular server before the specified time has passed, this server will take the piece of work. When the time expires and no more pieces of work have been submitted, the server will shut down, and a subsequent invocation of the Cross Memory Application Interface specifying this server name will cause a new server to be created. The first invocation of the Cross Memory Application Interface for a particular server determines the length of time while that particular server is running. Subsequent invocations to the same server while it is running will not change the time even if the SRVRTIME parm is specified on those later invocations.

#### minutes

Specifies the maximum number of minutes the server will wait after the last piece of work is finished before shutting down. The minutes must be a number from 0 through 357912 (248.55 days).

#### seconds

Specifies the maximum number of seconds the server will wait after the last piece of work is finished before shutting down. The seconds must be a number from 0 through 59.

The following examples demonstrate the affect on the system when you designate a SRVRTIME value:

- SRVRTIME=(1:30) The server will wait for 1 minute 30 seconds before shutting down.
- SRVRTIME=(24:00) The server will wait for 24 minutes before shutting down.
- SRVRTIME=(0:25) or SRVRTIME=(:25) The server will wait for 25 seconds before shutting down.
- SRVRTIME=(0:00) The server will shut down immediately after the last piece of work is finished.

**Restrictions:** If the SRVRTIME parameter is not specified, the time before the server shuts down is determined as follows:

- If the Cross Memory Application Interface is invoked from JCL, but the ASPACE parameter is not specified, the server will shut down after 4 minutes.
- If the Cross Memory Application Interface is invoked with JCL and the ASPACE parameter is specified, the server will wait 1 minute.

- If the Cross Memory Application Interface is invoked using the LINK, CALL, or ATTACH macros, but an ASPACE name wasn't provided in the ASIDPTR field, the server will wait 8 minutes.
- If the Cross Memory Application Interface is invoked using the LINK, CALL, or ATTACH macros and an ASPACE name was provided in the ASIDPTR field, the server will wait 1 minute.

#### ASPACE=id

Where id is determined by the installation to identify which server to use for processing DFSMSdss SYSIN command streams. ASPACE=AFFINITY is a special use. It causes ADRDSSU to be used within the client address space instead of running in a separate address space.

**NOTE:** ASPACE is only available when using JCL to invoke DFSMSdss with the cross memory application interface.

The following example demonstrates how you might designate the use of the ASPACE parameter:

//S1 EXEC PGM=ADRXMAIA, PARM='ASPACE=BACKUP'

#### SNAPX=\*|nn|(nn,nn[,nn])

The SNAPX parameter can be used to debug your user interaction module. The SNAPX parameter can be specified on JCL and system invocations of the Cross Memory Application Interface (API). Specifying the SNAPX parameter requests that ADRXMAIA write the contents of the EIDB and EIRECPTR to SYSPRINT whenever the specified exit is called. When an application writes its own messages to SYSPRINT, ADRXMAIA calls exit 2 of the user interaction module for that application.

When specifying the SNAPX parameter, you can specify:

- One exit to snap. For example, you can specify SNAPX=12 to see the contents of exit 12.
- More than one exit to snap. For example, you can specify SNAPX=(1,6,2) to see the contents of exits 1,2, and 6.
- All command processing exits. For example, you can specify SNAPX=\*.

The following example demonstrates how you might designate the use of the SNAPX parameter:

//S1 EXEC PGM=ADRXMAIA, PARM='SNAPX=(21,22,23)'

# System programming information

Some bit definitions in the installation options control block (ADRUFO) permit DFSMSdss to communicate with the installation options exit routine. When the installation options exit does not want a function to be scheduled, it returns a code of 8. For the UIM to do this requires a bit definition of UFSTOP to be set in the ADRUFO. If a SYSIN or SYSPRINT data set is not to be allocated or all SYSIN/SYSPRINT is to be handled in storage, UFSYSIN and UFSYSPR specify this to DFSMSdss.

If the application allows DFSMSdss to handle SYSPRINT by not setting UFSYSPR, then the application can not write to SYSPRINT directly. The application can only insert SYSPRINT records at UIM exit points 2 or 10. If the application chooses to handle SYSPRINT by setting UFSYSPR, then the application is responsible for printing DFSMSdss messages from UIM exit points 2 or 10.

Three additional bits determine allowances within the UIM interaction: UFAIINV, UFUIMAL and UFUIMCH. Two additional bits indicate the existence or absence of an input restore/copydump data set or an output dump/copydump data set: UFNOIN and UFNOOUT respectively. Refer to *z/OS DFSMS Installation Exits* for more information about the installation options exit routine.

When DFSMSdss has been invoked by using the Application Interface and the UIM has been specified and is to be called, the following information is passed to the UIM on every exit call:

- Register 1, which points to the interface parameter list pointer.
- The interface parameter list pointer, which points to the DFSMSdss exit identification block. See "ADREID0 data area" on page 607 for a detailed description of this block. This list consists of:
  - A halfword field specifying the length of the remainder of the list.
  - The remainder of the list that is mapped by the macro ADREID0. See "Exit identification block" below for the information contained in this block.

Upon return from the UIM, the user return code field is examined to determine the disposition of the current I/O record or data set (within the limits allowed to the exit).

# **Application interface blocks**

The parameter structure described in Figure 24 on page 580 can be viewed in block form as shown in Figure 25.



Figure 25. DFSMSdss Exit Interface Structure

### Exit identification block

The exit identification block is passed to the user interaction module every time DFSMSdss gives control to it. Each field is described below, but see "ADREID0 data area" on page 607 for the formal declarations.

#### Control Block Eye-Catcher

A 4-character string field that is supplied by DFSMSdss. It contains the character string *EIDB* and can aid in locating the control block when you are viewing a storage dump during DEBUG processing.

#### **TASK-ID**

A fullword binary field that is supplied by DFSMSdss. The number contained in this field is assigned by DFSMSdss to each function command statement submitted in SYSIN, whether obtained from the data set or from the UIM. This number is binary zero when DFSMSdss is calling the UIM for a function that is not related to a user command statement. Each command is numbered in sequence. When a task is scheduled to process this command, all messages associated with this task and all calls to the user interaction module for this task are accompanied by this unique number. In this way, the UIM can identify which task is being processed and what function is associated with that task.

#### User Exit Allowance

A fullword binary field supplied by DFSMSdss. The 32 bits defined in this

field can be used as flags to determine what actions the UIM can perform with respect to the record presented. The following actions are conditionally allowed:

- View and conditionally override the installation options.
- Insert data prior to current record.
- Replace the current data record with an exit-record supplied.
- Delete the current data record.
- · Modify the current data record.
- Disconnect the exit from further interaction.
- Recognize when a disallowed option has been attempted.
- End processing of the data set.
- End processing of the task.

## **DFSMSdss Processing Option**

A halfword binary field that is supplied by DFSMSdss. The number contained in this field can be used by the user interaction module (UIM) to vector branch to the appropriate processing routine for the record or data set being presented to the exit.

At appropriate locations in the DFSMSdss processing modules, the user interaction module is considered for receiving control. These locations are referred to as DFSMSdss exit points.

#### User Return Code

A halfword binary field that is supplied by the UIM. This return code identifies the action expected by the exit on the record or data set being presented to the exit. DFSMSdss examines this field when control returns from the UIM. Not all the following return codes are allowed at any given exit call. If a disallowed code is returned from the UIM, DFSMSdss passes the EIDB back to the UIM with the EIXERR flag set. This allows the UIM one chance to correct the option. If a disallowed code is returned again, it is ignored by DFSMSdss and the record is processed as though the exit had returned the code zero (0). If a valid code is returned, DFSMSdss processing is the same as if the valid code had been passed back on the initial UIM invocation. This sequence is followed for any subsequent incorrect return codes. The return codes that are allowed at any given exit call are specified in the EIXALLOW field.

- The meaning of each return code for those exits presenting records to the UIM (Eioptions 01 to 26) is:
  - 0 The record is processed as would normally have happened if there had not been a UIM. The original record is not changed in any way by the exit.
  - 4 The record was replaced by the exit. The new record must be placed in the area pointed to by the original record pointer field and its length stored in the original record length field.
  - 8 The record is to be inserted. The address of the new record must be stored in the original record pointer field or the new record must be stored in the area pointed to by the original record pointer field and its length must be stored in the original record length field. When this exit is next called, the original record is presented again.
  - 12 The record is to be deleted. The record presented to the UIM is ignored in the processing, thus deleting it.
  - 16 The record was modified by the exit. This return code is the only one allowing the original record to be altered and then to be

processed by DFSMSdss. Any changes made to the record must be logically correct because DFSMSdss cannot assure the validity of these changes.

#### Note:

- 1. You cannot change the record length when you modify the record (as contrasted with reason code 4).
- 2. If the record being processed is the installation options record (ADRUFO) and any values have been changed, return code 16 must be returned or the changes are ignored.
- The record is to be processed as though a return code zero (0) had been given, but this particular DFSMSdss exit point is no longer called from the current functional task, although it might be called from others. You must be cautious in using this code because multiple record types use the same DFSMSdss exit point. It would be better for the UIM to inspect each record type and only give a return code zero (0) when a record is not of interest to the exit.
- The record is to be processed but at all future visits of DFSMSdss at this exit point, only user statistical records are to be presented to the UIM.
- The notification-of-response return code. The WTOR has been handled by the UIM and the UIM has supplied the proper response from the WTOR in the area pointed to by the original record pointer. The interface allows you to handle all WTOR processing in the UIM exit routine and to supply the required response to DFSMSdss in lieu of DFSMSdss's issuing the WTOR itself. Note that the UIM must set the original record length to the proper value.
- 32 DFSMSdss ends the current functional task and issues message ADR356E.
- The meaning of each return code for those exits controlling data set processing (Eioptions 21, 22, 23, and 26) is:
  - The data set is processed as would normally have happened if there had not been a UIM. Data set processing is not altered in any way.
  - This return code is valid from exit 22 only. It indicates to DFSMSdss to examine the bypass processing flags and to modify processing of the data set according to which flags are on. These bypass flags are only examined by DFSMSdss if a return code of 16 is returned. See "Bypass verification exit (Eioption 22)" on page 597 for more details about these flags.
  - The record is to be processed as though a return code zero (0) had been given, but this particular DFSMSdss exit point is no longer called from the current functional task, although it might be called from others. You must be cautious in using this code because multiple record types use the same DFSMSdss exit point. It would be better for the UIM to inspect each record type and only give a return code zero (0) when a record is not of interest to the exit.

- 32 DFSMSdss ends the current functional task and issues message ADR356E.
- DFSMSdss ends processing of the data set named in the 36 parameter passed to the exit. Processing continues with the next data set (if any). If Exit 23 sets this return code after the data set has already been processed, then DFSMSdss does not undo the processing, but deletes the data set from the successfully-processed message list (if applicable) and includes it in the unsuccessfully-processed message list even though the data set may have been successfully processed up to that point

#### Record Area Length

A fullword binary field that is supplied by DFSMSdss. The number contained in this field represents the total length of the area in which the original record is stored. The number can be used by the UIM to verify that replacement and inserted records fit in the provided buffer area pointed to by the original record pointer field.

#### Original Record Length

A fullword binary field that is supplied by DFSMSdss but can be changed by the UIM. The number contained in this field represents the total length of the record pointed to by the original record pointer. The length includes just the length of the record pointed to by the original record pointer field and does not include the length of this field itself. The value of this field is zero when the UIM is called to supply in-storage SYSIN data.

#### Original Record Pointer

A fullword address field that is supplied by DFSMSdss but can be changed by the UIM. This field contains the address of the record being passed to the UIM on this call. This address normally is not changed by the exit unless an insertion is being used. Refer to the proper return code descriptions for the effect on this field. The value of this field is zero when the UIM is called to supply in-storage SYSIN data. The location of the original record, above or below the 16-megabyte (MB) virtual storage line, is controlled by using the installation options exit. If this record is to be above 16MB, the UIM has to run in 31-bit addressing mode in order to address the record.

#### User Area Pointer

A fullword address field that is supplied by the application program and is maintained by DFSMSdss. This field contains the address of the user data/work area that was supplied by the application program as a communications area for UIM internal process controls. DFSMSdss saves this pointer and supplies it in the EIUSEPTR field of the exit identification block on each call to the UIM. If any UIM exit changes the user area pointer, DFSMSdss presents the updated pointer on subsequent calls to the

Each DFSMSdss functional task keeps its own copy of the user area pointer. If the pointer is changed by the UIM for one task, it is not changed for any other task. At the beginning of each task, the user area pointer is the one passed to DFSMSdss by the application program.

#### **DDNAME/VOLID Pointer**

A fullword address field supplied by DFSMSdss. It contains the address of an area containing the DDNAME of the output dump data set, left-justified in an 8-byte area, followed by a 6-byte area containing the volume serial

number of the volume containing the dump data set, also left-justified. This pointer is valid only for the full-volume dump exit, EIOP06.

# **Application programming interface restrictions**

If you write a program that invokes ADRDSSU and needs to use some features of the z/OS Unix System Services, your program makes a call to z/OS UNIX through API. To connect to the kernel for z/OS UNIX, your program has to make an address space known to it. This process is called dubbing. Once dubbed, the address space is considered a thread in the z/OS Unix System Services space, and has the same security authorization as your program has. Therefore, your program and the ADRDSSU program are dubbed with your security authorization.

To avoid authorization problems, perform undub before DFSMSdss invocation. If you cannot undub before DFSMSdss invocation, undub after the ADRDSSU program has finished executing.

**Related reading:** For more information about using z/OS UNIX System Services, see:

- z/OS UNIX System Services Programming: Assembler Callable Services Reference.
- z/OS UNIX System Services Planning.

# **Cross-memory application interface restrictions**

Use SDUMP and SMSGCNT in place of ABEND and AMSGCNT when the Cross-Memory Application Interface is used. Although ABEND and AMSGCNT are supported by DFSMSdss, no dump is printed because DD allocations (SYSABEND, SYSUDUMP) in the application address space are unavailable to the address space producing the abend.

Serialization may operate differently, as application address space DD allocations are unavailable to the address space executing the DFSMSdss functions. Evaluate your serialization requirements when considering the use of the Cross-Memory Application Interface.

When multiple ADRDSSU tasks are executing in a DFSMSdss server address space, and identical DDNAMEs are passed in the SYSIN stream, allocation errors (such as MSGIKJ56246I – "file in use") can result. To avoid this possibility, use 8-character DDNAMEs or leave enough room after the DDNAME to allow ddname replacement. The Cross Memory Application Interface replaces common DDNAMEs passed in the SYSIN stream with unique 8-character, system-generated DDNAMEs whenever possible.

If you use the DFSMSdss Cross Memory Application Interface for logical COPY or logical DUMP and RESTORE of HFS and zFS type data sets, you must define a DFSMSdss user ID for the DFSMSdss server address spaces to be able to access the HFS and zFS data sets. The DFSMSdss user ID must be set up for the z/OS UNIX System Services (z/OS UNIX) access as follows:

- The default group for the DFSMSdss user ID must have a z/OS UNIX segment defined and a group ID associated with it.
- The home directory should be the root file system.
- The DFSMSdss user ID must be defined as a superuser (UID 0). Use the following RACF commands to make this assignment:

```
ADDGROUP OMVSGRP OMVS(GID(1))
ADDUSER DFSMSDSS DFLTGRP(OMVSGRP) OMVS(UID(0) HOME('/'))
```

You might want to set up a RACF (or equivalent) permission for the processing performed by the DFSMSdss cross-memory server address space. If you are using the ASPACE parameter, or ASIDPTR feature to request a specific address space name for the DFSMSdss Cross Memory server, enter an RDEF command to add that address space name to the Started Class table of your security product and associate that started task name (address space name) with a user id that has sufficient authority to perform the DFSMSdss functions.

The following example shows how to define started tasks that begin with ARC to RACF:

RDEF STARTED ARC\*.\*\* UACC(NONE) OWNER(ADMIN) AUDIT(ALL(READ)) STDATA(USER(DFSMSDSS) GROUP(STC) TRACE(YES))

where DFSMSDSs is a user id defined to RACF that has sufficient authority to perform the DFSMSdss functions and STC is a group that the user id is connected to. The above command sets a rule to match any new started tasks such as ARC1DUMP.ARC1DUMP with the DFSMSDSS user id. The wildcard usage allows other started tasks such as ARC1MIGR.ARC1MIGR to be associated with the DFSMSDSS id as well.

Specifying multiple commands (DUMP, RESTORE, or COPYDUMP) that process DFSMSdss dump data sets on the same tape volume is not supported when invoking DFSMSdss using the Cross-Memory Application Interface. This restriction applies whether or not the PARALLEL command is specified. To process multiple DFSMSdss dump data sets on the same tape volume using the Cross-Memory Application Interface, use multiple invocations of DFSMSdss with one command per invocation and ensure that the operations are executed serially.

The Cross-Memory Application Interface does not support overriding host-based encryption in favor of encryption provided by encrypting tape devices.

The DFSMSdss server's address space dispatching priority must be the same or higher than the priority of all clients' address spaces. The server's address space must be able to dispatch during the clients' termination process; otherwise, ABENDs may occur.

**Related reading:** For additional information about z/OS UNIX, see *z/OS UNIX System Services Planning*.

# User interaction module exit option descriptions

This section contains intended programming interface information.

Following are the descriptions for all exit points available with DFSMSdss.

# Function startup (Eioption 00)

This exit point is called during DFSMSdss initialization and again during function initialization (such as a dump or restore operation). The EIRECPTR points to the EIREC00 data area. The EIREC00 data area contains a field, EI00SBPL, which the application may use to return a subpool number that is to be shared between all DFSMSdss tasks. EI00SBPL is only valid when EITSKID is zero.

The application can set EI00NOLK to request that DFSMSdss bypass ADRLOCK ENQUEUE or DEQUEUE processing during full-volume and tracks RESTORE

operations. The application must be able to resolve any deadlock conditions that result from the request to bypass ADRLOCK ENQUEUE or DEQUEUE processing.

The application can also set EI00SENQ to request that VTOC serialization be held only for the duration of VTOC access. This flag is only valid for full volume dump operations and when EITSKID is nonzero. This flag provides a function similar to that provided by the Enqueue Installation Exit Routine (seez/OS DFSMS Installation Exits). The VTOC serialization is released after VTOC access is complete if either the EI00SENQ flag is set or the Enqueue Installation Exit Routine requests it.

The application can also set EI00NENQ to request that DFSMSdss not reserve on VTOC of the source volume. This flag is only valid for physical COPY and DUMP operations during function startup (for example, when EITSKID is nonzero).

The application can also set EI00BSEC flag to request that RACF verification and all other data set security checking is bypassed. This flag is only valid for full/tracks COPY, full/tracks DUMP, and full/tracks RESTORE operations during function startup (that is, when EITSKID is nonzero).

DFSMSdss provides the source VOLSER to the UIM. This field is only valid for full/tracks COPY, full/tracks DUMP, and full/tracks RESTORE during function startup (that is, when EITSKID is nonzero). For RESTORE, this field contains the volume serial number of the input volume where the dump data set resides.

The valid return codes for function startup are:

- 0 Continue normal processing
- **16** Record modified
- Inhibit all UIM calls—Not valid when EITSKID is zero and either UFSYSIN or UFSYSPR was set in the installation options exit, or EITSKID is nonzero and either UFNOIN or UFNOOUT was set in the installation options exit.
- End processing. This return code is only valid for a full dump and a full restore operation.

# Reading SYSIN record (Eioption 01)

This exit point is called after DFSMSdss reads a SYSIN record. You can replace, insert, delete, or modify a SYSIN record at this exit point. The EIRECPTR points to the SYSIN record. The valid return codes are:

- 0 Continue normal processing
- 4 Record replaced
- 8 Insert record
- **12** Delete record
- 16 Record modified
- 20 Disconnect exit

# **Printing SYSPRINT record (Eioption 02)**

This exit point is called when DFSMSdss is ready to print a SYSPRINT record. You can replace, insert, delete, or modify a SYSPRINT record at this exit point. The EIRECPTR points to the SYSPRINT record. Task-related SYSPRINT records are presented in task order unless the UIM requested that there be no SYSPRINT (see "System programming information" on page 584).

The valid return codes for printing SYSPRINT records are:

- Continue normal processing
- 4 Record replaced
- 8 Insert record
- 12 Delete record
- 16 Record modified
- 20 Disconnect exit

#### Note:

- 1. You can only modify or delete a page header record during the print operation.
- 2. EIXNTERR is set ON when the following conditions exist:
  - You have specified the TOL(IOERR) keyword.
  - DFSMSdss issues e-type messages with the exception of messages ADR324E, ADR347E, and ADR348E.
  - DFSMSdss issues t-type messages; the TOL(IOERR) keyword does not have to be specified.
- 3. EIXNTERR is set OFF when the following conditions exist:
  - An I-type or W-type message is issued by DFSMSdss.
  - DFSMSdss issues the ADR324E, ADR347E, and ADR348E (all or some combination) messages, and the TOL(IOERR) keyword is specified.
- 4. EIXNTERR is unchanged when DFSMSdss issues a nonprefixed message.

## Reading physical tape record (Eioption 03)

This exit point is called when DFSMSdss has read a record from a data set that has been dumped (on tape or DASD) by using the DUMP command. The EIRECPTR points to the tape record. The valid return codes are:

- Continue normal processing
- 8 Insert record. This return code is only valid when UFNOIN is set in the installation options exit
- 20 Disconnect exit. This return code is only valid when UFNOIN is not set in the user installation options exit
- 32 End function

# Reading logical tape record (Eioption 04)

This exit point is called when DFSMSdss has read a record from a data set that was created with a DUMP command and dumped on tape or DASD. The EIRECPTR points to the tape record. The valid return codes are:

- 0 Continue normal processing
- 8 Insert record
- 20 Disconnect exit
- 24 Select user statistics records
- 32 End function.

Note: If code 24 is returned, DFSMSdss only calls this exit point when DFSMSdss processes user statistics records.

# Writing logical tape record (Eioption 05)

This exit point is called when DFSMSdss writes a logical record to a dump data set, on tape, or on DASD, while performing a dump operation. If you insert a record at this exit point, DFSMSdss marks it as a statistics record, not a data record. The EIRECPTR points to the tape record. The valid return codes are:

- 0 Continue normal processing
- 8 Insert record
- 20 Disconnect exit
- 32 End function.

# Writing physical tape record (Eioption 06)

This exit point is called when DFSMSdss writes a physical record to a dump data set, on tape, or on DASD. The EIRECPTR points to the tape record and the EIDDID points to EIDDINFO. The valid return codes are:

- 0 Continue normal processing
- Delete record. This return code is only valid when UFNOOUT is set in the installation options exit
- Disconnect exit. This return code is only valid when UFNOOUT is not set in the user installation options exit
- 32 End function.

# Reading disk track (Eioption 07)

This exit point is called when DFSMSdss has read a track from DASD. The EIRECPTR points to the track buffer. The first 64 bytes (X'40') of the track buffer are IBM internal information that is followed by the ADRTAPB area, the DTTTRK area, and the track image. The valid return codes are:

- 0 Continue normal processing
- 20 Disconnect exit
- 32 End function. This return code is only valid for a full dump

**Related reading:** For additional information about ADRTAPB and DTTRK, see Chapter 13, "Format of the DFSMSdss dump data set," on page 197.

# Writing disk track (Eioption 08)

This exit point is called when DFSMSdss is ready to write a track to DASD. The EIRECPTR points to the track buffer. The valid return codes are:

- 0 Continue normal processing
- 20 Disconnect exit
- 32 End function. This return code is only valid for a full restore operation

# Reading utility SYSPRINT (Eioption 09)

This exit point is called when DFSMSdss is reading output from an attached utility. You can replace, insert, delete, or modify a utility SYSPRINT record at this exit point. The EIRECPTR points to the Utility SYSPRINT record. The valid return codes are:

0 Continue normal processing

- 4 Record replaced
- 8 Insert record
- 12 Delete record
- Record modified 16
- 20 Disconnect exit

## Writing SYSPRINT record (Eioption 10)

This exit point is called when DFSMSdss is ready to write a SYSPRINT record. You can replace, insert, delete, or modify the SYSPRINT record at this exit point. The EIRECPTR points to the SYSPRINT record. Task-related SYSPRINT records are not presented in task order. The valid return codes are:

- Continue normal processing
- 4 Record replaced
- 8 Insert record
- Delete record 12
- 16 Record modified
- 20 Disconnect exit

## Writing WTO message (Eioption 11)

This exit point is called when DFSMSdss is ready to write a WTO message. You can replace, insert, delete, or modify the WTO message at this exit point. The EIRECPTR points to the WTO message. The valid return codes are:

- Continue normal processing
- 4 Record replaced
- Insert record 8
- 12 Delete record
- 16 Record modified
- 20 Disconnect exit

# Writing WTOR message (Eioption 12)

This exit point is called when DFSMSdss is ready to write a WTOR message (that is, ADR369D, ADR345D, and ADR371D). You can insert or modify the WTOR message at this exit point. You can also return the response to DFSMSdss with return code 28. The EIRECPTR points to the WTOR message. The valid return codes are:

- 0 Continue normal processing
- 8 Insert record
- 16 Record modified
- 20 Disconnect exit
- WTOR response 28

# **Presenting ADRUFO record (Eioption 13)**

This exit point is called when DFSMSdss is ready to set up the installation options specified in the ADRUFO control block. You can modify the control block to override any options that have been specified thus far. You must use return code 16 for DFSMSdss to recognize the new options. The EIRECPTR points to ADRUFO. The valid return codes are:

- 0 Continue normal processing
- **16** Record modified
- End function. This return code is only valid for a full dump and a full restore operation.

# Function ending (Eioption 14)

This exit point is called when DFSMSdss is ready to end the task. The EIRECPTR points to the last message with highest nonzero return code. The record contains the DFSMSdss return code and the DFSMSdss message (message number and message type). The valid return code is:

0 Continue normal processing

## **Presenting WTOR response (Eioption 15)**

This exit point is called when the operator has responded to the WTOR (either a DFSMSdss WTOR or a user inserted WTOR, see exit point 12). You can only examine the response at this exit point. If you would like to change the response, you must use exit point 12, change the response, and use a return code of 28 to DFSMSdss. The EIRECPTR points to the response. The valid return code is:

0 Continue normal processing

# OPEN/EOV tape volume security and verification exit (Eioption 16)

This exit point is called when DFSMSdss is ready to open a tape. You can bypass password and expiration date checking for tape volumes or reject the volume and request a scratch tape with this exit by placing a return code in the first word of the record pointed to by EIRECPTR. DFSMSdss passes this return code to OPEN/EOV. The EIRECPTR points to the parameter list described by the IECOEVSE macro.

The valid return codes are:

- 0 Continue normal processing
- 16 Record modified
- 20 Disconnect exit
- End function. This return code is only valid for a full dump and a full restore operation

**Related reading:** For additional information about OPEN/EOV, see *z/OS DFSMS Using Data Sets*.

# **OPEN/EOV** nonspecific tape volume mount (Eioption 17)

This exit point is called when a nonspecific tape is passed to DFSMSdss. The EIRECPTR points to the DCB exit parameter list. You can specify a specific volume serial with this exit by placing the volume serial in the first 6 bytes of the record

pointed to by EIRECPTR. DFSMSdss passes this volume serial and return a code of 4 to OPEN/EOV informing it to use the specified volume serial. The EIRECPTR points to the parameter list described by the IECOENTE macro.

**Note:** DEFER must be specified in the JCL for this exit to be called.

The valid return codes are:

- Continue normal processing
- 16 Record modified
- 20 Disconnect exit
- 32 End function. This return code is only valid for a full dump and a full restore operation

## Insert logical VSAM record during restore (Eioption 18)

This exit point is called during a logical restore operation of a VSAM KSDS using record-level I/O. You can replace or modify a record at this exit point. The EIRECPTR points to the logical record that DFSMSdss is preparing to write to the data set. The valid return codes are:

- Continue normal processing
- 4 Record replaced
- Record modified 16
- 20 Disconnect exit

**Related reading:** For additional information about Eioption 18, see *z/OS DFSMS* Using Data Sets.

# Output tape I/O error (Eioption 19)

This exit point is called during a dump when a tape has a permanent I/O error. The EIRECPTR points to EIDDINFO. The valid return codes are:

- 0 Continue normal processing
- 20 Disconnect exit
- 32 End function

# **Volume notification (Eioption 20)**

During physical data set restore operations, this exit is called to provide information about the data set being allocated. This information includes:

- Cluster/data set name (for RENAME and RENAMEUNCONDITIONAL keywords, the new data set name is presented)
- An indication of whether the data set is VSAM or non-VSAM
- Number of data and index components (VSAM only)
- For each component or data set:
  - The number of volumes it resides on
  - The volume serial number of each volume
  - An RBA token for each volume.

EIRECPTR points to EIREC20. EI20DA@ and EI20IX@ point to EI20DSI.

Note: SMS-managed multivolume non-VSAM data sets have an RBA token only for the first volume. Non-SMS-managed data sets never have an RBA token.

The valid return codes are:

- 0 Continue normal processing
- 20 Disconnect exit
- End function. This return code is only valid for full or physical data set dump and full or physical data set restore operations

## **Data set verification (Eioption 21)**

This exit lets the UIM end data set copy, physical data set copy, dump, and restore processing for individual data sets. This exit is given control through the UIM at the start of data set copy, dump, and restore processing for each data set. DFSMSdss provides the UIM with the data set name through the EIREC21 structure within the exit identification block, ADREID0. EIREC21 is shown in Table 38 on page 607. The name provided is the original data set name prior to rename processing, if any, for copy and restore functions. The UIM returns to DFSMSdss with a return code in the exit identification block. The valid return codes are:

- 0 Continue normal processing
- 20 Disconnect exit
- 32 End function
- 36 End data set

DFSMSdss continues processing with the next data set, if any. If the user specifies the SPHERE keyword and processing for a base cluster is ended through this exit, processing for all AIXs related to the base cluster is also ended. If the user specifies the SPHERE keyword and the UIM attempts to end processing for an AIX that is related to a base cluster that was selected for processing, DFSMSdss invokes the UIM again. If the UIM attempts to end processing for the AIX again, DFSMSdss issues warning message ADR770W and ignores the request. If the user does not specify the SPHERE keyword, AIXs can be ended even if they are related to base clusters selected for processing. Ending a base cluster without the SPHERE keyword does not cause any related AIXs to be ended.

**Note:** See the "Note for Eioptions 21, 22, and 23" at the end of the description for eioption 23.

# **Bypass verification exit (Eioption 22)**

This exit lets a user force DFSMSdss bypass serialization and security verification during data set copy, physical data set copy, dump, and restore processing for individual data sets. It also lets a user turn on a tolerate-migrated-volser indicator that forces DFSMSdss to restore a data set with a migrated volser. This exit is given control through the UIM at the start of data set copy, dump, and restore processing for each data set. DFSMSdss provides the UIM with the data set name through the EIREC22 structure within the exit identification block, ADREID0. EIREC22 is shown in Table 38 on page 607. The data set name provided is the original name prior to rename processing, if any, for COPY or RESTORE. The UIM returns to DFSMSdss with a return code in the exit identification block. The valid return codes are:

- 0 Continue normal processing
- 16 Bypass one or more of the following:

- If the Reset indicator (EI22RSET) is set on by the UIM for a VSAM data set during a logical data set dump, DFSMSdss resets the data-set-changed flag in the VTOC if the data set is successfully serialized and processed. DFSMSdss will not reset the data-set-changed flag for data sets dumped with RLS access and BWO data sets, even if EI22RSET is set on by the UIM.
- If the DB2 Source Bypass indicator (EI22DB2) is set on by the UIM during a logical data set copy operation, and RENAMEU is specified for a DB2 VSAM linear data set, then DFSMSdss does not verify that the old component duplicates the DB2 naming convention when it derives the new component name. Alternatively, if the EI22DB2 bit is set on, DFSMSdss generates a DB2 component name for the target component—provided the new cluster name (specified in the RENAMEU parameter) matches the DB2 naming convention.
- If the IMS indicator (EI22IMS) is set on, the caller is IMS.
- If the Shared SYSDSN ENQ indicator (EI22SSYS) is set on by the UIM for a VSAM data set during logical data set dump, DFSMSdss attempts to obtain a shared SYSDSN enqueue. If EI22SSYS is not set on, then the type of SYSDSN enqueue (shared or exclusive) that DFSMSdss attempts to obtain depends upon whether or not the SHARE keyword was specified.
- If the Mark-As-Recovery-Required indicator (EI22RRB) is set on by the UIM during logical restore, DFSMSdss marks the target data set as recovery required, provided that the target data set is SMS-managed.
- If the Log Information Passed indicator (EI22LINF) is set on by the UIM during a logical restore, then DFSMSdss uses the log parameter (EI22LPRM), the log stream ID (EI22LSID) and the LOGREPLICATE indicator (EI22LREP) as the log information for the target data set, provided that the target data set is SMS-managed. If EI22LINF is not set, or the target data set is not SMS-managed, then the contents of EI22LPRM, EI22LSID and EI22LREP are ignored.
- If the BWO\_ALLOWED Passed indicator (EI22BWOP) is set on by the UIM during a logical restore, the DFSMSdss uses the BWO\_ALLOWED field (EI22BWOA) for the target data set, provided the target data set is SMS-managed. If EI22BWOP is not set or the target data set is not SMS-managed, then the contents of EI22BWOA are ignored.
- Serialization is bypassed if the UIM exit turns on the Bypass Serialization indicator, EI22BSER. Serialization is bypassed for the source data set for copy and dump processing, and for the target data set for copy and restore processing. DFSMSdss assumes that all necessary serialization has been performed by the invoker of DFSMSdss, but does not ensure that this is true. DFSMSdss performs normal serialization if the UIM exit does not turn on the bypass serialization indicator. DFSMSdss does not delete or uncatalog data sets that were bypassed for serialization even if the DELETE or UNCAT keywords are specified. If a preallocated data set is not large enough during a data set restore operation and the bypass serialization indicator is on, DFSMSdss does not scratch and reallocate that target data set and the restore operation
- RACF verification and all other data set security checking is bypassed if the UIM exit turns on the Bypass RACF indicator, EI22BSEC. If EI22BSEC is set on, DFSMSdss checks to ensure that the application program is authorized to bypass RACF and security processing. The application program is authorized to bypass RACF and security

processing if NOPASS was specified on the PPT statement of the SCHEDxx parmlib member. If the EI22BSEC indicator is on and NOPASS was specified, RACF verification and all other data set security processing including password checking is bypassed. DFSMSdss does not do any RACF authorization checks. DFSMSdss does not create any RACF profiles for the copied or restored target data set. DFSMSdss assumes that all necessary RACF authorization and security checking has already been performed by the invoker of DFSMSdss. For a copy or restore operation, RACF profiles are not created for the target data set. If the user turns on the bypass RACF indicator and PASS was specified on the PPT statement of the SCHEDxx parmlib member, DFSMSdss sets the error flag, EIXERR, on in the exit identification block and invokes the UIM again. If the user sets the bypass RACF indicator again, DFSMSdss issues error message ADR772W and processing continues as normal. DFSMSdss still allows serialization to be bypassed and tolerates migrated volume serial number processing if those indicators are set.

exit does not turn on the bypass RACF indicator.

• If the Tolerate-Migrated-Volser indicator is set on by the UIM, DFSMSdss takes special action to support the restoration of a non-VSAM data set

DFSMSdss performs normal RACF and security processing if the UIM

with a volume serial number of MIGRAT for a logical data set restore operation in an SMS-managed environment or when the CATALOG option has been specified. DFSMSdss ignores the EI22BMIG indicator for copy and dump operations and VSAM data sets.

When DFSMSdss is restoring a non-VSAM data set and the Tolerate-Migrated-Volser indicator is set on, a catalog LOCATE is issued to determine the status of the data set being restored. Based on the result of that LOCATE, different actions are taken.

### No catalog entry is found:

The data set being restored is not considered to be migrated. A normal DFSMSdss logical restore is performed. The Tolerate-Migrated-Volser indicator is ignored.

#### A catalog entry is found but the VOLSER is not MIGRAT:

The data set being restored is not considered to be migrated. Normal processing continues as though the indicator had not been set.

#### A catalog entry is found and the VOLSER is MIGRAT:

The data set is migrated and requires special processing. Instead of cataloging the data set after allocating it, DFSMSdss alters the existing MIGRAT volume serial number entry to the actual volume the data set was restored to. Once the catalog entry has been changed from MIGRAT to the new data set's volume serial numbers, the restore continues as normal.

**Note:** Because the migrated data set is not recalled during this restore, the user of this interface is responsible for deleting the migrated copy of the data set and updating the necessary control files.

DFSMSdss performs normal non-VSAM data set cataloging if the UIM exit does not turn on the tolerate-migrated-volser indicator.

- If the Extent Reduction bit (EI22EXTR) is set on by the UIM for a given data set and DFSMSdss is running in an SMS-managed environment, DFSMSdss tries to allocate the original volume where the data set was dumped.
- If the Restore-To-Like-Device bit (EI22LIKE) is set on by the UIM for a given data set and DFSMSdss is running in an SMS-managed environment, DFSMSdss tries to allocate the target data set on a device whose unit is the same as that of the source data set. If DFSMSdss can not allocate the target data set on a device whose unit type matches that of the source, the data set is not processed.
- Serialization by enqueuing on the major name of SYSDSN for a data set is bypassed if the UIM exit turns on the bypass SYSDSN indicator, EI22NSYS; other enqueues for a data set (for example, SYSVSAM) are not bypassed. The SYSDSN-level of enqueue serialization is bypassed for the source data set for DUMP and the target data set for RESTORE. DFSMSdss performs normal serialization if both EI22BSER and EI22NSYS are turned off.

DFSMSdss does not delete or uncatalog data sets if EI22NSYS is set, even if the DELETE or UNCATALOG keywords are specified. If EI22NSYS is on and the preallocated data set is too small, the data set is not scratched and reallocated, and the RESTORE fails.

If the UIM has set the "set reconnect" flag on, DFSMSdss then sets the reconnect flag in the catalog on. DFSMSdss ignores the EI22SFSM flag for VSAM data sets.

If the UIM exit sets the return code to EIRC16 but fails to turn on any of the bypass verification indicators, DFSMSdss ignores all bypass options and performs normally. If the UIM exit sets the return code to EIRC16 for a VSAM data set and turns on the tolerate-migrated-volser indicator, DFSMSdss does not treat it as an error condition and ignores the tolerate-migrated-volser indicator.

If a list of storage groups is passed by the UIM (EI22SGP) then the list is used to allocate SMS managed data sets during logical data set copy and restore. Users must take care to ensure that the storage groups passed do not conflict with the storage groups that would be assigned based on the storage class of the data set. A user may pass a maximum of 15 storage groups in the list. If the target data set is not SMS-managed then the storage groups passed are ignored.

If an ACS environment is passed by the UIM (EI22ACSEN), it is used in place of the DFSMSdss default environments (ALLOC for logical data set copy or RECOVER for logical data set restore). The ACS environment passed in is used when calling the management class and storage class ACS routines unless BYPASSACS indicates that one or both of the ACS routines should not be called. It is also passed to SMS on the allocation request. If EI22ACSEN specifies SPMGCLTR and a list of storage groups was not passed, DFSMSdss continues to process the data set in the default environments (ALLOC for logical data set copy or RECOVER for logical data set restore).

An application may set EI22DSSRL to either EISRLDB2, EISRLZFS, EISRLCICS or EISRLEXIT during a logical data set copy. If DFSMSdss is unable to obtain access to the data set, the service specified by EI22DSSRL is used to close the data set so that DFSMSdss is able to obtain access to process the data set. After the data set is processed the corresponding service is used to reopen the data set.

**Note:** When EI22DSSRL is set to either EISRLDB2, EISRLZFS, EISRLCICS or EISRLEXIT then RLS processing is bypassed.

- 20 Disconnect exit
- 32 End function
- 36 End data set

Refer to EIRC36 in "Data set verification (Eioption 21)" on page 597 for details on ending spheres.

**Note:** See the "Note for Eioptions 21, 22, and 23" at the end of the description for eioption 23.

## Data set processed notification exit (Eioption 23)

This exit indicates to the UIM whether or not the logical copy, dump, or restore processing for individual data sets was successful. This exit is given control through the UIM at the conclusion of logical copy, dump, and restore processing for each data set. DFSMSdss provides the UIM with information through the EIREC23 structure within the exit identification block, ADREID0. EIREC23 is shown in Table 38 on page 607.

DFSMSdss provides the UIM with the following information at the conclusion of processing for logical dump of each data set:

- The data set name that was dumped
- The RLS time stamps associated with the dump
- A flag indicating whether or not the data set is marked "recovery required"
- A return code for the data set that indicates whether processing was successful:
- O Data set completely successful (informational)
- 4 Data set partially successful (warning)
- 8 Data set unsuccessful (error)
- **12** Ending error
- 16 Ending error
- The source SMS flag (DS1SMSFG) from the Format 1 DSCB
- The source data set organization (DS1DSORG) from the Format 1 DSCB for a non-VSAM data set
- Flags to indicate data set type for a VSAM data set

DFSMSdss provides the UIM with the following information at the conclusion of processing for a logical copy and a logical restore of each data set:

- The original data set name that was copied or restored. This is the data set name prior to rename processing, if any.
- The new data set name being copied or restored if rename processing was performed.
- A return code for the data set that indicates whether processing succeeded:
  - O Data set completely successful (informational)
  - 4 Data set partially successful (warning)
  - 8 Data set unsuccessful (error)
  - **12** Ending error
  - **16** Ending error
- The source and target SMS flags (DS1SMSFG) from the Format 1 DSCB.
- The source and target data set organization (DS1DSORG) from the Format 1 DSCB for a non-VSAM data set.

- Flags to indicate data set type for a VSAM data set.
- A count of the volumes that the data set was copied or restored to.
- · A list of the volume serial numbers (VOLSERs) that the data set was copied or restored to.

The UIM returns to DFSMSdss with a return code in the exit identification block. The valid return codes are:

- Continue normal processing
- 20 Disconnect exit
- End function 32
- 36 End data set

It does not undo any successful processing, but deletes the data set from the successfully-processed message list (if applicable) and includes it in the unsuccessfully-processed message list. It is the responsibility of the user of this interface to delete the copied, dumped, or restored data set from the target volumes. DFSMSdss continues processing with the next data set, if any. Refer to EIRC36 in "Data set verification (Eioption 21)" on page 597 for details on ending spheres.

## Note for Eioptions 21, 22, and 23

If Eioptions 21, 22, and 23 end the function (UIM passes back a return code 32 to DFSMSdss) during a data set copy operation, DFSMSdss can be processing more than one data set at the time. This can happen if utilities are needed to process some of the data sets. DFSMSdss does the following before ending:

- No unprocessed data sets are scheduled for processing.
- All data sets in utility processing are allowed to complete normally.
- No new calls are made to exits 21, 22, or 23. This includes data sets in utility processing that are allowed to complete.
- Spheres that are being processed because of the SPHERE keyword and that are not complete at the end of the function have the target parts deleted to preserve sphere integrity. Preallocated spheres are left partially copied.
- Spheres being processed without the SPHERE keyword or individual sphere components being copied are left partially completed.

# Concurrent copy initialization complete (Eioption 24)

This section contains intended programming interfaces.

DFSMSdss calls the UIM with option code 24 to inform it that the initialization of the concurrent copy session for a given data set or volume has completed. For full-volume or tracks operation, there is only one call (because there is only one input volume). For a physical data set operation, there is one call for each input volume. For a logical data set operation, there is one call for every data set. DFSMSdss does not call the UIM with this option code if the CONCURRENT keyword is not specified. DFSMSdss provides the UIM with information through the EIREC24 structure within the Exit Identification Block, ADREIB (in the ADREID0 macro).

DFSMSdss provides the UIM with the following information:

 A return code indicating whether or not the concurrent copy session initialization succeeded:

- O Concurrent copy session initialization was successful and any serialization on the data has been released.
- 4 Concurrent copy session initialization failed. If this is a logical data set operation, this data set is not processed using concurrent copy, but other data sets may be. If this is a full-volume, tracks, or physical data set operation, concurrent copy is not used. In either case, serialization is obtained and released as if CONCURRENT were not specified. When this exit is called, DFSMSdss may not be holding any serialization.
- A reason code providing further details about the status of the concurrent copy session initialization (always valid, even for a zero return code):
  - The concurrent copy operation is logically complete at this time (data movement has not been done yet).
  - 4 All parts of the data being dumped or copied were not on hardware supporting concurrent copy.
  - 8 Hardware limits exceeded.
  - 12 System data mover failed.
  - 16 Host limits exceeded.
  - 20 System data mover not available.
  - 24 Other host error.
  - Data set type not supported for concurrent copy.
  - The concurrent copy operation is logically and physically complete at this time (data movement has been done).
  - The data being processed requires the use of SnapShot, but the SnapShot software support is not available on the system.
- The volume serial of the volume on which the concurrent copy initialization was attempted (valid only if the reason code is not 16).
- The name of the data set on which the concurrent copy initialization was attempted (valid only if a logical data set operation is being performed).
- A flag indicating whether or not DFSMSdss has reset the data-set-changed flag in the VTOC for the data set (valid only if a logical data set dump operation is being performed).

The UIM returns to DFSMSdss with a return code in the Exit Identification Block. DFSMSdss continues to process based on that return code, as follows:

- 00 Continue normal processing
- 20 Disconnect this exit
- The DFSMSdss function is ended (not valid for a physical data set dump or logical data set copy)
- 36 End data set (not valid for full or tracks operations)

Error handling is the same as described under User Return Code.

# **Backspace physical tape record (Eioption 25)**

This exit point is called when DFSMSdss requires the input to be repositioned to the previous tape block (tape or DASD). The EIRECPTR is zero. The valid return codes are:

- 0 Continue normal processing
- 20 Disconnect exit
- 32 End function

## Dump volume output notification (Eioption 26)

Exit 26 of the DFSMSdss UIM may be used to determine the following:

- When a new dump output volume has been added for each DDNAME being processed. (DFSMSdss sets EI26VOL with EI26DDN and EI26VSER.)
- When a dump output volume associated with a specific DDNAME receives a terminating error condition. (DFSMSdss sets EI26TERM with EI26DDN and EI26VSER. EI26VTRC contains the failing function return code.)
- When EI22IMS is on and an R0 count mismatch occurs during copy or dump processing for BWO(TYPEIMS) KSDS data sets. (DFSMSdss sets EI26ROCE. The data set name is located by EI26DSN.)
- When an application requests host-based encryption through the DFSMSdss application programming interface (API), and DFSMSdss overrides the request in favor of tape device encryption, DFSMSdss uses the Volume Output Notification Exit (Exit 26) to notify the caller. To indicate that the output tape volume used tape device encryption, DFSMSdss sets the EI26TWHE bit to one in the ADREID0 mapping.
- When a dump output volume associated with a specific DDNAME is closed. (DFSMSdss sets EI26VCLO with EI26DDN and EI26VSER, EI26VTRC contains the return code from CLOSE.)

Exit 26 is invoked with EI26VCLO set only during logical dump operations and only for output data sets residing on DASD devices.

If Exit 26 is not driven for a given DDNAME or is driven with EI26VTRC greater than zero, then the output data set associated with the DDNAME was not closed successfully and should not be depended upon for subsequent restore operations.

The UIM presents a return code to DFSMSdss in the Exit Identification Block. DFSMSdss continues to process based on that return code, as follows:

- 00 DFSMSdss continues normal processing
- Disconnect this exit 20
- DFSMSdss ends the function (valid only for EI26TERM)

# Physical data set processed notification exit (Eioption 27)

This exit indicates to the UIM whether or not the physical data set copy for individual data sets was successful. This exit is given control through the UIM at the conclusion of physical data set copy processing for each data set. DFSMSdss provides the UIM with information through the EIREC27 structure within the exit identification block, ADREID0. EIREC27 is shown in "ADREID0 data area" on page 607.

- The data set name.
- The new name of the data set.
- The new names of the VSAM data and index components.
- A return code indicating the success of processing the data set.
- The source data set organization (DS1DSORG).
- The source data set SMS flag (DS1SMSFG).

- Flags indicating the source VSAM data set type (KSDS, ESDS, LDS).
- Flags indicating the target VSAM data set type.
- A count of the number of tracks processed for this data set.
- The last volume indicator of the data set from the source data set. This will be valid for non-VSAM data sets only.
- If the first volume of a VSAM data set was processed, DFSMSdss will pass the total stripe count for the data component when the data set processed was a striped VSAM data set. The High Allocated RBA count for the data and index components will be passed as well.
- When processing a VSAM data set, DFSMSdss will pass the stripe number of the data component on this volume. 0 will be passed when the data set is not striped.
- When processing a VSAM data set, DFSMSdss will pass the number of RBAs processed for this data component on this volume.
- When processing an indexed VSAM data set, DFSMSdss will also pass the number of RBAs processed for this index component on this volume.
- · The target volume serial as well as the source volume serial.
- An indication of whether the target data set is protected by a discrete RACF profile.

## Target data set allocation notification exit (Eioption 28)

This exit indicates to the UIM how to direct allocation of target data sets during logical and physical restore and physical data set copy. The exit is given control through the UIM just prior to volume selection for target data set allocation for each data set being processed for logical data set operations. For physical operations, the exit is given control through the UIM just prior to target data set allocation. DFSMSdss provide the UIM with information through the EIREC28 structure within the exit identification block, ADREID0. EIREC28 is shown in "ADREID0 data area" on page 607. The actual call includes the following information:

- Source Data Set Name (input)
- Target Data Set Name (input)
- Extended Attribute Value (DS1EATTR) (output)
- Format-9 DSCB (output)
- Target Data Set Creation Date (output)
- CA Reclaim Attribute Value (output)

The UIM presents a return code to DFSMSdss in the Exit Identification Block. DFSMSdss continues to process based on that return code, as follows:

- 00 DFSMSdss continues normal processing.
- DFSMSdss will examine the paramter block passed back to determine if any parameters returned should be used for target allocation. If the UIM sets return code EIRC16 but did not indicate any of the parameters should be used, DFSMSdss continues normal processing.
- 20 Disconnect this exit.

# Physical data set volume allocation notification exit (Eioption 30)

This exit indicates to the UIM that allocation to the specified SMS volume failed during physical data set RESTORE or COPY. The exit is given control through the

UIM, after the allocation attempt for each data set attempted. DFSMSdss provides the UIM with information through the EIREC30 structure within the exit identification block, ADREID0. EIREC30 is shown in "ADREID0 data area" on page 607.

The actual call includes the following information:

- Tracks required
- · Overall exit return code
- Pointer to list of volumes
- Number of volumes in array
- VOLSER
- · Volume attempted flag
- Volume used flag
- Volume return code
- Volume reason code

The UIM presents a return code to DFSMSdss in the Exit Identification Block. DFSMSdss continues to process based on that return code, as follows:

- 00 DFSMSdss continues normal processing.
- 16 The record has been modified.
- 20 Disconnect exit.
- 32 End function.

## **Avoiding lockout**

Refer to "Avoiding lockout" on page 562 for a description of the ENQ scheme to prevent lockout.

# Application interface summary

For **Record Processing**, if the UIM makes any changes to the presented record (assuming it can validly do so), return code 16 must be returned or the changes are ignored. If the record is to be replaced in total, return code 4 must be returned or the original record is used. If a record is to be inserted before the current record, return code 8 must be returned or the record is ignored. If the current record is to be deleted, return code 12 must be returned or the current record is processed. If the exit is no longer interested in processing any records appearing at the current DFSMSdss exit point, return code 20 must be returned or the exit is called at the next visitation of DFSMSdss to the exit point. The current record is still processed in either event. If you want to receive only user statistical records at any specific exit, return code 24 must be returned. If you want to process a WTOR within the UIM, the response must be returned to DFSMSdss with a return code 28.

If a record is being returned that is longer than the original record, the exit must either replace the record in the area pointed to by the original record pointer (as long as it does not exceed the length in EIRECALN) or supply another area and store the address to the record in the original record pointer field. In either case, the length must be stored in the original record length field and a return code of 4 must be used.

If a record is being returned that is shorter than the original record, the exit can supply an area and store the address to the record in the original record pointer field or, if allowed, can replace the original record with the shorter one. In either case, the length of the new record must be placed in the original record length field. If the new area option was used, return code 4 must be used. If the new record overlaid the original, return code 16 must be used. Table 38 describes the data area corresponding to the DFSMSdss exit identification block.

For **Data Set Processing**, Eioptions 21, 22, and 23 are three exits that give you added control over data set processing during a logical data set copy, dump, and restore operations. These exits are called immediately before and immediately after processing each data set, on a data set by data set basis, and allow you to make a number of processing changes.

Eioptions 21 and 22 are called, consecutively, at the start of processing of each data set. DFSMSdss passes the name of the data set being processed to each exit. Based on that name, each exit permits the following:

- End processing of that one data set (return code 36).
- End processing of the entire functional task (return code 32).
- Disconnect the exit so that it will not be called before subsequent data sets task processing (return code 20).
- Perform nothing (return code 0).
- Eioption 22 only: Modify how the data set will be processed (return code 16). See "Bypass verification exit (Eioption 22)" on page 597 for details.

Eioption 23 is called immediately after a data set is processed. Eioption 23 lets you end processing of both the data set and the task, disconnect the exit, or do nothing.

## ADREID0 data area

Table 38 describes the data area corresponding to the DFSMSdss exit identification block.

Table 38. ADREIDO Mapping Macro

Off	sets				
Dec	Hex	Type	Len	Name (Dim)	Description
0	(0)	STRUCTURE	42	ADREIB	
0	(0)	SIGNED	2	EIDLLEN	LENGTH OF ADREIB - 2
2	(2)	CHARACTER	4	EIID	BLOCK IDENTIFIER EBCDIC "EIDB"
6	(6)	SIGNED	4	EITSKID	TASK ID NUMBER
10	(A)	BITSTRING	4	EIXALLOW	USER EXIT ALLOWANCE OPTIONS
10	(A)	BITSTRING	1	EIXALOW0	ALLOWANCE OPTION BYTE 1
		1		EIXREP	ALLOW REPLACE OF RECORD
		.1		EIXINS	ALLOW INSERTION OF RECORD
		1		EIXDEL	ALLOW DELETION OF RECORD
		1		EIXMOD	ALLOW MODIFICATION OF
					RECORD
		1		EIXDIS	ALLOW DISCONNECT OF EXIT
		1		EIXWTOR	ALLOW WTOR RESPONSE
		1.		EIXSTAT	ALLOW SELECTION OF USER STATS
		1		EIXTERM	ALLOW FUNCTION TERMINATION
11	(B)	BITSTRING	1	EIXALOW1	ALLOWANCE OPTION BYTE 2
		1		EIXTDSET	ALLOW DATA SET TERMINATION
		.111 1111		*	UNUSED
12	(C)	BITSTRING	1	EIXALOW2	ALLOWANCE OPTION BYTE 3
12	(C)	BITSTRING	1	*	RESERVED
13	(D)	BITSTRING	1	EIXALOW3	ALLOWANCE OPTION BYTE 4

Table 38. ADREID0 Mapping Macro (continued)

Off	sets				
Dec	Hex	Туре	Len	Name (Dim)	Description
		1		EIXERR	DISALLOWED OPTION ATTEMPTED
		.111 1111		*	RESERVED
14	(E)	SIGNED	2	EIOPTION	PROCESSING OPTION
16	(10)	SIGNED	2	EIRETCOD	EXIT RETURN CODE
18	(12)	SIGNED	4	EIRECALN	RECORD AREA LENGTH
22	(16)	SIGNED	4	EIRECLEN	ORIGINAL RECORD LENGTH
26	(1A)	ADDRESS	4	EIRECPTR	ORIGINAL RECORD ADDRESS
30	(1E)	ADDRESS	4	EIUSEPTR	USER DATA AREA ADDRESS
34	(22)	ADDRESS	4	EIDDID	EIOP06 DDNAME/VOLID PTR
38	(26)	BITSTRING	4	EIXFLAGS	OTHER FLAGS
38	(26)	BITSTRING	1	EIXFLAG0	FLAG BYTE 0
		1		EIXABEND	FOR EIOP02 ONLY, 1=MESSAGE IS ADR013 INDICATING AN ABEND CONDITION
		.1		EIXNTERR	FOR EIOP02 ONLY, 1=MESSAGE IS TYPE 'E' AND IS NOT 324 OR 347
		1		EIXWNGOK	FOR EIOP14 ONLY, 1=WARNING MSGS WERE ISSUED AND NONE ARE FATAL
		1		EIXTRKER	TRACK IS IN ERROR
		1111		*	RESERVED
39	(27)	BITSTRING	1	EIXFLAG1	FLAG BYTE 1
		1		*	RESERVED
		.1		*	RESERVED
		1		EIXTDUMS	DUMMY SOURCE TAPE
		1		EIXTDUMT	DUMMY TARGET TAPE
		1		EIXTISXM	APPL USING XMAPI
		1		EIXDASYS	XMAPI ALLOCATION ERR
		1.		EIXTWERR	XMAPI TAPE WRITE ERR
		1		EIXTRERR	XMAPI TAPE READ ERR
40	(28)	BITSTRING	1	EIXFLAG2	FLAG BYTE 2
40	(28)	BITSTRING	1	*	RESERVED
41	(29)	BITSTRING	1	EIXFLAG3	FLAG BYTE 3
41	(29)	BITSTRING	1	*	RESERVED
42	(2A)	CHARACTER		*	FORCE SIZE OF CONTROL BLOCK TO WORD BOUNDARY
Note: THE FC	DLLOWING MA	APS THE RECORD PRES	SENTED BY	exit 6 and point	ED TO BY EIDDID.
0	(0)	STRUCTURE	16	EIDDINFO	UIM-06 INFO
0	(0)	CHARACTER	8	EIDDNAME	O/P DEVICE DDNAME
8	(8)	CHARACTER	6	EIVOLID	O/P VOLSER
14	(E)	UNSIGNED	1	EIRETC	RESERVED FOR RETCODE
15	(E) (F)	UNSIGNED	1	EI06FLGS	EXIT 06 FLAGS
	(1)	1	1	EI06FLTR	RESERVED FOR HSM USE
		.1		EI06THWE	RESERVED FOR HSM USE OUTPUT
		11 1111		*	DEVICE ENCRYPTS RESERVED
16	10	ADDRESS	4	EI06DCB@	RESERVED FOR HSM USE
20	14	CHARACTER	4	*	RESERVED
	1	APS THE RECORD PRES	SENTED BY	EXIT 00 (FUNCTION	1
				<u> </u>	·
0	(0)	STRUCTURE	16	EIREC00	CHAPED CHIPDOOL NAD COED
0	(0)	UNSIGNED	1	EI00SBPL	SHARED SUBPOOL NUMBER
1	(1)	BITSTRING	1	EI00FLGS	STARTUP FLAGS
		1		EI00SENQ	SHORT VTOC ENQUEUE
		.1		EI00NONF	DO NOT ALLOW IGWNOTIF CALL

Table 38. ADREID0 Mapping Macro (continued)

Offs	sets				
Dec	Hex	Type	Len	Name (Dim)	Description
		1		EI00NOLK	DO NOT PERFORM ADRLOCK ENQUEUE OR DEQUEUE
		1		EI00NENQ	NO INPUT VOLUME SERIALIZATION. VALID DURING
		1		EI00BSEC	PHYSICAL COPY AND DUMP FUNCTION STARTUPS BYPASS SECURITY VERIFICATION FOR DATA SETS ON THE VOLUME DURING COPY FULL/TRACKS, DUMP FULL/TRACKS, AND
		1		EI00MVOLRECOV	RESTORE FULL/TRACKS FUNCTION STARTUPS 1=CALLER IS PERFORMING A
					MULTI-VOLUME RECOVERY USING PHYSICAL DATA SET RESTORE AND IT IS ACCEPTABLE FOR DFSMSDSS TO SCRATCH PREALLOCATED TARGET DATA SETS THAT ARE NOT THE CORRECT SIZE
		1.		EI00BSER	1=BYPASS SERIALIZATION OF THE DATA SETS BEING RESTORED DURING A PHYSICAL DATA SET RESTORE OPERATION
		1		*	RESERVED
2	(2)	CHARACTER	6	EI00SVOL	SOURCE VOLSER. VALID DURING COPY FULL/TRACKS, DUMP FULL/TRACKS, AND RESTORE FULL/TRACKS FUNCTION STARTUPS. FOR RESTORE, THIS FIELD CONTAINS THE VOLSER OF THE INPUT VOLUME WHERE THE DUMP DATA SET RESIDES
8	(8)	BITSTRING 1	1	EI00FLG2 EI00SWNCRYPT	SECOND FLAG AREA SOFTWARE ENCRYPTION WAS REQUESTED (RSA OR KEYPASSWORD WAS SPECIFIED)
		.1 1		EI00CANSFE EI00MIXDEV	CANCEL SOFTWARE ENCRYPTION MIXTURE OF DEVICES; SOME ARE PERFORMING HARDWARE ENCRYPTION AND OTHERS ARE NOT.
		1 1111		EI00ZCMP	ZCOMPRESSION IS ATTEMPTED RESERVED
9	(9)	1111 UNSIGNED	4	EI00CIRBA DA	RBA OF VVR CI DATA/NONVSAM
13	(D)	UNSIGNED	4	EI00CIRBA_IX	RBA OF VVR CI INDEX
I	LLOWING MA			_	E NUMBER ASSOCIATED WITH
0	(0)	CTDI ICTI IDE	17	EIDEC14	
0	(0) (0)	STRUCTURE CHARACTER	16 4	EIREC14 EI14RC	DSS RETURN CODE
4	(4)	CHARACTER	4	EI14KC EI14MESS	DSS MESSAGE
4	(4)	CHARACTER	3	EI14ME35 EI14MNUM	MESSAGE NUMBER
7	` ′	CHARACTER	3 1	EI14MNUM EI14MTYP	MESSAGE TYPE
	(7)				DSS CPU TIME
8	(8)	CHARACTER	8	EI14CPUT	
16	(10)	SIGNED	1	EI14ZCSV *	ZCOMPRESS PERCENTAGE SAVED
17   <b>Note:</b> THE FO	(11)   DLLOWING MA	CHARACTER  APS THE RECORD PRES	15 SENTED BY		UNUSED TIFICATION EXIT.
0		STRUCTURE	56	EIREC20	
U	(0)	SIKUCIUKE	26	EIKEC20	

Table 38. ADREID0 Mapping Macro (continued)

	fsets	_			
Dec	Hex	Type	Len	Name (Dim)	Description
0	(0)	CHARACTER	44	EI20DSN	DATA SET NAME/CLUSTER NAME
44	(2C)	BITSTRING	1	EI20FLGS	SOME FLAGS:
		1		EI20VSAM	1=DATA SET IS VSAM 0=DATA SET NONVSAM
		.1		EI20RACF	1=DATA SET IS PROTECTED BY A DISCRETE RACF PROFILE
		1		EI20LVOL	1=LAST VOLUME INDICATOR ON FOR NON-VSAM DS
		1 1111		*	RESERVED
45	(2D)	CHARACTER	1	*	RESERVED
46	(2E)	UNSIGNED	1	EI20DA#	NUMBER OF DATA COMPONENTS
47			1	EI20IX#	NUMBER OF INDEX COMPONENTS
	(2F)	UNSIGNED			(0 IF NONVSAM)
48	(30)	ADDRESS	4	EI20DA@	POINTER TO DATA COMPONENT INFO FOR VSAM/DATA SET INFO FOR NONVSAM
52	(34)	ADDRESS	4	EI20IX@	POINTER TO INDEX COMPONENT
TRUCTURE. OMPONEN	FOR A VSAMT), AND EI20I	I CLUSTER, EI20DA@ PO X@ POINTS TO A SIMILA	INTS TO AN AR ARRAY F	ARRAY OF STRUCTU	
56	(38)	SIGNED	2	*	PADDING (UNUSED) THE EI20SCN EI20DSHA, AND EI20ISHA FIELDS ARE PROVIDED WHEN PROCESSING THE FIRST VOLUME OF A MULTI VOLUME DATA SET
58	(3A)	SIGNED	2	EI20SCNT	TOTAL STRIPE COUNT FOR THIS VSAM DATA SET
60	(3C)	UNSIGNED	4	EI20DSHA	VSAM DATA COMPONENT HIGH ALLOCATED RBA CNT
64	(40)	UNSIGNED	4	EI20ISHA	VSAM INDEX COMPONENT HIGH ALLOCATED RBA CNT
0	(0)	STRUCTURE	68	EI20DSI	DATA SET INFO
0	(0)	CHARACTER	44	EI20CON	COMPONENT NAME (BLANKS FOR NONVSAM)
44	(2C)	UNSIGNED	2	EI20NVOL	# OF VOLUMES IN DS
46	(2E)	CHARACTER	2	*	RESERVED
	1		20		VOLUME INFORMATION
48	(30)	CHARACTER		EI20VLI	
48	(30)	CHARACTER SIGNED	6 2	EI20VOL E20DSTP#	VOLSER STRIPE NUMBER FOR THE DATA
54	(50)				
					DATA SETS
54 56	(38)	UNSIGNED	4	EI20RBA	DATA SETS RBA TOKEN. THE EI20DRBA FIELD IS CALCULATED BY SUBTRACTING
		UNSIGNED	4	EI20RBA EI20DRBA	RBA TOKEN. THE EI20DRBA FIELD IS CALCULATED BY SUBTRACTING THE HIGH RBA FIELDS FROM THE
56	(38)				DATA SETS RBA TOKEN. THE EI20DRBA FIELD IS CALCULATED BY SUBTRACTING THE HIGH RBA FIELDS FROM THE LOW RBA FLDS. TOTAL NUMBER OF RBAS
56	(38) (3C) (40)	UNSIGNED	4	EI20DRBA	DATA SETS RBA TOKEN. THE EI20DRBA FIELD IS CALCULATED BY SUBTRACTING THE HIGH RBA FIELDS FROM THE LOW RBA FLDS. TOTAL NUMBER OF RBAS PROCESSED FOR THIS COMPONED VOLUME SEQUENCE NUMBER FO
56 60 62 64	(38) (3C) (40) (42)	UNSIGNED SIGNED	4 2 2	EI20DRBA EI20VLSQ *	DATA SETS RBA TOKEN. THE EI20DRBA FIELD IS CALCULATED BY SUBTRACTING THE HIGH RBA FIELDS FROM THE LOW RBA FLDS. TOTAL NUMBER OF RBAS PROCESSED FOR THIS COMPONED VOLUME SEQUENCE NUMBER FOR THE DATA SET RESERVED
56 60 62 64 ote: THE FC	(38) (3C) (40) (42) DLLOWING M	UNSIGNED SIGNED SIGNED IAPS THE RECORD PRES	4 2 2 SENTED BY	EI20DRBA EI20VLSQ * EXIT 21: DATA SET VE	DATA SETS RBA TOKEN. THE EI20DRBA FIELD IS CALCULATED BY SUBTRACTING THE HIGH RBA FIELDS FROM THE LOW RBA FLDS. TOTAL NUMBER OF RBAS PROCESSED FOR THIS COMPONED VOLUME SEQUENCE NUMBER FO THE DATA SET RESERVED
56 60 62 64	(38) (3C) (40) (42)	UNSIGNED SIGNED SIGNED	4 2 2	EI20DRBA EI20VLSQ *	DATA SETS RBA TOKEN. THE EI20DRBA FIELD IS CALCULATED BY SUBTRACTING THE HIGH RBA FIELDS FROM THE LOW RBA FLDS. TOTAL NUMBER OF RBAS PROCESSED FOR THIS COMPONED VOLUME SEQUENCE NUMBER FOR THE DATA SET RESERVED

Table 38. ADREID0 Mapping Macro (continued)

Offs	ets				
Dec	Hex	Туре	Len	Name (Dim)	Description
0	(0)	STRUCTURE	102	EIREC22	
0	(0)	CHARACTER	44	EI22DSN	DATA SET/CLUSTER NAME
44	(2C)	BITSTRING	1	EI22FLGS	EXIT 22 FLAGS:
	()	1		EI22BSER	1=BYPASS SERIALIZATION
		.1		EI22BSEC	1=BYPASS DATASET LEVEL,
					STORCLAS & MGMTCLAS SECURITY
					CHECKS. ALSO BYPASS JES3
					INTEGRITY CHECKS AND DO NOT
					CREATE DISCRETE DATASET PROFILES.
		1		EI22BMIG	1=TOLERATE MIGRATED VOLSER
				LIZZDIVIIG	FOR NONVSAM DSETS (RESTORE
					ONLY) @DS007
		1		EI22NSYS	BYPASS SYSDSN ENQ SWAPPED W/
					EI22SIRS
		1		EI22LIKE	RESTORE/COPY DATA SET TO A
					LIKE DEVICE TYPE
		1		EI22EXTR	RESTORE DATA SET TO EXTENT REDUCTION VOLUME
		1.		EI22SIRS	SET INCMPLT RECALL SWAPPED
		4		FIGODRO	W/ EI22NSYS
44	(2D)	1	-	EI22DB2	BYPASS SOURCE FOR DB2 RENAME
45	(2D)	CHARACTER	5	EI22SFLG	SOURCE DATA SET FLGS
45	(2D)	CHARACTER	1	E22SSMSF	SOURCE SMS FLAGS
46	(2E)	CHARACTER	2 2	E22SDSRG	SOURCE DATA SET ORG
48	(30)	BITSTRING	2	E22SVFLG	SRCE VSAM DSET FLAGS
		1 .1		E22SESDS E22SKSDS	1=ESDS DATA SET 1=KSDS DATA SET
		.1		E22SKRDS	1=KSDS DATA SET 1=KRDS DATA SET
		1		E22SLDS	1=LINEAR DATA SET
		1		E22SRRDS	1=RRDS DATA SET
		1		E22SPSSI	1=PAGE/SWAP/STGINDEX, ETC.
		1		12201 001	UNSUPPRTED DATA SETS
		1.		E22SVVDS	1=VVDS DATA SET
		1		E22SBCS	1=BCS DATA SET
49	(31)	1		E22SAIX	1=AIX DATA SET
		.1		E22SVRRD	VRRDS DATASET
		11 1111		*	RESERVED
50	(32)	BITSTRING	1	EI22FLG2	MORE EXIT 22 FLAGS
		1		EI22RSET	RESET DS CHANGED FLAG
		.1		EI22SSYS	GET SHARED SYSDSN ENQ
		1		EI22RRB	MARK TGT RECOVRY REQ'D
		1		EI22LINF	LOG INFO PASSED, SEE EI22LPRM
		1		FIGORIAGO	AND EI22LSID
		1		EI22BWOP	BWO_ALLOWED PASSED, SEE EI22BWOA
		1		EI22IMS	CALLER IS IMS
		1.		EI22BWOE	ENQ ON BWODSN ONLY, NO ADR OR SYS ENQ'S
		1		*	UNUSED
51	(33)	CHARACTER	1	EI22LPRM	LOG PARAMETER FOR TGT
52	(34)	CHARACTER	26	EI22LSID	LOG STREAM ID FOR TGT
78	(4E)	BITSTRING	1	EI22FLG3	MORE EXIT 22 FLAGS
		1111		EI22BWOA	BWO_ALLOWED
		1		EI22BRLS	BYPASS RLS QUIESCE
		1		EI22SFSM	SET RECONNECTABLE FLAG

Table 38. ADREID0 Mapping Macro (continued)

Off	sets				
Dec	Hex	Туре	Len	Name (Dim)	Description
		1.		EI22LREP	SET LOGREPLICATE FLAG
		1		*	UNUSED
79	(4F)	UNSIGNED	1	EI22DSSRL	DATA SET SERIALIZATION ERROR ACTION
80	(50)	CHARACTER	8	EI22ACSEN	ACS ENVIRONMENT
88	(58)	ADDRESS	4	EI22SGP	STORAGE GROUP LIST PTR
92	(5C)	CHARACTER	32	AVAILABLE	
Note: THE FC EI22SGP.	DLLOWING MA	APS THE RECORD PRES	SENTED BY	EXIT 22: BYPASS VE	ERIFICATION. EISGLIST IS BASED ON
0	(0)	STRUCTURE	484	EISGLIST	UIM-22 STORAGE GROUP LIST
0	(0)	CHARACTER	4	EISGHDR	STORAGE GROUP LIST HEADER
0	(0)	UNSIGNED	1	EISGCNT	NUMBER OF STORAGE GROUP
IST ENTRIES		01,0101,122	-	12.000111	THE TABLET OF STERRING SHOOT
1	(1)	CHARACTER	3	*	FOR ALIGNMENT
4	(4)	CHARACTER	32	EISGENT(15)	STORAGE GROUP ENTRY ARRAY
4	(4)	SIGNED	2	EISGLEN	LENGTH OF STORAGE GROUP
NAME			'	•	·
6	(6)	CHARACTER	30	EISGNAM	NAME OF STORAGE GROUP
Note: THE FC	DLLOWING MA	APS THE RECORD PRES	SENTED BY	EXIT 23: DATA SET	PROCESSED NOTIFICATION EXIT.
0	(0)	STRUCTURE	*	EIREC23	
0	(0)	CHARACTER	141	EI23CNST	CONSTANT LENGTH PORTION OF CONTROL BLK
0	(0)	CHARACTER	44	EI23DSN	DATA SET/CLUSTER NAME
44	(2C)	CHARACTER	44	EI23NEWN	NEW DSET/CLUSTER NAME
88	(58)	SIGNED	2	EI23DSRC	RETURN CODE FOR DATA SET PROCESSING
90	(5A)	CHARACTER	5	EI23SFLG	SOURCE DATA SET FLAGS
90	(5A)	CHARACTER	1	E23SSMSF	SOURCE SMS FLAGS
91	(5B)	CHARACTER	2	E23SDSRG	SOURCE DATA SET ORG
93	(5D)	BITSTRING	2	E23SVFLG	SOURCE VSAM DSET FLAGS
		1		E23SESDS	1=ESDS DATA SET
		.1		E23SKSDS	1=KSDS DATA SET
		1		E23SKRDS	1=KRDS DATA SET
		1		E23SLDS	1=LINEAR DATA SET
		1		E23SRRDS	1=RRDS DATA SET
		1		E23SPSSI	1=PAGE/SWAP/STGINDEX, ETC. UNSUPPORTED DATA SETS
		1.		E23SVVDS	1=VVDS DATA SET
		1		E23SBCS	1=BCS DATA SET
	I	1 1		E23SAIX	1=AIX DATA SET
94	(5E)	1			
94	(5E)	.1		E23BCSEL	1=BASE CLUSTER SELECTED
94	(5E)			E23BCSEL E23SVRRD	1=BASE CLUSTER SELECTED VRRDS DATASET
94	(5E)	.1			
94	(5E)	.1 1		E23SVRRD	VRRDS DATASET
94 95	(5E) (5F)	.1 1 1	5	E23SVRRD EI23RRB	VRRDS DATASET RECOVERY REQUIRED
		.1 1 1 1111	5 1	E23SVRRD EI23RRB *	VRRDS DATASET RECOVERY REQUIRED UNUSED
95	(5F)	.1 1 1 1111 CHARACTER		E23SVRRD EI23RRB * EI23TFLG	VRRDS DATASET RECOVERY REQUIRED UNUSED TARGET DATA SET FLAGS
95 95	(5F) (5F)	.1 1 1 1111 CHARACTER CHARACTER	1	E23SVRRD EI23RRB * EI23TFLG E23TSMSF	VRRDS DATASET RECOVERY REQUIRED UNUSED TARGET DATA SET FLAGS TARGET SMS FLAGS
95 95 96	(5F) (5F) (60)	.1 1 1 1111 CHARACTER CHARACTER CHARACTER	1 2	E23SVRRD E123RRB * E123TFLG E23TSMSF E23TDSRG	VRRDS DATASET RECOVERY REQUIRED UNUSED TARGET DATA SET FLAGS TARGET SMS FLAGS TARGET DATA SET ORG
95 95 96	(5F) (5F) (60)	.111 1111 CHARACTER CHARACTER CHARACTER BITSTRING	1 2	E23SVRRD E123RRB * E123TFLG E23TSMSF E23TDSRG E23TVFLG	VRRDS DATASET RECOVERY REQUIRED UNUSED TARGET DATA SET FLAGS TARGET SMS FLAGS TARGET DATA SET ORG TARGET VSAM DSET FLAGS
95 95 96	(5F) (5F) (60)	.111 1111 CHARACTER CHARACTER CHARACTER BITSTRING 1	1 2	E23SVRRD E123RRB * E123TFLG E23TSMSF E23TDSRG E23TVFLG E23TESDS	VRRDS DATASET RECOVERY REQUIRED UNUSED TARGET DATA SET FLAGS TARGET SMS FLAGS TARGET DATA SET ORG TARGET VSAM DSET FLAGS 1=ESDS DATA SET
95 95 96	(5F) (5F) (60)	.111 1111 CHARACTER CHARACTER CHARACTER BITSTRING 11	1 2	E23SVRRD E123RRB * E123TFLG E23TSMSF E23TDSRG E23TVFLG E23TESDS E23TKSDS	VRRDS DATASET RECOVERY REQUIRED UNUSED TARGET DATA SET FLAGS TARGET SMS FLAGS TARGET DATA SET ORG TARGET VSAM DSET FLAGS 1=ESDS DATA SET 1=KSDS DATA SET

Table 38. ADREID0 Mapping Macro (continued)

Offs		пу масто (сопшией)			
Dec	Hex	Туре	Len	Name (Dim)	Description
		1		E23TPSSI	1=PAGE/SWAP/STGINDEX, ETC. UNSUPPORTED DATA SETS
		1.		E23TVVDS	1=VVDS DATA SET
		1		E23TBCS	1=BCS DATA SET
99	(63)		1	E23TAIX	1=AIX DATA SET
	, ,	.1		E23TVRRD	VRRDS DATASET
		11 1111		*	RESERVED
100	(64)	CHARACTER	16	EI23RLST	RLS TIME STAMPS
100	(64)	CHARACTER	8	EI23GMT	RLS GMT TIME STAMP
108	(6C)	CHARACTER	8	EI23LOC	RLS LOCAL TIME STAMP
116	(74)	CHARACTER	8	E23BYTES	DS BYTE COUNT
124	(7C)	CHARACTER	1	E23FLGS	MISC FLAGS
121	(, )	1	-	E23BSET	1=E23BYTES SET
		.1		E23BPDS	1=BROKEN PDS
		1		E23BPSE	E23BYTES IS FOR PSE
		1 1111		*	RESERVED
125	(7D)	CHARACTER	6	EI23DNAM	NAME OF DEVICE NEEDED TO DO
123	(7D)	CHARACIER	O	EIZODIVAIVI	NOPACKING FOR THE BROKEN PDS (I.E. A LIKE DEVICE)
131	(83)	CHARACTER	9	*	RESERVED
140	(8C)	UNSIGNED	1	EI23VOL#	NUMBER OF VOLUMES
141	(8D)	CHARACTER	6	EI23VSER (*)	VOLSER ARRAY
	` '			\ /	COPY INITIALIZATION COMPLETE.
0	(0)	STRUCTURE	83	EIREC24	
0	(0)	UNSIGNED	2	EI24RTCD	RETURN CODE
2	(2)	UNSIGNED	2	EI24RSCD	REASON CODE
4	(4)	UNSIGNED	4	*	RESERVED
8	(8)	CHARACTER	6	EI24VOL	VOLUME SERIAL
14	(E)	CHARACTER	44	EI24DSN	DATA SET NAME
58	(3A)	BITSTRING	1	EI24FLGS	FLAGS
	` ′	1		EI24RSET	DS CHANGE FLAG RESET
		.1		E24SAIX	1=AIX DATA SET
		1		E24BCSEL	1=BASE CLUSTER SELECTED
		1 1111		*	UNUSED
59	(3B)	CHARACTER	24	*	AVAILABLE
''	` ′			ı Exit 26: Dump Outpu	T VOLUME MOUNT NOTIFICATION
EXIT.					
0	(0)	STRUCTURE	128	EIREC26	
0	(0)	BITSTRING	4	EI26TYPE	EXIT TYPE
		1		EI26VOL	OUTPUT VOLUME NOTIFICATION
		.1		EI26TERM	OUTPUT VOLUME TERMINATED
		1		EI26R0CE	BWO R0 COUNT ERROR
		1		EI26VCLO	OUTPUT VOLUME CLOSE - ONLY FOR DASD OUTPUTS DURING
		1		EI26TWHE	LOGICAL DUMP OPERATIONS WHEN SET TO 1, TAPE DEVICE
					WILL BE ENCRYPTING DATA IN HARDWARE.
		XXX		3f-	UNUSED
0	(0)	BITSTRING	3	*	RESERVED FOR EXPANSION
4	(4)	CHARACTER	64	EI26DSN	DSNAME IF EI26ROCE = '1'B
68	(44)	UNSIGNED	1	EI26DSNL	LENGTH OF DSNAME
69	(45)	UNSIGNED	3	**	RESERVED FOR ALIGNMENT

Table 38. ADREID0 Mapping Macro (continued)

Off	sets	,			
Dec	Hex	Туре	Len	Name (Dim)	Description
72	(48)	CHARACTER	8	EI26DDN	OUTPUT DDNAME IF EI26VOL, EI26TERM, OR EI26VCLO SET
80	(50)	CHARACTER	6	EI26VSER	VOLSER - PRESENT IF EI26VOL, EI26TERM, EI26VCLO SET
86	(56)	CHARACTER	2	*	RESERVED FOR ALIGNMENT
88	(58)	UNSIGNED	4	EI26VTRC	RETURN FOR VOLUME TERM AND VOLUME CLOSE
92	(5C)	ADDRESS	36	*	RESERVED FOR EXPANSION
Note: THE FC EXIT.	OLLOWING MA	APS THE RECORD PRES	SENTED IN	EXIT 27: PHYSICAL	DATA SET PROCESSED NOTIFICATION
0	(0)	STRUCTURE	168	EIREC27	С
0	(0)	CHARACTER	44	EI27DSN	DATA SET/CLUSTER NAME
44	(2C)	CHARACTER	44	EI27NEWN	NEW DATA SET/CLUSTER NAME
88	(58)	SIGNED	2	EI27DSRC	RETURN CODE FOR DATA SET PROCESSING
90	(5A)	BITSTRING	5	EI27SFLG	SOURCE DATA SET FLAGS
90	(5A)	CHARACTER	1	E27SSMSF	SOURCE SMS FLAGS
91	(5B)	CHARACTER	2	E27SDSRC	SOURCE DATA SET ORG
93	(5D)	CHARACTER	2	E27SVFLG	VSAM DATA SET FLAGS:
		1		E27SESDS	1=ESDS DATA SET FOR PHYSICAL DATA SET COPY IF THE SOURCE DATA SET IS A KSDS AND THE VOLUME BEING PROCESSED IS NOT THE PRIMARY VOLUME AND THE INDEX FOR THAT KSDS DOES NOT RESIDE ON THE CURRENT VOLUME BEING PROCESSED, THIS BIT MAY BE ON BECAUSE IT APPEARS TO BE A ESDS
		.1		E27SKSDS	1=KSDS DATA SET
		1		E27SKRDS	1=KRDS DATA SET
		1		E27SLDS	1=LINEAR DATA SET
		1		E27SRRDS	1=RRDS DATA SET
		1		E27SPSSI	1=PAGE/SWAP/STGINDEX, ETC. UNSUPPORTED DATA SETS
		1.		E27SVVDS	1=VVDS DATA SET
		1		E27SBCS	1=BCS DATA SET
94	(5E)	1		E27SAIX	1=AIX DATA SET
		.1		E27BCSEL	1=BASE CLUSTER SELECTED
		1		E27SVRRD	VRRDS DATA SET A
		1 1111		EI27RRB *	RECOVERY REQUIRED RESERVED
95	(5F)	BITSTRING	5	EI27TFLG	TARGET DATA SET FLAGS
95	(5F)	CHARACTER	1	E27TSMSF	TARGET SMS FLAGS
96	(60)	CHARACTER	2	E27TDSRG	TARGET DATA SET ORG
98	(62)	CHARACTER	2	E27TVFLG	VSAM DATA SET FLAGS
		1		E27TESDS	1=ESDS DATA SET FOR PHYSICAL DATA SET COPY IF THE SOURCE DATA SET IS A KSDS AND THE VOLUME BEING PROCESSED IS NOT THE PRIMARY VOLUME AND THE INDEX FOR THAT KSDS DOES NOT RESIDE ON THE CURRENT VOLUME BEING PROCESSED, THIS BIT MAY BE ON BECAUSE IT APPEARS TO BE A ESDS
		.1		E27TKSDS	1=KSDS DATA SET

Table 38. ADREID0 Mapping Macro (continued)

Offs	sets	,			
Dec	Hex	Type	Len	Name (Dim)	Description
Dec	нех	Туре	Len	Name (Dim)	Description
		1		E27TKRDS	1=KRDS DATA SET
		1		E27TLDS	1=LINEAR DATA SET
		1		E27TRRDS	1=RRDS DATA SET
		1		E27TPSSI	1=PAGE/SWAP/STGINDEX, ETC. UNSUPPORTED DATA SETS
		1.		E27TVVDS	1=VVDS DATA SET
		1		E27TBCS	1=BCS DATA SET
99	(63)	1		E27TAIX	1=AIX DATA SET
		.1		E27TVRRD	1=VRRDS DATA SET
		1		E27TRACF	1=DATA SET IS PROTECTED BY DISCRETE RACF PROFILE
		1 1111		*	RESERVED
100	(64)	CHARACTER	8	EI27TRKS	TOTAL TRACKS COPIED
108	(6C)	CHARACTER	6	EI27SVOL	SOURCE VOLUME SERIAL
114	(72)	CHARACTER	6	EI27TVOL	TARGET VOLUME SERIAL
120	(78)	CHARACTER	2	E27FLGS	MISC FLAGS
		1		EI27LVOL	LAST VOLUME INDICATOR FROM THE SOURCE DATA SET
		.111 1111		*	RESERVED
121	(79)	CHARACTER	1		RESERVED
122	(7A)	SIGNED	2	EI27VLSQ	VOLUME SEQUENCE NUMBER FOR SOURCE DATA SET
124	(7C)	SIGNED	4	EI27DSHA	VSAM DATA COMPONENT ALLOCATED RBA COUNT
128	(80)	SIGNED	4	EI27ISHA	VSAM INDEX COMPONENT HIGH ALLOCATED RBA COUNT
132	(84)	SIGNED	2	EI27SCNT	VSAM DATA SET STRIPE COUNT
134	(86)	SIGNED	2	E27DSTP#	DATA COMPONENT STRIPE COUNT
Note: THE ELL ENDING RBA		EI27IRBA FIELDS ARE (	CALCULATE	D BY SUBTRACTING	THE STARTING RBA FROM THE
136	(88)	UNSIGNED	4	EI27DRBA	RBAS PROCESSED FOR THE DATA COMPONENT
140	(8C)	UNSIGNED	4	EI27IRBA	RBAS PROCESSED FOR THE INDEX COMPONENT
144	(90)	CHARACTER	44	EI27DANM	NEW DATA COMPONENT NAME
188	(BC)	CHARACTER	44	EI27IXNM	NEW INDEX COMPONENT NAME
232	(E8)				RESERVED
					A SET ALLOCATION NOTIFICATION
0	(0)	STRUCTURE	332	EIREC28	
0	(0)	BITSTRING	4	EI28PARMS1	EXIT 28 PARMS FIELD 1. ANY FIELD SET ON IDICATES THAT FIELD HAS BEEN SPECIFIED TO BE USED FOR THIS EXIT.
		1		EIOGE ATTED	THIS EXIT
		1 .1		EI28EATTRP	EATTR VALUE PASSED F9 DSCB PASSED
		1		EI28F9DSCBP EI28CREDTP	CREATION DATE PASSED
		1		EI28CKEDTP	CA RECLAIM ATTR PASSED
		1 XXXX		*	UNUSED
4	(4)	CHARACTER	4	EI28PARMS2	EXIT 28 PARMS FIELD 2
8	(8)	CHARACTER	44	EI28TGTDSN	TARGET DATA SET NAME
52	(34)	CHARACTER	44	EI28SRCDSN	SOURCE DATA SET NAME
96	(60)	CHARACTER	140	EI28F9DSCB	FORMAT 9 DSCB
236	(EC)	BITSTRING	140	EI28FIELDS1	EXIT 28 FIELDS 1. FLAG BYTE FOR
250	(EC)	DITOTIMING	1	2.1011111111111	BIT FIELDS.

Table 38. ADREID0 Mapping Macro (continued)

Offs	sets				
Dec	Hex	Type	Len	Name (Dim)	Description
		11		EI28EATTR	EATTR VALUE TO BE USED FOR TARGET DATASET ALLOCATION. '00'B = NS (DEFAULT VALUE USED) '01'B = NO '10'B = OPT
		1		EI28RCA	CA RECLAIM ATTR TO BE USED FOR TARGET DATASET ALLOCATION
	(77)	X XXXX	_		UNUSED
237	(ED)	CHARACTER	3	EI28CREDT *	CREATION DATE (DS1CREDT)
240	(F0)	CHARACTER	92		RESERVED
Note: THE FC	DLLOWING MA	APS THE RECORD PRES	SENTED BY E	XIT 30: PHYSICAL DA	TA SET ALTERNATE SMS VOLUME
0	(0)	STRUCTURE	*	EIREC30	
0	(0)	UNSIGNED	4	EI30TRKS	TRACKS REQUIRED
4	(4)	SIGNED	2	EI30RC	OVERALL EXIT RETURN CODE
6	(6)	CHARACTER	2	*	RESERVED
8	(8)	CHARACTER	4	EI30VSER@	POINTER TO VOLUME STRUCTURE
Note: THE FC	LLOWING MA	APS THE VOLUME STR	UCTURE	1	·
0	(0)	STRUCTURE	*	EI30VLIST	VOLUME LIST
0	(0)	SIGNED	2	EI30VOL#	NUMBER OF VOLUME ENTRIES
2	(2)	CHARACTER	2	*	RESERVED
4	(4)	STRUCTURE	*	EI30VOLENT(16)	VOLUME ENTRY ARRAY
4	(4)	CHARACTER	6	EI30VSER	VOLSER
10	(A)	CHARACTER	1	EI30VFLG	VOLUME FLAGS
	\	1		EI30ATT	ALLOCATION ATTEMPTED
		.1		EI30USED	VOLUME USED
		11 1111		*	RESERVED
11	(B)	CHARACTER	1	*	RESERVED
12	(C)	SIGNED	4	EI30VRC	VOLUME RETURN CODE
16	(10)	SIGNED	4	EI30VRSN	VOLUME REASON CODE
	(10)	5151,22			

## **Constants for ADREID0**

The following shows the length, type, value, name and description for each constant:

```
4 CHARACTER EIDB ADREIBID BLOCK IDENTIFIER
2 DECIMAL O EIRCOO CONTINUE NORMAL PROCESS
2 DECIMAL 4 EIRCO4 RECORD REPLACED
2 DECIMAL 8 EIRCO8 INSERT RECORD
2 DECIMAL 12 EIRC12 DELETE RECORD
2 DECIMAL 16 EIRC16 RECORD MODIFIED
2 DECIMAL 20 EIRC20 DISCONNECT EXIT
2 DECIMAL 24 EIRC24 SELECT USER STATS RECS
2 DECIMAL 28 EIRC28 WTOR RESPONSE
2 DECIMAL 32 EIRC32 TERMINATE FUNCTION
2 DECIMAL 36 EIRC36 TERMINATE DSET ONLY
2 DECIMAL 0 EIOPOO FUNCTION STARTUP ENTRY
2 DECIMAL 1 EIOPO1 READING SYSIN RECORD
2 DECIMAL 2 EIOPO2 PRINTING SYSPRINT RECORD
2 DECIMAL 3 EIOPO3 READING PHYSICAL TAPE
2 DECIMAL 4 EIOPO4 READING LOGICAL TAPE
2 DECIMAL 5 EIOPO5 WRITING LOGICAL TAPE
2 DECIMAL 6 EIOPO6 WRITING PHYSICAL TAPE
2 DECIMAL 7 EIOPO7 READING DISK TRACK
2 DECIMAL 8 EIOP08 WRITING DISK TRACK
```

2 DECIMAL 9 EIOPO9 READING UTILITY SYSPRINT 2 DECIMAL 10 EIOP10 WRITING UTILITY SYSPRINT

```
2 DECIMAL 11 EIOP11 WRITING WTO MESSAGE
2 DECIMAL 12 EIOP12 WRITING WTOR MESSAGE
2 DECIMAL 13 EIOP13 PRESENTING ADRUFO REC
2 DECIMAL 14 EIOP14 FUNCTION TERMINATION
2 DECIMAL 15 EIOP15 PRESENTING WTOR RESPONSE
2 DECIMAL 16 EIOP16 TAPE VOL SECURITY
2 DECIMAL 17 EIOP17 TAPE MOUNT(NON-SPEC)
2 DECIMAL 18 EIOP18 INSERT LOGICAL REC
2 DECIMAL 19 EIOP19 TAPE OUTPUT ERROR
2 DECIMAL 20 EIOP20 VOLUME NOTIFICATION
2 DECIMAL 21 EIOP21 DSET VERIFICATION
2 DECIMAL 22 EIOP22 BYPASS VERIFICATION
2 DECIMAL 23 EIOP23 DS PROC NOTIFICATION
2 DECIMAL 708 VOLSLST MAX SIZE OF VOLSER LIST FOR EIREC23 (118
2 DECIMAL 24 EIOP24 CC INIT DONE
2 DECIMAL 25 EIOP25 BACKSPACE TAPEIN
2 DECIMAL 26 EIOP26 VOLUME OPEN FOR O/P
2 DECIMAL 27 EIOP27 PHYSICAL DS PROCESSED
2 DECIMAL 28 EIOP28 TARGET ALLOCATION EXIT
2 DECIMAL 29 EIOP29 RESERVED
2 DECIMAL 30 EIOP30 RESERVED
2 DECIMAL 30 EIMAXOP MAXIMUM VALID EXIT NUMBER
2 DECIMAL 48 EXITRECL EXIT RECORD LEN
CONSTANTS FOR SERIALIZATION ERROR ACTIONS
1 DECIMAL 0 EISRLNONE USE NONE
1 DECIMAL 1 EISRLDB2 USE DB2
1 DECIMAL 2 EISRLZFS USE ZFS
1 DECIMAL 3 EISRLCICS USE CICS
1 DECIMAL 4 EISRLEXIT USE USER EXIT
4 DECIMAL 42 EIDBLEN LENGTH OF BLOCK
2 BIT 00 EI28EATTR NS EATTR NOT SPECIFIED CONSTANT
2 BIT 01 EI28EATTR_NO EATTR NO CONSTANT
2 BIT 10 EI28EATTR_OPT EATTR NO CONSTANT
```

#### Cross reference for ADREID0

ADREIB 0 EIDDID 22 EIDDINFO 0 EIDDNAME 0 EIDLLEN 0 EIID 2 EIOPTION E EIRECALN 12 EIRECLEN 16 EIRECPTR 1A EIREC00 0 EIREC14 0 EIREC20 0 EIREC21 0 EIREC22 0 EIREC23 0 EIREC24 0 EIREC26 0 EIREC27 0 EIREC28 0 EIRETC E EIRETCOD 10 EISGCNT 0 EISGENT 4 EISGHDR 0 EISGLEN 4 EISGLIST 0

EISGNAM 6 EITSKID 6 EIUSEPTR 1E EIVOLID 8 EIXABEND 26 EIXALLOW A EIXALOWO A EIXALOW1 B EIXALOW2 C EIXALOW3 D EIXDASYS 27 EIXDEL A EIXDIS A EIXERR D EIXFLAGS 26 EIXFLAGO 26 EIXFLAG1 27 EIXFLAG2 28 EIXFLAG3 29 EIXINS A EIXMOD A EIXMWPL 22 EIXNTERR 26 EIXREP A EIXSTAT A EIXTDSET B EIXTDUMS 27 EIXTDUMT 27 EIXTERM A EIXTISXM 27 EIXTRC32 27 EIXTRERR 27 EIXTRKER 26 EIXTWERR 27 EIXWNGOK 26 EIXWTOR A EIOOBSEC 1 EIOOBSER 1 EIOOCANSFE 8 EIOOFLGS 1 EI00FLG2 8 EI00MIXDEV 8 EIOOMVOLRECOV 1 EIOONENQ 1 EIOONOLK 1 EIOONONF 1 EI00SBPL 0 EIOOSENQ 1 EIOOSVOL 2 EIOOSWNCRYPT 8 EI06DCB@ 10 EI06FLGS F EI06FTLR F EI06THWE F EI14CPUT 8 EI14MESS 4 EI14MNUM 4 EI14MTYP 7 EI14RC 0 EI20CON 0 EI20DA# 2E EI20DA@ 30 EI20DRBA 3C EI20DSHA 3C EI20DSI 0 EI20DSN 0 EI20FLGS 2C

EI20ISHA 40 EI20IX# 2F EI20IX@ 34 EI20LVOL 2C EI20NVOL 2C EI20RACF 2C EI20RBA 38 EI20SCNT 3A EI20VLI 30 EI20VLSQ 40 EI20V0L 30 EI20VSAM 2C EI21DSN 0 EI22ACSEN 50 EI22BMIG 2C EI22BRLS 4E EI22BSEC 2C EI22BSER 2C EI22BWOA 4E EI22BW0E 32 EI22BWOP 32 EI22DB2 2C EI22DSN 0 EI22EXTR 2C EI22FLGS 2C EI22FLG2 32 EI22FLG3 4E EI22IMS 32 EI22LIKE 2C EI22LINF 32 EI22LPRM 33 EI22LSID 34 EI22NSYS 2C EI22RRB 32 EI22RSET 32 EI22SFLG 2D EI22SFSM 4E EI22SGP 58 EI22SIRS 2C EI22SSYS 32 EI23CNST 0 EI23DNAM 7D EI23DSN 0 EI23DSRC 58 EI23GMT 64 EI23LOC 6C EI23NEWN 2C EI23RLST 64 EI23RRB 5E EI23SFLG 5A EI23TFLG 5F EI23VOL# 8C EI23VSER 8D EI24DSN E EI24FLGS 3A EI24RSCD 2 EI24RSET 3A EI24RTCD 0 EI24VOL 8 EI26DDN 48 EI26DSN 4 EI26DSNL 44 EI26R0CE 0 EI26TERM 0 EI26THWE 0 EI26TYPE 0 EI26VCLO 0

EI26VOL 0 EI26VSER 50 EI26VTRC 58 EI27CNST 0 EI27DRBA 88 EI27DSHA 7C EI27DSN 0 EI27DSRC 58 EI27IRBA 8C EI27ISHA 80 EI27LVOL 78 EI27NEWN 2C EI27RRB 5E EI27SCNT 84 EI27SFLG 5A EI27SVOL 6C EI27TFLG 5F EI27TRKS 64 EI27TVOL 72 EI27VLSQ 7A EI28CREDT ED EI28CREDTP 0 EI28EATTR EC EI28EATTRP 0 EI28FIELDS1 EC EI28F9DSCB 60 EI28F9DSCBP 0 EI28PARMS1 0 EI28PARMS2 4 EI28RCA EC EI28RCAP 0 EI28SRCDSN 34 EI28TGTDSN 8 E20F9ATT 2C E22SAIX 31 E22SBCS 30 E22SDSRG 2E E22SESDS 30 E22SKRDS 30 E22SKSDS 30 E22SLDS 30 E22SPSSI 30 E22SRRDS 30 E22SSMSF 2D E22SVFLG 30 E22SVRRD 31 E22SVVDS 30 E23BCSEL 5E E23BPDS 7C E23BPSE 7C E23BSET 7C E23BYTES 74 E23FLGS 7C E23F9ATT 7C E23SAIX 5E E23SBCS 5D E23SDSRG 5B E23SESDS 5D E23SKRDS 5D E23SKSDS 5D E23SLDS 5D E23SPSSI 5D E23SRRDS 5D E23SSMSF 5A E23SVFLG 5D E23SVRRD 5E

E23SVVDS 5D

E23TAIX 63 E23TBCS 62 E23TDSRG 60 E23TESDS 62 E23TKRDS 62 E23TKSDS 62 E23TLDS 62 E23TPSSI 62 E23TRRDS 62 E23TSMSF 5F E23TVFLG 62 E23TVRRD 63 E23TVVDS 62 E24BCSEL 3A E24SAIX 3A E27BCSEL 5E E27DSTP# 86 E27FLGS 78 E27F9ATT 78 E27SAIX 5E E27SBCS 5D E27SDSRG 5B E27SESDS 5D E27SKRDS 5D E27SKSDS 5D E27SLDS 5D E27SPSSI 5D E27SRRDS 5D E27SSMSF 5A E27SVFLG 5D E27SVRRD 5E E27SVVDS 5D E27TAIX 63 E27TBCS 62 E27TDSRG 60 E27TESDS 62 E27TKRDS 62 E27TKSDS 62 E27TLDS 62 E27TPSSI 62 E27TRACF 63 E27TRRDS 62 E27TSMSF 5F E27TVFLG 62 E27TVRRD 63 E27TVVDS 62

# Example: invoking DFSMSdss by using an application program

The following example shows that a full DASD volume is to be dumped to a tape volume or volumes. DFSMSdss is LINKed somewhere in MYJOB to perform the dump, and, conditionally, the DEFRAG functions.

```
//J0B1
          JOB accounting information, REGION=nnnnK
//STEP1
          EXEC PGM=MYJOB
//STEPLIB DD
                DSN=MY.LINKLIB,DISP=SHR
//SYSPRINT DD
                SYSOUT=A
          DD UNIT=3380, VOL=(PRIVATE, SER=111111), DISP=OLD
//DASD
                UNIT=3480, VOL=SER=(TAPE01, TAPE02),
//TAPE
          DD
// LABEL=(1,NL),DISP=(NEW,KEEP)
//SYSIN
         DD
  DUMP INDD(DASD) OUTDD(TAPE)
  IF LASTCC = 0 -
     THEN DEFR DDN(DASD)
```

The preceding example does not show how the invocation of DFSMSdss was brought about, but does show that the user program, MYJOB, was run. At some point MYJOB needs to run DFSMSdss to perform the functions specified in the SYSIN data set. The next example shows the code needed at that point to LINK to DFSMSdss. Because no EXEC PARMs were specified and the standard SYSIN and SYSPRINT data set names are to be used, there is no need to pass special parameters.

```
LINK EP=ADRDSSU, PARAM=(OPTPTR), VL=1
         CNOP 2,4
OPTPTR
        DC
            H(0)
```

**Related reading:** For additional information about the Application Interface, see Chapter 23, "Examples of the application program with the user interaction module (UIM)," on page 625.

## How to determine DFSMSdss version, release, and modification level

Subsystems that invoke DFSMSdss dynamically must determine if DFSMSdss is installed on the system, and if it is, its version, release, and modification level, and features supported. A DFSMSdss-provided macro tries to determine the DFSMSdss version, release, and modification level and features supported and pass the requested information in a register.

ADRMCLVL (in SYS1.MACLIB) is an in-line executable assembler-language macro that can be invoked by a caller. The caller can be in problem program state and can have a user key. The caller must save registers 0, 1, 14, and 15 before invoking the macro. No other registers are disturbed. The caller can determine the installed level and features of DFSMSdss from the information returned in registers 1 and 14.

On return, register 1 contains information as follows:

- If the release level of ADRDSSU cannot be determined, register 1 contains X'04000000'.
- Otherwise, register 1 contains:

```
Byte 0 Product number, in binary:
            0 = DFDSS
            2 = MVS \text{ or } OS/390 \text{ DFSMSdss}
```

```
3 = z/OS DFSMSdss
```

#### Byte 1

Version number, in binary:

1 = Version 1

2 = Version 2

#### Byte 2

When byte 0 is 0 or 2:

- Release number, in binary:

1 = Release 1

2 = Release 2

3 = Release 3

4 = Release 4

5 = Release 5

A = Release 10

#### When byte 0 is 3:

- Release number, in decimal:

01 = Release 1

02 = Release 2

03 = Release 3

04 = Release 4

05 = Release 5

10 = Release 10

11 = Release 11

12 = Release 12

#### Byte 3 Modification level, in binary:

0 = Modification level 0

1 = Modification level 1

2 = Modification level 2

On return, register 14 contains the following information:

- If the release level of ADRDSSU is less than DFSMSdss Version 1, Release 4, Modification level 0, then the contents of register 14 are unpredictable.
- Otherwise, register 14 contains the following:

#### Byte 0 Feature Flags:

Bit 0, when set to 1, means DFSMSdss cross-memory Application Programming Interface support for concurrent copy is available.

Bit 1, when set to 1, means the PTF that introduced the ZCOMPRESS keyword support (OA42238) is applied.

Bits 2–7 are reserved.

### Bytes 1-3

Reserved.

# Chapter 23. Examples of the application program with the user interaction module (UIM)

This topic contains General-use Programming Interface and Associated Guidance information, and Product sensitive Programming Interface information.

Figure 26 shows the process by which DFSMSdss can call user interaction module (UIM) functions.




Figure 26. The Application Program Process

This topic contains the following examples:

- The JCL to invoke an application program that invokes DFSMSdss
- A complete sample program listing showing how a user can use all of the UIM exit functions to receive control from DFSMSdss (Figure 27 on page 626 and Figure 30 on page 629)
- An output listing (Figure 41 on page 640) resulting from the sample program in Figure 27 on page 626 and Figure 30 on page 629

**Note:** The example shown is not written in reentrant code. If you are planning to share a UIM between tasks, you should code the module in reentrant code.

The example has not been submitted to any formal test and is distributed as it is, without any warranty either expressed or implied. The use of this example or the implementation of these techniques is a customer responsibility and depends on the customer's ability to evaluate and integrate them into the customer's operational environment. Although each item may have been reviewed by IBM for accuracy in a specific situation, there is no guarantee that the same or similar results will be obtained elsewhere. Customers attempting to adapt these techniques to their own environment do so at their own risk.

The following JCL was used to invoke an application program, which then called DFSMSdss.

```
//STEPS014 EXEC PGM=USRAIPGM
//STEPLIB DD DISP=SHR,DSN=SYS1.LINKLIB
//SYSPRINT DD SYSOUT=*
//DASD DD UNIT=SYSDA,VOL=SER=D9S060,DISP=SHR
//TAPE DD DD DISP=(,CATLG),DSN=PUBSEXMP.DUMP,
// UNIT=3390,VOL=SER=DAVIS4,
// SPACE=(CYL,(10,10),RLSE)
//MYDATA DD *
EOJ
/*
```

```
= USRAIPGM
* Module Name
* Descriptive Name = DFSMSdss Application Interface Program Example
                = Invoke DFSMSdss supplying alternate UIM: USRUIM
* Function
                                 or
                = Invoke DFSMSdss Cross Memory Application
Interface UIM: USRUIM
    Operation
               = Place SYSIN records in the user area. The UIM
                  will pass these records to DFSMSdss.
USRAIPGM CSECT
USRAIPGM AMODE 31
USRAIPGM RMODE ANY
*****************
* Standard entry linkage
********
       STM 14,12,12(13)
        BALR 12,0
        USING *,12
        LA
            3,SAVEAREA
        ST
             3,8(13)
        ST
        LR
            13,3
******************
\star Load and call DFSMSdss
        LOAD EP=ADRDSSU
        CNOP 0,4
                                                        @YA29363 01-LOAD
        LA 0,*+8
                             LOAD PARAMETER INTO REGISTER ZERO
                              BRANCH AROUND CONSTANT(S)
                                                                01-L0AD
        DC
             CL8'ADRDSSU'
                             ENTRY POINT NAME
                                                                01-LOAD
        \mathsf{SR}
                             SHOW NO DCB PRESENT
                                                                01-L0AD
             1,1
        SVC
                                                                01-L0AD
        LR
             15,0
             3,USERAREA
        LA
             3,UA@
        ST
```

Figure 27. Application Interface Program Example

```
CALL (15), (OPTPTR, DDNPTR, PAGEPTR, UIMPTR, UAPTR), VL
                                                          01-CALL
       CNOP
                                                           02-IHBOP
                                        LIST ADDRESS @L1C 02-IHBOP
       LA
            1,IHB0003
       В
            IHB0003A
                                        BYPASS LIST @ZMC3742 02-IHBOP
+IHB0003 EQU
                                                          02-IHBOP
            A(OPTPTR)
                            PROB.PROG.PARAMETER
                                                          02-IHBOP
            A (DDNPTR)
                            PROB.PROG.PARAMETER
                                                          02-IHBOP
       DC
            A (PAGEPTR)
                            PROB.PROG.PARAMETER
                                                          02-IHBOP
                      PROB.PROG.PARAMETER
                                                          02-IHBOP
       DC
            A(UIMPTR)
            A(UAPTR+X'80000000')
                                                   @G860P40 02-IHB0P
       DC
+IHB0003A EQU
                                                          02-IHBOP
                                       BRANCH TO ENTRY POINT 01-CALL
       BALR 14,15
* Load and call DFSMSdss Cross Memory Application Interface
       LOAD EP=ADRXMAIA
       LR
            15,0
            3,USERAREA
       LA
       ST
            3.UA@
       CALL (15), (OPTPTR, DDNPTR, PAGEPTR, UIMPTR, UAPTR, ASNPTR). VL
*****************
* Standard exit linkage
***********************
            13,4(13)
       RETURN (14,12),,RC=(15)
       L 14,12(0,13)
LM 0,12,20(13)
BR 14
                                       RESTORE REG 14 @L1C 01-RETUR
                                    RESTORE THE REGISTERS 01-RETUR
RETURN 01-RETUR
************************
* Option area (same format as EXEC parameters)
*********************
       CNOP 2,4
OPTPTR DC AL2(OPTLEN)
OPTIONS DC C'SIZE=4096
            C'SIZE=4096K,TRACE=YES'
OPTLEN EQU *-OPTIONS
*************************
* DDNAME area (SYSIN is replaced by MYDATA)
**********************
       CNOP 2.4
DDNPTR
       DC
            AL2 (DDNLEN)
DDNAMES DC
            XL8'00'
       DC
            XL8'00'
       DC
            XL8'00'
            XL8'00'
       DC
            CL8'MYDATA'
            CL8'SYSPRINT'
       DC
DDNLEN EQU
           *-DDNAMES
******************
* Page number area (first page will be 1)
       CNOP 2,4
PAGEPTR DC AL2 (PAGELEN)
PAGENO DC
            CL4'0001'
PAGELEN EQU *-PAGEPTR
```

Figure 28. Application Interface Program Example (continued)

## UIM

```
* User Interaction Module area (UIM is called USRUIM)
        CNOP 2,4
UIMPTR DC
             AL2(UIMLEN)
            CL8'USRUIM'
UIMLEN EQU *-UIM
********
* User area pointer area
        CNOP 2,4
UAPTR
             AL2(UALEN)
UA@
       DS
UALEN
       EQU *-UA@
*********************
* User area
                                  Length of first command
USERAREA DC AL1(COM1)
            C' WTO ''USRAIPGM INVOKING DFSMSdss'''
       DC
        EQU *-USERAREA-1
COM1
            AL1(COM2) Length of first command
C' DUMP DS(EXC(SYS1.**)) LOGINDD(DASD) OUTDD(TAPE)'
SECNDCOM DC
       DC
            *-SECNDCOM-1
COM2
        EQU
            AL1(COM3)
C' IF LASTCC=0 -'
*-THIRDCOM-1
THIRDCOM DC
                                  Length of third command
       DC
COM3
        EQU
             AL1(COM4) Length
C' THEN DEFRAG DDN(DASD)'
                                  Length of fourth command
FOURCOM DC
       DC
COM4 EQU *-FOURCOM-1
ENDCOMM DC X'00'
                                   End of command flag
***********
* Register save area
            18F
SAVEAREA DS
        END
```

Figure 29. Application Interface Program Example (continued)

М	odule Name	= USRUIM	*	к *		
			*	k		
D	escriptive Name	= DFSMSdss User Interaction Module Example	*	*		
F	unction	= Perform various functions at different exit	*	k		
		points.	*	k		
	Exit Point	Operation	*	*		
			*	k		
r	0	Initialize counters for task	*	k		
k	1	Insert SYSIN records from user area	*	k		
k	2	Insert table of accounting data	*	k		
k k	3	Count Tape Blocks Read	*			
k k	5	Count Logical Tape Blocks Read Count Logical Tape Blocks Written	*	r -		
r k	6	Count Tape Blocks Written	· .			
r k	7	Count DASD Tracks Read	*	*		
*	8	Count DASD Tracks Written	*	k		
*	9	Nothing	*	k		
*	10	Nothing	*	k		
k	11	Insert a WTO message	*	k		
k	12	Never allow ADR369D	*	k		
*	13	Force Reblocking	*	k		
*	14	Convert counts to printable characters	*	k		
*	15	Nothing	*			
*	16	Always bypass password protection for tape	*			
*	17 18	Supply TAPE01 as a tape volser Nothing	*	r -		
*	19	Save Tape DDNAME and volser which had error	*	*		
*	20	Save Data Set name	*	*		
*	21	Do not process temporary data sets	*	k		
*	22	Bypass serialization of SYS1 data sets	*	k		
*	23	End function if processing errors	*	k		
k	24	End function if initialization fails	*	k		
*			*	k		
*	25	Nothing	*	k		
*	26	Nothing	*	k		
* USR USR USR	UIM CSECT UIM AMODE 31 UIM RMODE ANY	**********				
	egisters with sp		*			
	•	******************	***			
k						
ΞID	BASE EQU 2	Base reg for ADREIB.				
DPT	ION EQU 3	Reg to test option				
WOR.	KREG EQU 4	Work register				
	GTH EQU 5	Reg to get length of record				
	PBASE EQU 6	Temporary base reg for exit	ts			
RC	EQU 7	Register for return code				
	PBASE EQU 8	Register for sysprint recs	.1.			
	OFF EQU 9	Register for offsets to tab				
			***			
		d Establish Addressability.	***			
	USING *,15					
	STM 14,1					
	U.II 17,1					

Figure 30. User Interaction Module Example

```
BALR 12,0
                               New base addressability
       USING *,12
       DROP 15
            BEGIN
       DC
            CL16'CSECT - USRUIM'
********************
* Establish Addressability to EIDB
******************
                       Save caller SA pointer
BEGIN
            13, SAVEAREA
       LA
                                Set my SA pointer
            15, SAVEAREA+4
                               Backward Chain
       ST
            BEGIN
       ST
            13,8(15)
                                Forward Chain
       USING ADREIB, EIDBASE
                                Addressability to EIDB
            EIDBASE,0(,1)
                                Address of EIDB
            OPTION, EIOPTION
                                Get DFSMSdss processing option
       SLL
            OPTION,2
                                Multiply times four
                                Point to vector table start
            15, VECTABLE
       LA
            15,0(OPTION,15)
                                Point to processor routine
       BALR 14,15
                                Go to processor routine
            13,SAVEAREA+4
                                Restore SA pointer
                                Return to DFSMSdss
       RETURN (14,12)
                                 RESTORE THE REGISTERS 01-RETURN
       LM
            14,12,12(13)
       BR
                                 RFTURN
                                                     01-RFTURN
            14
*******************
* Processing Routines
********************
******************
* AIOPT00: Function Startup
 Initialize counters for tape and dasd accounting.
* Insert message identifying task into table
********************
            RTBCNT, RTBCNT
AIOPTOO XC
                                Init Tape Blocks Read
            WTBCNT,WTBCNT
       XC
                                Init Tape Blocks Written
                            Init Log Tape Blocks Read
       XC
            RLTBCNT, RLTBCNT
       XC
            WLTBCNT, WLTBCNT
                                Init Log Tape Blocks Written
       XC.
            RDTCNT, RDTCNT
                                Init Disk Tracks Read
       XC
            WDTCNT, WDTCNT
                                Init Disk Tracks Written
       ICM
            WORKREG, 15, EITSKID
                                Get current task identifier
       CVD
            WORKREG, CVDWORK
                                Convert to decimal
            OPTOOTSK(2),CVDWORK+6(2) Unpack into message insert
       UNPK
       01
            OPTOOTSK+1,X'F0'
                                Make last character printable
            MSGOFF, MSGCOUNT
                                Get current MSGCOUNT
       МН
            MSGOFF, MSGLEN
                                Multiply by MSGLEN to get
            WORKREG, MSGTABLE
                                offset into message table
            TEMPBASE, 0 (MSGOFF, WORKREG)
       USING TABLEMAP, TEMPBASE
            TABENTRY(133), OPTOOMSG Move into msgtable
       DROP TEMPBASE
            WORKREG, MSGCOUNT
                                Increment MSGCOUNT
            WORKREG, 1 (WORKREG)
       ST
            WORKREG, MSGCOUNT
                                Save new count
            RC,EIRC00
                                Set normal process retcode
       STH
            RC, EIRETCOD
                                Store retcode in EIDB
       BR
                                Return to intercept processor
*****************
* AIOPTO1: Read SYSIN Record
   Get SYSIN records from the user area and give them to DFSMSdss *
   using the Insert Record return code.
*******************
```

Figure 31. User Interaction Module Example (continued)

```
AIOPT01 TM
              SYSINFL, SYSIFRST
                                      Q. First entry to SYSIN exit?
         ВО
              NXTSYS
                                      A. No, get next input
               SYSINFL, SYSIFRST
                                       Indicate first time taken
         01
              TEMPBASE, 15, EIUSEPTR
                                      Get address of UA
         ICM
         ST
               TEMPBASE, CURCOMM
                                       Save pointer to first record
NXTSYS
               TEMPBASE, CURCOMM
                                      Get current command pointer
         LA
               WORKREG, 1 (, TEMPBASE)
                                      Get past length
         STCM
              WORKREG, 15, EIRECPTR
                                      Initialize the pointer
               LENGTH, LENGTH
                                       Clear workreg
         IC
              LENGTH, 0 (, TEMPBASE)
                                      Get length of record
         LTR
              LENGTH, LENGTH
                                      Q. End of SYSIN data?
         ΒZ
               SYSDEL
                                      A. Yes, bypass SYSIN DS
         STCM
              LENGTH, 15, EIRECLEN
                                       Set record length
               TEMPBASE,1(LENGTH, TEMPBASE) Point to new record
         LA
         ST
              TEMPBASE, CURCOMM
                                      Save new pointer
         LH
              RC,EIRC08
                                       Set insert record retcode
         В
              SYSEXIT
                                      Continue setup
SYSDEL
        ICM
              LENGTH, 15, EIRECLEN
                                      Get current record length
              LENGTH, LENGTH
                                      Q. EOF condition ? (reclen=0)
         LTR
              SYSRC00
                                      A. Yes, process it.
         BZ
              RC.EIRC12
        LH
                                      Set delete record retcode
              SYSEXIT
         В
                                      Continue Setup
SYSRC00 LH
              RC,EIRC00
SYSEXIT STH
                                      Store retcode in FIDB
              RC, EIRETCOD
        BR
              14
                                      Return to intercept processor
********************
* AIOPTO2: Write SYSPRINT
* Insert SYSPRINT records before message ADR012I
********************
AIOPTO2 ICM SYSPBASE, 15, EIRECPTR
        USING SYSPMAP, SYSPBASE
                                      Q. Last SYSPRINT rcd?
         CLC
              MSGID(8),ADR012I
         BNE
              NOTLAST
                                      A. No, don't insert records
              SYSPRFL, INSDONE
         TM
                                      Q. Are we done inserting?
         RΩ
              NOTLAST
                                      A. Yes, don't insert records
              WORKREG, INSERTCT
         I R
              MSGOFF, WORKREG
                                      Save INSERTCT for offset
         LA
              WORKREG, 1 (WORKREG)
                                      Increment INSERTCT and
               WORKREG, MSGCOUNT
                                      Q. Have we printed all rcds?
         BNH
              INSERT
                                       A. No, insert another record
         01
              SYSPRFL, INSDONE
                                       Indicate we are done insert
              WORKREG, TRAILER
                                       Point to trailer record
         STCM
              WORKREG, 15, EIRECPTR
                                       Store into EIRECPTR
         LH
              WORKREG, MSGLEN
                                      Update EIRECLEN
         STCM
              WORKREG, 15, EIRECLEN
              RC,EIRC08
                                       Set insert record retcode
         LH
               SYSPEXIT
INSERT
        MH
              MSGOFF, MSGLEN
                                      Multiply by MSGLEN to get
               WORKREG, MSGTABLE
         LA
                                      offset into message table
               WORKREG, 0 (MSGOFF, WORKREG)
         LA
         STCM
              WORKREG, 15, EIRECPTR
                                       Store address in EIRECPTR
         LH
               WORKREG, MSGLEN
         STCM
              WORKREG, 15, EIRECLEN
                                       Store length in EIRECLEN
               WORKREG, INSERTCT
                                       Increment MSGCOUNT
         LA
               WORKREG, 1 (WORKREG)
         ST
               WORKREG, INSERTCT
                                       Save new count
         LH
              RC,EIRC08
                                       Set insert record retcode
               SYSPEXIT
         В
NOTLAST LH
               RC, EIRC00
                                       Set normal process retcode
SYSPEXIT STH
              RC.EIRETCOD
                                       Store retcode in EIDB
                                      Return to intercept processor
```

Figure 32. User Interaction Module Example (continued)

******	*******	******
	ad Tape Block Exit	*
	e Block records read	*************
AIOPTO3 LH LA STH	WORKREG,RTBCNT WORKREG,1(WORKREG) WORKREG,RTBCNT	Increment Read Tape Block count
LH STH BR	RC,EIRCOO RC,EIRETCOD 14	Set normal process retcode Store retcode in EIDB
		Return to intercept processor
	ad Logical Tape Block E	
	ical Tape Block records	read *
AIOPT04 LH LA STH	WORKREG,RLTBCNT WORKREG,1(WORKREG) WORKREG,RLTBCNT	Increment Read logical Tape Block count
LH STH	RC,EIRCOO RC,EIRETCOD	Set normal process retcode Store retcode in EIDB
BR	14	Return to intercept processor
******	*******	*******
	ite Logical Tape Block	
	ical Tape Block records *******	**********
AIOPTO5 LH LA STH	WORKREG,WLTBCNT WORKREG,1(WORKREG) WORKREG,WLTBCNT	Increment Write logical Tape Block count
LH STH	RC,EIRCÓO RC,EIRETCOD	Set normal process retcode Store retcode in EIDB
BR	14	Return to intercept processor
	ite Tape Block Exit	*
	e Block records written	
AIOPTO6 LH	**************************************	**************************************
LA STH	WORKREG, 1 (WORKREG) WORKREG, WTBCNT	Tape Block count
LH STH	RC,EIRCOO RC,EIRETCOD	Set normal process retcode Store retcode in EIDB
BR *	14	Return to intercept processor
*****	*******	*******
* Count DASI	ad DASD Track Exit D Tracks read	*
**************************************		**************************************
LA STH	WORKREG,RDTCNT WORKREG,1(WORKREG) WORKREG,RDTCNT	Increment Read DASD Track count
LH	RC,EIRCOO	Set normal process retcode
STH BR	RC,EIRETCOD 14	Store retcode in EIDB Return to intercept processor
		********
* Count DAS	ite DASD Track Exit D Tracks written	* * *********
AIOPTO8 LH LA STH	WORKREG, WDTCNT WORKREG, 1 (WORKREG) WORKREG, WDTCNT	Increment Write DASD Track count
LH STH BR	RC,EIRCOO RC,EIRETCOD	Set normal process retcode Store retcode in EIDB Return to intercept processor

Figure 33. User Interaction Module Example (continued)

```
* AIOPTO9: Read Utility SYSPRINT
*******************
             RC,EIRC00 Set normal process retcode RC,EIRETCOD Store retcode in EIDB
AIOPTO9 LH
       STH RC, EIRETCOD
       BR 14
                                Return to intercept processor
* AIOPT10: Write SYSPRINT Record
******************
AIOPT10 LH RC,EIRC00 Set normal process retcode
STH RC,EIRETCOD Store retcode in EIDB
BR 14 Return to intercept processor
*******************
* AIOPT11: Write WTO Message
 Delete the WTO and insert my own
****************
       LH WORKREG,WTOCT Check WTO count
LTR WORKREG,WORKREG Q. Is WTOCT 0?
BZ OPT11INS A. Yes, insert of
LH RC,EIRC12 Set delete recor
AIOPT11 LH
                                  A. Yes, insert one
OPT11DEL LH
                                  Set delete record retcode
             OPT11XIT
       В
                                  (delete all other WTOs)
             WORKREG,1(WORKREG) Increment WTOCT
OPT11INS LA
        STH
             WORKREG, WTOCT
             WORKREG, UIMWTO
                                  Get address of WTO
        ΙA
        STCM WORKREG, 15, EIRECPTR
                                  Store it in EIRECPTR
             WORKREG.WTOLEN
                                  Get length of WTO
       ΙA
        STCM WORKREG, 15, EIRECLEN
                                  Store length it in EIRECLEN
        LH
             RC,EIRC08
                                  Set insert record retcode
        R
             OPT11XIT
OPT11XIT STH RC,EIRETCOD
                                  Store retcode in EIDB
       RR
           14
                                  Return to intercept processor
********************
* AIOPT12: Write WTOR Message
\star \, Check for ADR369D, never allow it to write over VTOC, etc \,
***********************
AIOPT12 ICM
             WORKREG, 15, EIRECPTR
       CLC
             12(8,WORKREG),ADR369D Q. Authorize request?
             WORKREG, UIMRESP
       BNE
                                  A. No, let DFSMSdss do WTOR
        LA WORKREG, UTTING STOM WORKREG, 15, EIRECPTR Store in EIRECPTA Get length of response
                                  Get address of response
        STCM WORKREG, 15, EIRECLEN
                                  Store in EIRECLEN
       LH
             RC,EIRC28
                                  Set WTOR Response retcode
       В
             OPT12XIT
OPT12RC0 LH
             RC,EIRC00
                                  Set normal process retcode
OPT12XIT STH
             RC,EIRETCOD
                                  Store retcode in EIDB
       BR
             14
                                  Return to intercept processor
********************
* AIOPT13: Present ADRUFO Record
   If parm call, set IO and AI buffers above 16M
 If function call and Copy, force reblocking.
*******************
AIOPT13 ICM TEMPBASE, 15, EIRECPTR
        USING ADRUFOB, TEMPBASE
                                  Get addressability to UFO
        CLC UFFUNCT, PARM
                                  Q. Is this a PARM call?
             PARMCALL
        BE
                                  A. Yes, go to parm call
FUNCTION TM
             UFFUNCT1, UFFUCOPY
                                  Is this a copy?
        BN0
             OPT13RC0
                                  No, don't change options
             WORKREG, WORKREG
        SR
        ICM
             WORKREG, 3, UFBDYOFF
                                  Get offset for PARM list
             WORKREG, TEMPBASE
                                  Add to address of UFO
        AR
```

Figure 34. User Interaction Module Example (continued)

## UIM

		UFOFUNCT, WORKREG	Establish addressability
	0I	UF03FLGS,UF0FRBLK	Force reblocking
	DROP	WORKREG	
	LH	RC,EIRC16	Set modify record retcode
DADMCALL	В	OPT13XIT	This is a norm soll
PARMCALL	ICM	WORKREG, WORKREG	This is a parm call. Get offset for PARM list
	AR	WORKREG,3,UFBDYOFF WORKREG,TEMPBASE	Add to address of UFO
		UFOFUNCT, WORKREG	Establish addressability
	OI OI	UFXAFLAG, UFXABUFF	Make sure IO buffers are >16M
	0I	UFXAFLAG, UFAI31B	Make sure AI buffers are >16M
	DROP	WORKREG	make sure AI burrers are >10m
	LH	RC,EIRC16	Set modify record retcode
	LA	WORKREG,2	Initialize message table:
	ST	WORKREG, MSGCOUNT	Initialize msgcount
	DROP	TEMPBASE	initialize mageount
	LA	TEMPBASE, MSGTABLE	Get address of table
		TABLEMAP, TEMPBASE	det dadress or table
	MVC	TABENTRY (133), HEADER	Move header into msgtable
	LA	TEMPBASE, 133 (TEMPBASE)	Move past first message
		TABENTRY(133),BLAN	Move blank line into table
		TEMPBASE	
	В	OPT13XIT	Exit.
OPT13RC0	LH	RC,EIRC00	Set normal process retcode
OPT13XIT		*	р
	STH	RC,EIRETCOD	Store retcode in EIDB
	BR	14	Return to intercept processor
*****	*****	******	********
* AIOPT1	4: Fund	ction Ending	*
******	*****	*******	**********
AIOPT14	LH	WORKREG, RTBCNT	Get Tape Blocks Read
	CVD	WORKREG,CVDWORK	Convert to decimal
		RTBINS,CVDWORK	Unpack into message insert
	OI	RTBINS+7,X'F0'	Make last character printable
	LH	WORKREG, WTBCNT	Get Tape Blocks Written
	CVD	WORKREG, CVDWORK	Convert to decimal
		WTBINS, CVDWORK	Unpack into message insert
	0I	WTBINS+7,X'F0'	Make last character printable
	LH	WORKREG, RLTBCNT	Get Tape Logical Blocks Read
	CVD	WORKREG, CVDWORK	Convert to decimal
		RLTBINS, CVDWORK	Unpack into message insert
	01	RLTBINS+7,X'F0'	Make last character printable
	LH	WORKREG, WLTBCNT	Get Tape Log Blocks Written
			Convert to decimal
	CVD	WORKREG, CVDWORK	
	UNPK	WLTBINS,CVDWORK	Unpack into message insert
	UNPK OI	WLTBINS,CVDWORK WLTBINS+7,X'F0'	Unpack into message insert Make last character printable
	UNPK OI LH	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT	Unpack into message insert Make last character printable Get Disk Tracks Read
	UNPK OI LH CVD	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WORKREG,CVDWORK	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal
	UNPK OI LH CVD UNPK	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WORKREG,CVDWORK RDTINS,CVDWORK	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert
	UNPK OI LH CVD UNPK OI	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WOORKREG,CVDWORK RDTINS,CVDWORK RDTINS+7,X'F0'	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable
	UNPK OI LH CVD UNPK OI LH	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WORKREG,CVDWORK RDTINS,CVDWORK RDTINS+7,X'F0' WORKREG,WDTCNT	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable Get Disk Tracks Written
	UNPK OI LH CVD UNPK OI LH CVD	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WORKREG,CVDWORK RDTINS,CVDWORK RDTINS+7,X'F0' WORKREG,WDTCNT WORKREG,CVDWORK	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable Get Disk Tracks Written Convert to decimal
	UNPK OI LH CVD UNPK OI LH CVD UNPK	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,CDTONT WORKREG,CVDWORK RDTINS,CVDWORK RDTINS+7,X'F0' WORKREG,WDTCNT WORKREG,CVDWORK WDTINS,CVDWORK	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable Get Disk Tracks Written Convert to decimal Unpack into message insert
	UNPK OI LH CVD UNPK OI LH CVD UNPK OI	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WORKREG,CVDWORK RDTINS,CVDWORK RDTINS+7,X'F0' WORKREG,WDTCNT WORKREG,CVDWORK WDTINS,CVDWORK WDTINS,CVDWORK WDTINS+7,X'F0'	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable Get Disk Tracks Written Convert to decimal Unpack into message insert Make last character printable
	UNPK OI LH CVD UNPK OI LH CVD UNPK OI LH CVD UNPK OI L L L L	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WOORKREG,CVDWORK RDTINS+7,X'F0' WORKREG,WDTCNT WORKREG,WDTCNT WORKREG,CVDWORK WDTINS,CVDWORK WDTINS,CVDWORK WDTINS+7,X'F0' MSGOFF,MSGCOUNT	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable Get Disk Tracks Written Convert to decimal Unpack into message insert Make last character printable Get current MSGCOUNT
	UNPK OI LH CVD UNPK OI LH CVD UNPK OI LH CVD UNPK OI L MH	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WORKREG,CVDWORK RDTINS,CVDWORK RDTINS+7,X'F0' WORKREG,WDTCNT WORKREG,CVDWORK WDTINS,CVDWORK WDTINS,CVDWORK WDTINS+7,X'F0' MSGOFF,MSGCOUNT MSGOFF,MSGLEN	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable Get Disk Tracks Written Convert to decimal Unpack into message insert Make last character printable Get current MSGCOUNT Multiply by MSGLEN to get
	UNPK OI LH CVD UNPK OI LH CVD UNPK OI LH CVD UNPK OI L L L L	WLTBINS,CVDWORK WLTBINS+7,X'F0' WORKREG,RDTCNT WOORKREG,CVDWORK RDTINS+7,X'F0' WORKREG,WDTCNT WORKREG,WDTCNT WORKREG,CVDWORK WDTINS,CVDWORK WDTINS,CVDWORK WDTINS+7,X'F0' MSGOFF,MSGCOUNT	Unpack into message insert Make last character printable Get Disk Tracks Read Convert to decimal Unpack into message insert Make last character printable Get Disk Tracks Written Convert to decimal Unpack into message insert Make last character printable Get current MSGCOUNT Multiply by MSGLEN to get offset into message table

Figure 35. User Interaction Module Example (continued)

```
USING TABLEMAP, TEMPBASE
         MVC TABENTRY (133), READMSG
                                        Move into msgtable
                TEMPBASE, 133 (TEMPBASE)
                                        Increment pointer for 2nd msg
         MVC
               TABENTRY(133), WRITEMSG Move into msgtable
         DROP
               TEMPBASE
                WORKREG, MSGCOUNT
                                        Increment MSGCOUNT
                WORKREG, 2 (WORKREG)
               WORKREG, MSGCOUNT
         ST
                                        Save new count
               RC.EIRC00
                                        Set normal process retcode
         STH RC, EIRETCOD
                                        Store retcode in EIDB
                                        Return to intercept processor
*****************
* AIOPT15: Present WTOR Response
*******************
AIOPT15 LH
         LH RC,EIRC00 Set normal process retcode
STH RC,EIRETCOD Store retcode in EIDB
BR 14 Return to intercept processor
******************
* AIOPT16: OPEN/EOF Tape Security and Verification
* Always bypass password protection
********************
AIOPT16 ICM TEMPBASE,15,EIRECPTR Get address of record LH RC,EIRC16 Bypass password protection ST RC,0(TEMPBASE) Store in EIRECPTR LH RC,EIRC16 Set modify record retcode STH RC,EIRETCOD Store retcode in EIDB R 14 Return to intercept processor
***************
* AIOPT17: OPEN/EOF Nonspecific Tape Mount
* Supply DFSMSdss with TAPE01
AIOPT17 ICM TEMPBASE,15,EIRECPTR Get address of record Supply TAPE01 as volser LH RC,EIRC16 Sth RC,EIRETCOD Store retcode in EIDB Return to intercept processor
*******************
* AIOPT18: Insert logical VSAM Record during Logical Restore *
AIOPT18 LH RC,EIRC00 Set normal process retcode
STH RC,EIRETCOD Store retcode in EIDB
BR 14 Return to intercept processor
******************
* AIOPT19: Output Tape I/O Error
  Save DDNAME, Volser, and Return code, print record.
*******************
AIOPT19 ICM TEMPBASE, 15, EIRECPTR Get address of EIRECORD
         USING EIDDINFO,TEMPBASE Est addressability to DDINFO
MVC OPT19DD,EIDDNAME Move DDNAME to message
MVC OPT19VS,EIVOLID Move VOLSER to message
SR WORKREG, WORKREG Clear out work register
IC WORKREG,EIRETC Get return code
CVD WORKREG.CVDWORK Convert to decimal
               WORKREG, CVDWORK
         CVD
                                        Convert to decimal
               OPT19RC(2), CVDWORK+6(2) Unpack into message insert
               OPT19RC+1,X'F0'
         ΟI
                                       Make last character printable
         DROP
               TEMPBASE
               MSGOFF, MSGCOUNT
                                        Get current MSGCOUNT
         МН
               MSGOFF, MSGLEN
                                        Multiply by MSGLEN to get
               WORKREG, MSGTABLE
         LA
                                        offset into message table
```

Figure 36. User Interaction Module Example (continued)

```
TEMPBASE, 0 (MSGOFF, WORKREG)
        USING TABLEMAP, TEMPBASE
             TABENTRY(133), OPT19MSG Move into msgtable
        DROP TEMPBASE
                                  WORKREG, MSGCOUNT
                                                        Increment MSGCOUNT
             WORKREG, 1 (WORKREG)
             WORKREG, MSGCOUNT
                                   Save new count
             RC,EIRC00
                                   Set normal process retcode
                                   Store retcode in EIDB
             RC, EIRETCOD
                                   Return to intercept processor
********************
* AIOPT20: Volume Information Exit
 Save Data Set name
****************
AIOPT20 ICM TEMPBASE,15,EIRECPTR Establish addressability to
        USING EIREC20, TEMPBASE
                                   EIREC20
        MVC OPT20DSN(44),EI20DSN
                                  Move data set name into msg
        DROP
            TEMPBASE
             MSGOFF, MSGCOUNT
                                   Get current MSGCOUNT
        МН
             MSGOFF, MSGLEN
                                  Multiply by MSGLEN to get
        LA
             WORKREG, MSGTABLE
                                   offset into message table
             TEMPBASE, 0 (MSGOFF, WORKREG)
        LA
        USING TABLEMAP, TEMPBASE
             TABENTRY(133), OPT20MSG Move into msgtable
        MVC
             TEMPRASE
        DROP
             WORKREG, MSGCOUNT
                                   Increment MSGCOUNT
        ΙΑ
             WORKREG, 1 (WORKREG)
        ST
             WORKREG, MSGCOUNT
                                   Save new count
        LH
             RC,EIRC00
                                   Set normal process retcode
        STH
             RC,EIRETCOD
                                   Store retcode in EIDB
        BR
             14
                                  Return to intercept processor
*****************
* AIOPT21: Data Set Verification Exit
    Do Not Process TEMP Data Sets
********************
AIOPT21 EOU
        ICM
              TEMPBASE,15,EIRECPTR Get record pointer
        USING EIREC21, TEMPBASE
                                  Get addressability
                                  If first 4 char of dsn='TEMP'
        CLC
              EI21DSN(4),TMPL
        DROP
              TEMPBASE
                                   Release addressability
        BNE
              LABEL1
                                   Then
        LH
              RC,EIRC36
                                  Do not process data set
              LABEL2
                                   Else
              RC,EIRC00
LABEL1
                                   Set normal return code
LABEL2
        STH
              RC, EIRETCOD
                                   Store retcode in EIDB
        BR
                                   Return to intercept processor
**********************
* AIOPT22: Bypass Verification Exit
   Bypass Serialization of SYS1 Data Sets
AIOPT22 EQU
              TEMPBASE, 15, EIRECPTR
                                  Get record pointer
        USING
              EIREC22, TEMPBASE
                                   Get addressability
        CLC
              EI22DSN(5),SYSL
                                   If first 5 char of dsn='SYS1.'
              LAB1
                                   Then
        LH
              RC,EIRC16
                                   Bypass serialization of dsn
        01
              EI22FLGS,B'10000000'
                                   Set EI22BSER bit on
              LAB2
                                   Else
        DROP
              TEMPBASE
                                   Release addressability
LAB1
        LH
              RC,EIRC00
                                   Set normal return code
LAB2
        STH
              RC, EIRETCOD
                                   Store retcode in EIDB
                                   Return to intercept processor
```

Figure 37. User Interaction Module Example (continued)

```
* AIOPT23: Data Set Processed Notification Exit
    End Function If Errors in Processing
*******************
AIOPT23 EQU
        ICM TEMPBASE, 15, EIRECFIN
USING EIREC23, TEMPBASE
LH WORKREG, EI23DSRC
DROP TEMPBASE
LTR WORKREG, WORKREG
R7 LABL1
         ICM TEMPBASE,15,EIRECPTR Get record pointer
                                       Get addressability
                                       If data set processing RC^=0
                                       Release addressability
                                     Then
               RC,EIRC32
                                     End function
         LH
               RC,EIRU32
LABL2 Else
RC,EIRC00 Set normal return code
RC,EIRETCOD Store retcode in EIDB
Return to intercept processor
         В
LABL1
         LH
LABL2
         STH
         BR
             14
****************
* AIOPT24: Concurrent Copy initialization complete
* End function if initialization is not successful
*******************
                            Start EIOP24 processing
AIOPT24 EQU
LH RC,EIRCOO Assume goodness
ICM TEMPBASE,15,EIRECPTR Get record pointer
USING EIREC24,TEMPBASE Get addressability
LH WORKREG,EI24RTCD Get the return code
DROP TEMPBASE Release addressability
LTR WORKREG,WORKREG If zero
BZ OPT24END End function
LH RC,EIRC32 Else end the function
OPT24END STH RC,EIRETCOD Store retcode in EIDB
BR 14 Return to intercept processor
               RC,EIRC00
         LH
                                       Assume goodness
***************
* AIOPT25: Backspace tape input
*******************
******************
* AIOPT26: Volume open for output
*****************
AIOPT26 EQU * Start EIOP26 processing
LH RC,EIRC00 Set normal process retcode
STH RC,EIRETCOD Store retcode in EIDB
BR 14 Return to intercept processor
******************
* Start of local variables
CURCOMM DC
               F'0'
                                       Address of current command
SYSINFL DC
               X'00'
                                       SYSIN Flag
SYSIFRST EQU
               X'80'
                                       First entry SYSIN Performed
SYSPRFL DC
                                       SYSPRINT Flag
               X'80'
INSDONE EQU
                                       Done inserting SYSPRINT recs
                                    Done inserting statement.
TEMP high-level qualifier
               C'TEMP'
         DC.
SYSL
        DC
               C'SYS1.'
                                       SYS1 high-level qualifier
SAVEAREA DC
               18F'0'
                                       My save area
VECTABLE DC
               A(AIOPTOO)
                                       Function Startup Exit
               A(AIOPTO1)
VEC01
       DC
                                       Read SYSIN Exit
```

Figure 38. User Interaction Module Example (continued)

## UIM

VEC02	DC	A(AIOPTO2)	Write SYSPRINT Exit
VEC03	DC	A(AIOPTO3)	Read Tape Block Exit
VEC04	DC	A(AIOPTO4)	Read Logical Tape Exit
VEC05	DC	A(AIOPTO5)	Write Logical Tape Exit
VEC05	DC	A(AIOPTO6)	Write Tape Block Exit
VEC07	DC	A(AIOPTO7)	Read DASD Track Exit
VEC08	DC	A(AIOPT08)	Write DASD Track Exit
VEC09	DC	A(AIOPTO9)	Read Utility Sysprint Exit
VEC10	DC	A(AIOPT10)	Write SYSPRINT Record
VEC11	DC	A(AIOPT11)	Write WTO Message Exit
VEC12	DC	A(AIOPT12)	Write WTOR Message Exit
VEC13	DC	A(AIOPT13)	Present ADRUFO Record Exit
VEC14	DC	A(AIOPT14)	Function Ending Exit
		1 1	
VEC15	DC	A(AIOPT15)	Present WTOR Response
VEC16	DC	A(AIOPT16)	OPEN/EOF Tape Sec/Ver Exit
VEC17	DC	A(AIOPT17)	OPEN/EOF NonSpec Tape Mount
VEC18	DC	A(AIOPT18)	Insert log VSAM Rcd -Restore
VEC19	DC	A(AIOPT19)	Output Tape I/O Error Exit
VEC20	DC	A(AIOPT20)	Volume Information Exit
VEC21	DC	A(AIOPT21)	Data Set Verification Exit
VEC22	DC	A(AIOPT22)	Bypass Verification Exit
VEC23	DC	A(AIOPT23)	Data Set Processed Exit
VEC24	DC	A(AIOPT24)	Concurrent Copy Init Complete
*	D.O.	1 (ATORTOE)	B 1
VEC25	DC	A(AIOPT25)	Backspace tape input
VEC26	DC	A(AIOPT26)	Volume open for output
*			
UIMWTO	DC	C'>>> USRUIM is acti	ve <<<'
	=0		
WTOLEN	EQU	*-UIMWTO	Show that we are active
*			
UIMRESP	DC	C'T'	Reply T to ADR369
RESPLEN	EQU	*-UIMRESP	
*			
ADR369D	DC	CL8'ADR369D'	DFSMSdss Authorization WTOR
ADR012I	DC	CL8'ADR012I'	Last DFSMSdss message id
*			•
MSGLEN	DC	H'133'	Length of messages
INSERTCT		F'0'	Count of msgs given to DFSMSdss
MSGCOUNT		F'0'	Count of messages in table
+	DC	1 0	count or messages in table
RTBCNT	DC	H'0'	Count of Tape Blocks Read
	DC	H'0'	
WTBCNT *	DC	по	Count of Tape Blocks Written
	DC	11101	Count I am Tama Dilanka Dani
RLTBCNT	DC	H'0'	Count Log Tape Blocks Read
WLTBCNT	DC	H'0'	Count Log Tape Blocks Written
*			
RDTCNT	DC	H'0'	Count Disk Tracks Read
WDTCNT	DC	H'0'	Count Disk Tracks Written
*			
WTOCT	DC	H'0'	Count of WTOs
*			
PARM	DC	X'0000'	Parm call test for Opt 13
*			
TAPE01	DC	CL6'TAPE01'	Tape volser for Opt 17
TAPE01 *	DC	CL6'TAPE01'	Tape volser for Opt 17
	DC	CL6'TAPE01'	Tape volser for Opt 17
*	DC DC		
*		C' *********	Tape volser for Opt 17  *** Begin USRUIM Messages ' ************************************
*	DC	C' *********	*** Begin USRUIM Messages '

Figure 39. User Interaction Module Example (continued)

```
TRAILER DC
            ************
BLANKS
       DC
            CL133''
                                Blank message
READMSG
            C' Disk Tracks Read:
RDTINS
            C'XXXXXXXX
                 Tape Blocks Read:
       DC
RTBINS
            C'XXXXXXXXX
       DC
       DC
                 Logical Tape Blocks Read:
RLTBINS
            C,XXXXXXXX
       DC
            CL(133-(*-READMSG))' '
       DC
WRITEMSG DC
                 Disk Tracks Written: '
WDTINS
       DC
            C'XXXXXXXX
                 Tape Blocks Written: '
       DC
WTBINS
            C'XXXXXXXXX
       DC
                 Logical Tape Blocks Written: '
       DC
WLTBINS
            C'XXXXXXXXX
       DC
            CL(133-(*-WRITEMSG))' '
       DC
OPTOOMSG DC
               Messages follow for task: '
            C'XX'
OPTOOTSK DC
            CL(133-(*-OPT00MSG))' '
       DC:
OPT19MSG DC
                  Permanent Tape Error for DDNAME: '
            C'XXXXXXXXX
OPT19DD DC
            C' VOLSER:
       DC
OPT19VS DC
            C'XXXXXXX'
            C' Return Code: '
       DC
OPT19RC
            C'XX'
       DC
            CL(133-(*-OPT19MSG))' '
       DC
                  EI20DSN = '''
OPT20MSG DC
OPT20DSN DC
            DC
            CL(133-(*-OPT20MSG))' '
       DC
CVDWORK DS
            D
                                Workarea for decimal conversion
       ADREID0
                                Macro to map EIDB
       ADRUF0
                                Macro to map UFO
USRUIM CSECT
MSGTABLE DS
             CL13300
                                Room in table for 100 msgs
TABLEMAP DSECT
                                DSECT to insert msgs into table
TABENTRY DS
             CL133
SYSPMAP DSECT
                                DSECT to find MSGID in DFSMSdss
             CL1
       DS
                                messages
MSGID
       DS
            CL7
```

Figure 40. User Interaction Module Example (continued)

```
PAGE 0001
                5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                                             1999.211 14:56
ADR010I (SCH)-PRIME(01), SIZE VALUE OF 4096K WILL BE USED FOR GETMAIN WTO 'USRAIPGM INVOKING DFSMSdss'
ADR1011 (R/I)-R101 (01), TASKID 001 HAS BEEN ASSIGNED TO COMMAND 'WTO 'DUMP DS(EXC(SYS1.**)) LOGINDD(DASD) OUTDD(TAPE)
ADR101I (R/I)-RI01 (01), TASKID 002 HAS BEEN ASSIGNED TO COMMAND 'DUMP'
    IF LASTCC=0 -
ADR101I (R/I)-RI01 (01), TASKID 003 HAS BEEN ASSIGNED TO COMMAND 'IF '
        THEN DEFRAG DDN(DASD)
ADR101I (R/I)-RI01 (01), TASKID 004 HAS BEEN ASSIGNED TO COMMAND 'DEFRAG'
ADR1091 (R/I)-RI01 (01), 1999.211 14:56:05 INITIAL SCAN OF USER CONTROL STATEMENTS COMPLETED. ADR0501 (002)-PRIME(01), DFSMSDSS INVOKED VIA APPLICATION INTERFACE
ADR016I (002)-PRIME(01), RACF LOGGING OPTION IN EFFECT FOR THIS TASK
ADR006I (002)-STEND(01), 1999.211 14:56:05 EXECUTION BEGINS
ADR788I (002)-DIVSM(03), PROCESSING COMPLETED FOR CLUSTER PUBSEXMP.KSDS.S01, 100 RECORD(S) PROCESSED, REASON 0
ADR801I (002)-DTDSC(01), DATA SET FILTERING IS COMPLETE. 4 OF 4 DATA SETS WERE SELECTED: 0 FAILED SERIALIZATION
                              AND 0 FAILED FOR OTHER REASONS.
ADR454I (002)-DTDSC(01), THE FOLLOWING DATA SETS WERE SUCCESSFULLY PROCESSED
                               PUBSEXMP.SAM.S01
                               PUBSEXMP.PDS.S01
                               CLUSTER NAME PUBSEXMP.ESDS.S01
                               CATALOG NAME
                                                SYS1.MVSRES.MASTCAT
                               COMPONENT NAME PUBSEXMP.ESDS.S01.DATA
                               CLUSTER NAME
                                                PUBSEXMP.KSDS.S01
                               CATALOG NAME
                                                SYS1.MVSRES.MASTCAT
                               COMPONENT NAME PUBSEXMP.KSDS.S01.DATA
COMPONENT NAME PUBSEXMP.KSDS.S01.INDEX
ADR006I (002)-STEND(02), 1999.211 14:56:06 EXECUTION ENDS
ADR013I (002)-CLTSK(01), 1999.211 14:56:06 TASK COMPLETED WITH RETURN CODE 0000
ADR050I (004)-PRIME(01), DFSMSDSS INVOKED VIA APPLICATION INTERFACE
ADR016I (004)-PRIME(01), RACF LOGGING OPTION IN EFFECT FOR THIS TASK
ADR0061 (004)-STEND(01), 1999.211 14:56:07 EXECUTION BEGINS
ADR2081 (004)-EANAL(01), 1999.211 14:56:07 BEGINNING STATISTICS ON D9S060:
                               FREE CYLINDERS
                                                                        000058
                               FREE TRACKS
                                                                        000003
                               FREE EXTENTS
                                                                        000002
                               LARGEST FREE EXTENT (CYL, TRK) 000053,0003
```

Figure 41. Output Resulting from Use of the UIM Exits

```
PAGE 0002
             5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                               1999.211 14:56
                         FRAGMENTATION INDEX
                                                            0.050
                         PERCENT FREE SPACE
ADR220I (004)-EANAL(01), INTERVAL BEGINS AT CC:HH 00001:0000 AND ENDS AT CC:HH 00006:000C
ADR209I (004)-EFRAG(01), 1999.211 14:56:07 MOVED EXTENT 001 FROM 00006:0000-00006:0004 TO 00001:0000-00001:0004 FOR
                        PUBSEXMP.ESDS.S01.DATA
ADR209I (004)-EFRAG(01), 1999.211 14:56:07 MOVED EXTENT 001 FROM 00006:0005-00006:0006 TO 00001:0005-00001:0006 FOR
                        PUBSEXMP.KSDS.S01.DATA
ADR209I (004)-EFRAG(01), 1999.211 14:56:07 MOVED EXTENT 001 FROM 00006:0007-00006:0008 TO 00001:0007-00001:0008 FOR
                        PUBSEXMP.SAM.S01
ADR209I (004)-EFRAG(01), 1999.211 14:56:07 MOVED EXTENT 001 FROM 00006:0009-00006:000A TO 00001:0009-00001:000A FOR
                        PUBSEXMP.PDS.S01
ADR209I (004)-EFRAG(01), 1999.211 14:56:08 MOVED EXTENT 002 FROM 00006:000B-00006:000B TO 00001:000B-00001:000B FOR
                        PUBSEXMP.PDS.S01
ADR213I (004)-EANAL(01), 1999.211 14:56:08 ENDING STATISTICS ON D9S060:
                         DATA SET EXTENTS RELOCATED
                                                           000005
                         TRACKS RELOCATED
                                                           000012
                         FREE CYLINDERS
                                                           000058
                         FREE TRACKS
                                                           000003
                         FREE EXTENTS
                                                           000001
                         LARGEST FREE EXTENT (CYL,TRK) 000058,0003
                         FRAGMENTATION INDEX
PAGE 0003
             5695-DF175 DFSMSDSS V2R10.0 DATA SET SERVICES
                                                               1999.211 14:56
ADR212I (004)-EANAL(01), EXTENT DISTRIBUTION MAP FOR D9S060:
                                 *FREE SPACE BEFORE* *FREE SPACE AFTER*
                                                                           * ALLOCATED *
                         EXTENT
                          SIZE
                           ΤN
                                       NO.
                                            CUM.
                                                         NO.
                                                               CUM.
                                                                             NO.
                                                                                   CUM.
                                      EXTS PCT/100
                                                                                 PCT/100
                         TRACKS
                                                        EXTS PCT/100
                                                                            EXTS
                             1
                                                                              4
                                                                                  0.148
                             2
                                                                              4
                                                                                  0.444
                             5
                                                                              1
                                                                                  0.629
                            10
                                                                              1
                                                                                  1.000
                            75
                                           0.085
                          >499
                                           1.000
                                                              1.000
ADRO06I (004)-STEND(02), 1999.211 14:56:08 EXECUTION ENDS
ADR013I (004)-CLTSK(01), 1999.211 14:56:08 TASK COMPLETED WITH RETURN CODE 0000
                        Begin USRUIM Messages ********************
  Messages follow for task: 00
  Messages follow for task: 02
   Disk Tracks Read: 00000014
                                                        00000000
                                    Tape Blocks Read:
                                                                    Logical Tape Blocks Read:
                                                                                                 00000000
   Disk Tracks Written: 00000000
                                    Tape Blocks Written: 00000036
                                                                    Logical Tape Blocks Written: 00000012
  Messages follow for task: 04
                       00000052
                                                        00000000
                                                                                                 00000000
   Disk Tracks Read:
                                    Tape Blocks Read:
                                                                    Logical Tape Blocks Read:
                                                                    Logical Tape Blocks Written: 00000000
   Disk Tracks Written: 00000012
                                    Tape Blocks Written: 00000000
                               USRUIM Messages
 ****** End
                                               *******
ADR012I (SCH)-DSSU (01), 1999.211 14:56:08 DFSMSDSS PROCESSING COMPLETE. HIGHEST RETURN CODE IS 0000
```

Figure 42. Output Resulting from Use of the UIM Exits (continued)

## **Chapter 24. Data set attributes**

This topic lists various attributes that DFSMSdss can set or change for a given data set, and identifies where DFSMSdss gets the attribute information from.

Locate the data set attribute of interest in the first column of Table 39. The remaining columns indicate where and under which conditions DFSMSdss finds the attribute information. For example, the data set size is usually determined by the source data set, unless the preallocated target data set is larger. The ALLDATA(x) and ALLEXCP keywords have an effect on the data set size.

Table 39. Data Set Attributes and How They Are Determined.

	Is the Attribute Determined by						
Attribute	the Source Data Set?	the Pre-Allocated Target?	a Keyword?	another Factor?			
Data set name	Yes, if no RENAME or RENAMEU	No	RENAME or RENAMEU	No			
Data set size	Yes, unless the preallocated target data set is larger	Yes, if it is big enough	ALLDATA(x) or ALLEXCP	No			
Volumes	Yes, if doing a RESTORE and no output volumes were specified, no target exists, and not SMS-managed	Yes	Yes, if not SMS, OUTDDNAME(x,) or OUTDYNAM(x,)	If SMS-managed, ACS routines and SMS allocation choose volumes with most available space; if not SMS-managed, DFSMSdss chooses volumes with most available space			
Data set location on volume	Yes, if no target and either ABSTR, PSU, POU, or DAU	Yes	FORCE can override ABSTR, PSU, POU, and DAU	DFSMSdss locates wherever space is available; DEFRAG may move extents			
PDS directory size (blocks)	Yes	No	No	No			
PDSE directory size (blocks)	Yes	No	No	No			
SMS Storage Class or Management Class	Yes, if no target and BYPASSACS is specified	Yes	Yes, if STORCLAS(x) or MGMTCLAS(x), or both, are specified with BYPASSACS				
SMS Data Class	Yes, if no target	Yes	No	No			
BLKSZ	Yes, if REBLOCK is not specified and data set is not system reblockable	No	If REBLOCK keyword is specified, DFSMSdss chooses a new optimal blocksize	If system reblockable, DFSMSdss chooses a new optimal blocksize, or else the user can change blocksize with the installation reblock exit and can specify REBLOCK with the installation options exit			
LRECL	Yes	No	No	No			
RECFM	Yes	No	No	No			
DSORG	Yes	No	No	No			
Number of stripes	Yes, source must be striped	Yes for non-VSAM. No for VSAM	No	For nonguaranteed-space, determined by sustained data rate (SDR) in STORCLAS. For guaranteed-space, must have a nonzero SDR, then determined by number of output volumes supplied			

## **Data Set Attributes**

Table 39. Data Set Attributes and How They Are Determined. (continued)

	Is the Attribute Determined by					
Attribute	the Source Data Set?	the Pre-Allocated Target?	a Keyword?	another Factor?		
Number of volumes (VOLCOUNT)	Yes	Yes	VOLCOUNT can make a single volume source into a multivolume target, or change the number of volumes for a multivolume data set	Yes (see the COPY and RESTORE command VOLCOUNT parameter descriptions for specific information)		
Number of extents	Yes, for imbedded extended KSDSs during physical data set restore	Yes	No	DFSMSdss always tries to consolidate during COPY/RESTORE. RELEASE may reduce the number of extents		
PDS/PDSE	Yes, if no target or if doing a RESTORE	Yes, if doing a COPY	CONVERT(PDS(x)) or CONVERT(PDSE(x))	No		
Cataloged	Yes, if RECATALOG(*) is specified, no target, and the user is not doing a physical data set restore	Yes	RECATALOG(x), CATALOG, UNCATALOG (applies to source only)	If SMS or VSAM, cataloged by default; if physical data set restore, only single volume non-VSAM is cataloged (if CATALOG is specified)		
Allocation unit	Yes, if no target and TGTALLOC (SOURCE) specified or defaulted	Yes	TGTALLOC(x)	No		
Free space in VSAM	Yes, if going to like device, nonVALIDATE, no dummy blocks, and CI and CA sizes do not change	Yes, if doing VSAM I/O and uses values in target catalog entry	VALIDATE, NOVALIDATE, FREESPACE	No		
Security (RACF)	If no target and source was generic or discrete, and no applicable profile protecting new target, a new discrete will be defined	Yes	MENTITY, MVOLSER	Full RACF profile information (access lists) are not preserved		
AIX data sets on VSAM clusters	If SPHERE is specified during COPY or DUMP and RESTORE, sphere and connections are preserved	No	SPHERE	No		
GDS state	Yes, if no target and TGTGDS (source) specified	Yes	TGTGDS(x)	No		
RLS BWO field	Yes, if no preallocated target and no UIM input	Yes, if no UIM input	No	UIM can pass a value in Exit 22 during logical RESTORE		
RLS timestamps	Yes, if not a logical restore	No	No For logical restore, if dump RLS access, timestamps refl time of the dump; otherwis timestamps are zero			
RLS recovery required	Yes, if no UIM input	No	No	UIM can pass a value in Exit 22 during logical RESTORE		
RLS log parameter	Yes, if no preallocated target and no UIM input	Yes, if no UIM input	No	UIM can pass a value in Exit 22 during logical RESTORE		
RLS log stream ID	Yes, if no preallocated target and no UIM input	Yes, if no UIM input	No	UIM can pass a value in Exit 22 during logical RESTORE		

Table 39. Data Set Attributes and How They Are Determined. (continued)

	Is the Attribute Determined by					
Attribute	the Source Data Set?	the Pre-Allocated Target?	a Keyword?	another Factor?		
BCS Quiesce enabled	Yes, unless preallocated	Yes	No	Only applies to logical restore		
BCS lock or suspend	Yes, unless preallocated	Yes	No	Only applies to logical restore. BCSRECOVER(LOCK   SUSPEND) is ignored if not preallocated.		
BCS RLS in use	No	No	No	Only applies to logical restore. BCSRECOVER(LOCK   SUSPEND) is ignored if not preallocated.		
Class transition information	Yes, if no preallocated target	Yes, unless it is unusable and needs to be scratched and reallocated	No	No		
LOGREPLICATE parameter	Yes, if no preallocated target and no UIM input	Yes, if no UIM input	No	UIM can pass a value in EXIT 22 during logical restore		
extended format sequential version number	Yes, if no preallocated target	Yes, if target has to be scratched and reallocated, the target version type will be preserved	No	No, if the target data set does not exist the target will be allocated with the source version type		

# Part 3. Appendixes

## **Appendix A. Coexistence Considerations**

This topic presents considerations for migrating to a newer version of DFSMSdss.

## Restoring backups using DFSMSdss

Dumps created with an older version or release of DFDSS or DFSMSdss can be restored with a newer version or release.

Data sets with extended attribute DSCBs can be restored to volumes that do not support extended attribute DSCBs; however, the extended attributes are lost. To prevent losing the extended attributes, restore the data set to volumes that support extended attribute DSCBs.

## Appendix B. Accessibility

Accessible publications for this product are offered through IBM Knowledge Center (http://www.ibm.com/support/knowledgecenter/SSLTBW/welcome).

If you experience difficulty with the accessibility of any z/OS information, send a detailed message to the "Contact us" web page for z/OS (http://www.ibm.com/systems/z/os/zos/webqs.html) or use the following mailing address.

**IBM** Corporation

Attention: MHVRCFS Reader Comments

Department H6MA, Building 707

2455 South Road

Poughkeepsie, NY 12601-5400

**United States** 

## **Accessibility features**

Accessibility features help users who have physical disabilities such as restricted mobility or limited vision use software products successfully. The accessibility features in z/OS can help users do the following tasks:

- Run assistive technology such as screen readers and screen magnifier software.
- Operate specific or equivalent features by using the keyboard.
- Customize display attributes such as color, contrast, and font size.

## Consult assistive technologies

Assistive technology products such as screen readers function with the user interfaces found in z/OS. Consult the product information for the specific assistive technology product that is used to access z/OS interfaces.

## Keyboard navigation of the user interface

You can access z/OS user interfaces with TSO/E or ISPF. The following information describes how to use TSO/E and ISPF, including the use of keyboard shortcuts and function keys (PF keys). Each guide includes the default settings for the PF keys.

- z/OS TSO/E Primer
- z/OS TSO/E User's Guide
- z/OS ISPF User's Guide Vol I

## **Dotted decimal syntax diagrams**

Syntax diagrams are provided in dotted decimal format for users who access IBM Knowledge Center with a screen reader. In dotted decimal format, each syntax element is written on a separate line. If two or more syntax elements are always present together (or always absent together), they can appear on the same line because they are considered a single compound syntax element.

Each line starts with a dotted decimal number; for example, 3 or 3.1 or 3.1.1. To hear these numbers correctly, make sure that the screen reader is set to read out

punctuation. All the syntax elements that have the same dotted decimal number (for example, all the syntax elements that have the number 3.1) are mutually exclusive alternatives. If you hear the lines 3.1 USERID and 3.1 SYSTEMID, your syntax can include either USERID or SYSTEMID, but not both.

The dotted decimal numbering level denotes the level of nesting. For example, if a syntax element with dotted decimal number 3 is followed by a series of syntax elements with dotted decimal number 3.1, all the syntax elements numbered 3.1 are subordinate to the syntax element numbered 3.

Certain words and symbols are used next to the dotted decimal numbers to add information about the syntax elements. Occasionally, these words and symbols might occur at the beginning of the element itself. For ease of identification, if the word or symbol is a part of the syntax element, it is preceded by the backslash (\) character. The \* symbol is placed next to a dotted decimal number to indicate that the syntax element repeats. For example, syntax element \*FILE with dotted decimal number 3 is given the format 3 \\* FILE. Format 3 \\* FILE indicates that syntax element FILE repeats. Format 3\* \\* FILE indicates that syntax element \* FILE repeats.

Characters such as commas, which are used to separate a string of syntax elements, are shown in the syntax just before the items they separate. These characters can appear on the same line as each item, or on a separate line with the same dotted decimal number as the relevant items. The line can also show another symbol to provide information about the syntax elements. For example, the lines 5.1\*, 5.1 LASTRUN, and 5.1 DELETE mean that if you use more than one of the LASTRUN and DELETE syntax elements, the elements must be separated by a comma. If no separator is given, assume that you use a blank to separate each syntax element.

If a syntax element is preceded by the % symbol, it indicates a reference that is defined elsewhere. The string that follows the % symbol is the name of a syntax fragment rather than a literal. For example, the line 2.1 %0P1 means that you must refer to separate syntax fragment OP1.

The following symbols are used next to the dotted decimal numbers.

## ? indicates an optional syntax element

The question mark (?) symbol indicates an optional syntax element. A dotted decimal number followed by the question mark symbol (?) indicates that all the syntax elements with a corresponding dotted decimal number, and any subordinate syntax elements, are optional. If there is only one syntax element with a dotted decimal number, the ? symbol is displayed on the same line as the syntax element, (for example 5? NOTIFY). If there is more than one syntax element with a dotted decimal number, the ? symbol is displayed on a line by itself, followed by the syntax elements that are optional. For example, if you hear the lines 5?, 5 NOTIFY, and 5 UPDATE, you know that the syntax elements NOTIFY and UPDATE are optional. That is, you can choose one or none of them. The ? symbol is equivalent to a bypass line in a railroad diagram.

#### ! indicates a default syntax element

The exclamation mark (!) symbol indicates a default syntax element. A dotted decimal number followed by the ! symbol and a syntax element indicate that the syntax element is the default option for all syntax elements that share the same dotted decimal number. Only one of the syntax elements that share the dotted decimal number can specify the ! symbol. For example, if you hear the lines 2? FILE, 2.1! (KEEP), and 2.1 (DELETE), you know that (KEEP) is the

default option for the FILE keyword. In the example, if you include the FILE keyword, but do not specify an option, the default option KEEP is applied. A default option also applies to the next higher dotted decimal number. In this example, if the FILE keyword is omitted, the default FILE(KEEP) is used. However, if you hear the lines 2? FILE, 2.1, 2.1.1! (KEEP), and 2.1.1 (DELETE), the default option KEEP applies only to the next higher dotted decimal number, 2.1 (which does not have an associated keyword), and does not apply to 2? FILE. Nothing is used if the keyword FILE is omitted.

### \* indicates an optional syntax element that is repeatable

The asterisk or glyph (\*) symbol indicates a syntax element that can be repeated zero or more times. A dotted decimal number followed by the \* symbol indicates that this syntax element can be used zero or more times; that is, it is optional and can be repeated. For example, if you hear the line 5.1\* data area, you know that you can include one data area, more than one data area, or no data area. If you hear the lines 3\*, 3 HOST, 3 STATE, you know that you can include HOST, STATE, both together, or nothing.

#### Notes:

- 1. If a dotted decimal number has an asterisk (\*) next to it and there is only one item with that dotted decimal number, you can repeat that same item more than once.
- 2. If a dotted decimal number has an asterisk next to it and several items have that dotted decimal number, you can use more than one item from the list, but you cannot use the items more than once each. In the previous example, you can write HOST STATE, but you cannot write HOST.
- 3. The \* symbol is equivalent to a loopback line in a railroad syntax diagram.

## + indicates a syntax element that must be included

The plus (+) symbol indicates a syntax element that must be included at least once. A dotted decimal number followed by the + symbol indicates that the syntax element must be included one or more times. That is, it must be included at least once and can be repeated. For example, if you hear the line 6.1+ data area, you must include at least one data area. If you hear the lines 2+, 2 HOST, and 2 STATE, you know that you must include HOST, STATE, or both. Similar to the \* symbol, the + symbol can repeat a particular item if it is the only item with that dotted decimal number. The + symbol, like the \* symbol, is equivalent to a loopback line in a railroad syntax diagram.

## **Notices**

This information was developed for products and services offered in the U.S.A. or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 U.S.A

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan, Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

Site Counsel IBM Corporation 2455 South Road Poughkeepsie, NY 12601-5400 **USA** 

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

## COPYRIGHT LICENSE:

This information might contain sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

## Policy for unsupported hardware

Various z/OS elements, such as DFSMS, HCD, JES2, JES3, and MVS<sup>™</sup>, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted

for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

## Minimum supported hardware

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: IBM Lifecycle Support for z/OS (http://www.ibm.com/software/support/systemsz/lifecycle/)
- For information about currently-supported IBM hardware, contact your IBM representative.

## **Programming interface information**

This publication primarily documents information that is NOT intended to be used as a Programming Interface of DFSMSdss.

This publication also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of DFSMSdss. This information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

Programming Interface Information	
End Programming Interface Information —	

## **Trademarks**

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available at Copyright and Trademark information (http://www.ibm.com/legal/copytrade.shtml).

## **Glossary**

This glossary defines technical terms and abbreviations used in DFSMSdss documentation. If you do not find the term you are looking for, refer to the index of the appropriate DFSMSdss manual or view *IBM Glossary of Computing Terms*, located at http://www.ibm.com/ibm/terminology.

#### A

#### **ABARS**

Aggregate backup and recovery support.

#### **ABEND**

Abnormal end of task. End of a task, a job, or a subsystem because of an error condition that cannot be resolved by recovery facilities while the task is performed.

#### **ABEND**xxx

The keyword that identifies the abnormal end of DFSMSdss because of a system-detected error.

#### ABSTR

A subparameter of the SPACE parameter in a DD statement. It indicates that specified tracks be assigned to a data set.

#### **ACCEPT** processing

An SMP/E process necessary for installing the FMIDs. SMP/E ACCEPT processing uses JCL to accept the modules and macros necessary to run the FMIDs. The FMIDs are accepted into the DLIBs from the temporary data sets.

### access method services

A multifunction service program that is used to manage both VSAM and non-VSAM data sets and integrated catalog facility or the ICF catalog. It is used to define data sets and allocate space for them; convert indexed-sequential data sets to key-sequenced data sets; modify data set attributes in the catalog; reorganize data sets; facilitate data portability between operating systems; create backup copies of data sets, data set records, and catalog entries; help make inaccessible data sets accessible; list the records of data sets and catalogs; define and build alternate

indexes; and convert OS CVOLs and the ICF catalog to integrated catalog facility catalogs.

ACDS Active control data set.

**ACS** Automatic class selection.

ADSP Automatic data set protection.

**alias** An alternate name for a member of a partitioned data set.

#### **ALLOC**

A space allocation parameter that indicates type, such as cylinders or tracks.

#### alternate index

In systems with VSAM, a key-sequenced data set containing index entries organized by the alternate keys of its associated base data records. It provides an alternate means of locating records in the data component of a cluster on which the alternate index is based.

#### alternate index cluster

In VSAM, the data and index components of an alternate index.

APAR Authorized program analysis report.

APF Authorized program facility.

## application interface

An interface used to invoke DFSMSdss from another program.

#### apply processing

In SMP and SMP/E, the process, initiated by the APPLY command, that places system modifications (SYSMODS) into the target system libraries.

attach In programming, to create a task that can be performed asynchronously with the performance of the mainline code.

#### authorization

(1) The right granted to a user to communicate with or make use of a computer system. (2) The process of giving a user either complete or restricted access to an object, resource, or function.

## authorized program analysis report (APAR)

A request for correction of a problem

caused by a suspected defect in a current unaltered release of a program.

## automatic class selection (ACS)

A mechanism for assigning SMS classes and storage groups.

### automatic data set protection (ADSP)

A system function, enabled by the SETROPTS ADSP specification and the assignment of the ADSP attribute to a user with ADDUSER or ALTUSER, that causes all permanent data sets created by the user to be automatically defined to RACF with a discrete RACF profile..

В

#### backout

The CICSVR function that you can use if CICS fails in the attempt to back out uncommitted changes on a VSAM sphere. Using information from the RCDS, CICSVR constructs a job to back out uncommitted changes on a VSAM data set as indicated on the log.

### backup

The process of creating a copy of a data set to ensure against accidental loss.

#### backup while open

DFSMSdss can perform backup of data sets that are open for update for a long period of time (like CICS). DFSMSdss can perform a logical data set dump of these data sets even if another application has them serialized.

### base cluster

In systems with VSAM, a key-sequenced or entry-sequenced data set over which one or more alternate indexes are built.

## basic catalog structure (BCS)

The name of the catalog structure in the integrated catalog facility environment. An integrated catalog facility catalog consists of a BCS and its related VSAM volume data sets (VVDSs).

#### basic direct access method (BDAM)

An access method used to directly retrieve or update particular blocks of a data set on a direct access device.

#### basic partitioned access method (BPAM)

An access method that can be applied to create program libraries in direct access storage for convenient storage and retrieval of programs.

### basic sequential access method (BSAM)

An access method for storing or retrieving data blocks in a continuous sequence, using either a sequential access or a direct access device.

**BCS** Basic catalog structure.

#### **BDAM**

Basic direct access method.

**BLK** A subparameter of the SPACE parameter in a DD statement. It specifies that space is allocated by blocks.

## block length

Synonym for block size.

#### block size

(1) The number of data elements in a block. (2) A measure of the size of a block, usually specified in units such as records, words, computer words, or characters. (3) Synonymous with block length. (4) Synonymous with physical record size.

**BPAM** Basic partitioned access method.

**bpi** Bits per inch.

#### Broken data set

Data sets which do not conform to IBM data set standards are referred to as *broken*. Broken data sets are either missing catalog entries, VTOC entries, or VVDS entries; or, have invalid catalog entries, VTOC entries, or VVDS entries.

#### **BSAM**

Basic sequential access method.

 $\mathbf{C}$ 

**CA** Control area.

call (ISO) The action of bringing a computer program, a routine, or a subroutine into effect, usually by specifying the entry conditions and jumping to an entry point.

## card image

A one-to-one representation of the hole patterns of a punched card; for example, a matrix in which a one represents a punch and a zero represents the absence of a punch.

#### **CC-compatible SnapShot**

See virtual concurrent copy.

#### **CCHHR**

Cylinder, cylinder, head, head, record.

**CCW** Channel command word.

**CDE** Contents directory entry.

CDS Control data set.

#### channel command word (CCW)

A doubleword at the location in main storage specified by the channel address word. One or more CCWs make up the channel program that directs data channel operations.

CI Control interval.

**CICS** Customer Information Control System.

#### **CICSVR**

CICS VSAM Recovery.

## CICS VSAM Recovery (CICSVR)

CICS VSAM Recovery is an IBM product that recovers your lost or damaged VSAM data.

**CLIST** Command list.

#### complete recovery

The CICSVR function that consists of forward recovery followed by backout, if needed. In CICSVR complete recovery, CICSVR restores a DFSMShsm or DFSMSdss backup for you.

### component identification keyword

The first keyword, represented as a number, in a set of keywords used to describe a DFSMSdss program failure.

#### compress

(1) To reduce the amount of storage required for a given data set by having the system replace identical words or phrases with a shorter token associated with the word or phrase. (2) To reclaim the unused and unavailable space in a partitioned data set that results from deleting or modifying members by moving all unused space to the end of the data set.

## **COMPRESS** command

The DFSMSdss function that reduces partitioned data sets by taking unused space and consolidating it at the end of the data set.

#### compressed format

A particular type of extended-format data set specified with the (COMPACTION) parameter of data class. VSAM can compress individual records in a compressed-format data set. SAM can compress individual locks in a compressed-format data set. See compress.

#### concatenation

An operation that joins two characters or strings in the order specified, forming one string whose length is equal to the sum of the lengths of the two characters or strings.

#### concurrent copy

A function to increase the accessibility of data by letting you make a consistent backup or copy of data concurrent with normal application program processing.

# concurrent copy-compatible (CC-compatible) SnapShot

See virtual concurrent copy.

#### conditioned volume.

The target volume from a previous FULL volume COPY operation which specified DUMPCONDITIONING.

#### control area (CA)

A group of control intervals used as a unit for formatting a data set before adding records to it. Also, in a key-sequenced data set, the set of control intervals, pointed to by a sequence-set index record, that is used by VSAM for distributing freespace and for placing a sequence-set index record adjacent to its data.

## control interval (CI)

A fixed-length area of auxiliary storage space in which VSAM stores records. It is the unit of information transmitted to or from auxiliary storage by VSAM.

#### control volume (CVOL)

A volume that contains one or more indexes of the catalog.

#### constructs

A collective name for data class, storage class, management class, and storage group.

#### **CONVERTV** command

The DFSMSdss function that converts volumes to and from Storage Management Subsystem management without data movement.

#### **COPY** command

The DFSMSdss function that performs data set, volume, and track movement.

**CP** Control program.

#### **CREDT**

Creation date.

**CSW** Channel status word.

CVAF Common VTOC access facility.

CVOL Control volume.

CVT Communication vector table.

CYL A subparameter of the SPACE parameter in a DD statement. It specifies that space is allocated by cylinders.

D

#### **DADSM**

The direct access space management program that maintains the VTOC, VTOCIX, and space on a volume.

**DAM** Direct access method.

#### **DASD**

Direct access storage device.

#### DASD ERP

DASD error recovery procedure.

## DASD volume

A DASD space identified by a common label and accessed by a set of related addresses.

#### data class

A list of data set allocation parameters and the values that are used when allocating a new SMS-managed data set.

## data compression (run-length)

A method of encoding repetitive series of identical characters so that they occupy less space on a dump tape. Data compression is supported by both physical dump and logical dump processing.

## Data Facility Storage Management Subsystem (DFSMS)

The complementary functions of DFSMSdfp, DFSMSdss, DFSMShsm, and DFSMSrmm which, together with RACF, provide a system-managed, administrator-controlled storage environment.

#### data set backup

Backup to protect against the loss of individual data sets.

### data set FlashCopy

One of the FlashCopy Version 2 functions. See also FlashCopy Version 2.

## data-set-changed indicator.

A bit that is set when a data set is opened for processing other than input.

DAU Direct access unmovable.

DB<sub>2</sub> IBM DATABASE 2.

**DCB** Data control block.

#### **DEFRAG** command

The DFSMSdss function that consolidates the free space on a volume to help prevent out-of-space abends on new allocations.

DEQ An assembler language macro instruction used to remove control of one or more serially reusable resources from the active

#### **DFSMS**

Data Facility Storage Management Subsystem.

### **DFSMS** environment

An environment that helps automate and centralize the management of storage. This is achieved through a combination of hardware, software, and policies. See also system-managed storage.

### DFSMSdfp

A DFSMS functional component that provides functions for storage management, data management, program management, device management, and distributed data access.

## **DFSMSdss**

A DFSMS functional component used to copy, move, dump, and restore data sets and volumes. DFSMSdss is the primary data mover of DFSMS.

#### **DFSMShsm**

A DFSMS functional component used for backing up and recovering data, and managing space on volumes in the storage hierarchy.

#### **DFSORT**

Data Facility Sort.

#### **DIAGNOSE**

An access method services command that scans an integrated catalog facility basic catalog structure (BCS) or a VSAM volume data set (VVDS) to validate the data structure.

DIRF DADSM interrupt recording facility. If a system fails, or a permanent I/O error occurs during allocation of space or during performance of a routine that updates the VTOC, the VTOC may be in error. To ensure that an error is recorded, the DADSM routines turn on a bit in the VTOC upon entry to a DADSM function, and, if no errors occur during processing, turn off that bit upon exiting from that function.

#### distribution libraries

IBM-supplied partitioned data sets on tape containing one or more components that the user restores to disk for subsequent inclusion in a new system.

**DLIB** Distribution library.

**DOC** In diagnosing program failures, the keyword that identifies an error in the documentation of a program.

**DOS** Disk Operating System.

#### DOS bit

On a volume without an indexed VTOC, a bit that indicates that the free space map is invalid.

**DSCB** Data set control block.

## **DSCHA**

A DFSMSdss keyword that is used in BY filtering. It indicates that the data set is to be selected if the data set has been changed.

#### dsname

Data set name.

#### **DSORG**

Data set organization. It is specified in the ICL as "DSORG=".

#### **DUMP** command

The DFSMSdss function used to back up data sets, tracks, and volumes.

#### dynamic allocation

Assignment of system resources to a program when the program is performed rather than when it is loaded main storage.

E

## early warning system (EWS)

A microfiche copy of the information contained in the software support facility (SSF), organized by component identification number, and indexed by APAR symptom code. EWS is published monthly and available to customers of IBM licensed programs.

**ECB** Event control block.

#### EC mode

Engineering change mode.

#### empty data set

A data set in which the pointer to the last-used block is 0.

ENQ An assembler language macro instruction that requests the control program to assign control of one or more serially reusable resources to the active task. It is also used to determine the status of a resource; that is, whether it is immediately available or in use, and whether control has been previously requested for the active task in another ENQ macro instruction.

#### entry-sequenced data set (ESDS)

In VSAM, a data set whose records are loaded without respect to their contents and whose RBAs cannot change. Records are retrieved and stored by addressed access, and new records are added at the end of the data set.

**EOF** End-of-file.

**EOJ** End of job.

#### erase-on-scratch

The physical erasure of data on a DASD data set when the data set is deleted (scratched).

**ESA** Enterprise Systems Architecture.

**ESS** Enterprise Storage Server.

ESDS Entry-sequenced data set.

#### **ESTAE**

Extended specify task abnormal exit.

**EQ** Equal to.

**EWS** Early warning system.

**EXCP** Execute channel program.

## execute channel program (EXCP)

A macro used to access a data set without specifying the organization.

#### **EXPDT**

Expiration date.

#### extended format

The format of a data set that has a data set name type (DSNTYPE) of EXTENDED. The data set is structured logically the same as a data set that is not in extended format but the physical format is different. Data sets in extended format can be striped or compressed. Data in an extended format VSAM KSDS can be compressed. See also striped data set and compressed format.

#### extended specify task abnormal exit (ESTAE)

A task recovery routine that provides recovery for those programs that run enabled, unlocked, and in task mode.

**extent** A continuous space on a DASD volume occupied by a data set or portion of a data set. An extent of a data set contains a whole number of control areas.

F

FC CVAF function code.

FCEC CVAF function-error code.

## filtering

The process of selecting data sets based on specified criteria. These criteria consist of fully- or partially-qualified data set names, or of certain data set characteristics, or of both.

## **FlashCopy**

A function of the Enterprise Storage Server (ESS) and DFSMSdss that provides instant data copying. When resources allow, DFSMSdss automatically selects FlashCopy.

## FlashCopy Version 1

The initial FlashCopy feature provided by ESS. FlashCopy Version 1 is supported at the volume level. Both the source and target volumes must reside on the same logical subsystem (LSS). Each volume can be in one FlashCopy relationship.

## FlashCopy Version 2

FlashCopy Version 2 provides enhancements to the existing FlashCopy Version 1 feature of ESS. These

enhancements include data set FlashCopy, multiple relationship FlashCopy, incremental FlashCopy, improvement in FlashCopy establish time, elimination of LSS constraint, and consistency group support. The source and target volumes must reside in the ame ESS. DFSMS exploits data set FlashCopy.

FMID Function modification identifier.

## forward recovery

The CICSVR function that reapplies all changes to the VSAM sphere since the last backup. CICSVR gets the information it needs to construct the recovery job from the RCDS. The contents of the logs are applied to the VSAM sphere to return it to its exact state before the data was lost. With CICSVR forward recovery, CICSVR restores a DFSMShsm or DFSMSdss backup for you.

## fragmentation index

The qualitative measure of the scattered free space on a volume.

## fully-qualified data set name

A data set in which all the qualifiers are completely spelled out.

## function modification identifier (FMID)

A code that identifies the release levels of a program product.

**FVL** Function vector list.

G

GDG Generation data group.

**GDS** Generation data set.

## generalized trace facility (GTF)

An optional OS/VS service program that records significant systems events, such as supervisor calls and start I/O operations, for the purpose of problem determination.

## generation data group (GDG)

A collection of historically related non-VSAM data sets that are arranged in chronological order; each data set is a generation data set.

#### generation data set

One generation of a generation data group.

## global resource serialization (GRS)

A component of z/OS used for serializing use of system resources and for

converting hardware reserves on DASD volumes to data set enqueues.

**GT** Greater than.

**GTF** Generalized trace facility.

Η

**HFS** Hierarchical file system.

Ι

#### **ICKDSF**

Device Support Facilities.

#### **IDCAMS**

Access Method Services.

**IDRC** Improved data recording capability.

#### **IMS/VS**

Information Management System/Virtual Storage.

#### **INCORROUT**

In diagnosing program failures, the keyword that identifies incorrect or missing program output.

## incremental backup

A process in which data sets are backed up only if they have changed since their last backup.

## installation exit

The means specifically described in an IBM software product's documentation by which an IBM software product may be modified by a customer's system programmers to change or extend the functions of the IBM software product. Such modifications consist of exit routines written to replace one or more existing modules of an IBM software product, or to add one or more modules or subroutines to an IBM software product, for the purpose of modifying (including extending) the functions of the IBM software.

## integrated catalog facility

A facility by which VSAM data set volume-related fields are separated from the catalog and maintained in the VVDS on the volume on which the data set resides.

#### integrated catalog facility catalog

A catalog that is composed of a basic catalog structure (BCS) and its related volume table of contents (VTOC) and VSAM volume data sets (VVDSs).

## **Interactive Problem Control System (IPCS)**

A component of z/OS that permits online problem management, interactive problem diagnosis, problem tracking, and problem reporting.

## **Interactive Storage Management Facility (ISMF)**

An interactive interface of z/OS that allows users and storage administrators access to the storage management functions.

## Interactive System Productivity Facility (ISPF)

An IBM licensed program used to develop, test, and run application programs interactively. ISPF is the interactive interface for all storage management functions.

I/O Input/output.

IPCS Interactive Problem Control System.

**IPL** Initial program load.

**ISMF** Interactive Storage Management Facility.

**ISAM** Indexed sequential access method.

ISMF Interactive Storage Management Facility.

**ISPF** Interactive Systems Productivity Facility.

## ISPF/PDF

Interactive Systems Productivity Facility/Program Development Facility.

J

**ICL** Job control language.

**JES** Job entry subsystem.

JES2 An MVS subsystem that receives jobs into the system, converts them to internal format, selects them for operation, processes their output, and purges them from the system. In an installation site with more than one processor, each JES2 processor independently controls its job input, scheduling, and output processing.

JES3 An MVS subsystem that receives jobs into the system, converts them to internal format, selects them for operation, processes their output, and purges them from the system. In complexes that have several loosely coupled processing units, the JES3 program manages processors so that the global processor exercises centralized control over the local processors and distributes jobs to them via a common job queue.

JFCB Job file control block.

## job control language (JCL)

A problem-oriented language used to identify the job or describe its requirements to an operating system.

## job entry subsystem (JES)

A system facility for spooling, job queuing, and managing I/O.

**JSCB** Job step control block.

K

K Kilobyte: 1 024 bytes.

## key-sequenced data set

A VSAM file or data set whose records are loaded in ascending key sequence and controlled by an index. Records are retrieved and stored by keyed access or by addressed access, and new records are inserted in key sequence by means of distributed free space. Relative byte addresses can change because of control interval or control area splits.

## keyword

A symptom that describes one aspect of a program failure.

**KRDS** Keyrange data set. Also known as a key-sequenced data set with key ranges.

KSDS Key-sequenced data set.

L

#### **LASTCC**

Last condition code.

LDS Linear data set.

#### like devices

Devices that have the same track capacity and number of tracks per cylinder (for example, 3380 Model D, Model E, and Model K).

LINK An assembler language macro instruction that causes control to be passed to a specified entry point. The linkage relationship established is the same as that created by a basic assembler language (BAL) instruction.

## link-pack area (LPA)

An area of virtual storage that contains reenterable routines that are loaded at IPL (initial program load) time and can be used concurrently by all tasks in the system.

#### load module

A computer program in a form suitable for loading into main storage for operation.

## load module library

A partitioned data set used to store and retrieve load modules.

## logical DUMP operation (data set)

A DUMP operation in which logical processing is performed.

## logical processing (data set)

Processing that treats each data set and its associated information as a logical entity. As an example, DFSMSdss processes an entire data set before beginning with the next one.

## logical storage subsystem (LSS)

Used internally by ESS to manage a set of logical volumes which are associated with an individual device adapter, e.g., a physical ESS subsystem may be partitioned into multiple logical storage subsystems.

## logical RESTORE operation (data set)

A RESTORE operation that uses as input a data set produced by a logical DUMP operation.

## logical volume

The output produced from a physical DUMP operation, for which all data is derived from a single DASD volume.

LOOP In diagnosing program failures, the keyword that identifies a program failure in which some part of the program repeats endlessly.

**LPA** Link-pack area.

LSS Logical storage subsystem.

LT Less than.

**LRECL** 

Logical record length.

LVOL Logical volume.

M

**Mb** Megabit; 1 048 576 bits.

MB Megabyte; 1 048 576 bytes.

## maintenance-level keyword

In diagnosing program failures, a keyword that identifies the maintenance level of DFSMSdss.

## management class

A list of the migration, backup, and retention parameters and the values for an SMS-managed data set.

## map record

The record that maps the tracks dumped by DFSMSdss.

#### **MAXCC**

Maximum condition code.

MCS Multiple console support.

#### **MENTITY**

Model entity.

#### minivolume

In an MVS system running on VM/370, an OS/VS-formatted VM/370 minidisk whose size is equal to or less than that of the real volume. DFSMSdss uses the device size specified in the VTOC. Minivolumes are supported only by the system version of DFSMSdss.

#### **MSGADRnnnt**

In diagnosing program failures, the DFSMSdss message keyword that tells of an error, or seems itself to be in error.

**MVS** Multiple Virtual Storage.

Ν

NVR Non-VSAM volume record.

0

## operating system (OS)

Software that controls the execution of programs; an operating system may provide services such resource allocation, scheduling, input/output control, and data management.

P

## pageable link-pack area (PLPA)

Link-pack area.

**PAM** Partitioned access method.

## partially qualified data set name

A data set name in which the qualifiers are not spelled out. Asterisks and percent signs are used in place of the undefined qualifiers.

#### partitioned data set (PDS)

A data set in direct access storage that is divided into partitions, called members, each of which can contain a program, part of a program, or data.

## partitioned data set extended (PDSE)

A system-managed, page-formatted data set on direct access storage. A PDSE contains an indexed directory and members similar to the directory and members of partitioned data sets. A PDSE can be used instead of a partitioned data set.

PDS Partitioned data set.

PDSE Partitioned data set extended.

#### **PERFM**

In diagnosing program failures, the keyword that identifies degradation in program performance.

## physical DUMP operation (data set)

A DUMP operation in which physical processing is performed.

## physical processing (data set)

Processing that moves data at the track-image level and can operate against volumes, tracks, and data sets. As an example, DFSMSdss may only process one volume of a multivolume data set.

PLPA Pageable link-pack area.

**POU** Partitioned organization unmovable.

**PRB** Program request block.

## private library

A user-owned library that is separate and distinct from the system library.

**PSU** Physical sequential unmovable.

**PSW** Program status word.

PTF Program temporary fix.

0

#### **QSAM**

Queued sequential access method.

## qualified name

A data set name consisting of a string of names separated by periods; for example, "TREE.FRUIT.APPLE" is a qualified name.

#### qualifier

Each component name in a qualified name other than the rightmost name. For example, "TREE" and "FRUIT" are qualifiers in "TREE.FRUIT.APPLE."

## queued sequential access method (QSAM)

An extended version of the basic

sequential access method (BSAM). Input data blocks awaiting processing or output data blocks awaiting transfer to auxiliary storage are queued on the system to minimize delays in I/O operations.

R

**RACF** Resource Access Control Facility.

#### RAMAC Virtual Array (RVA)

A DASD that uses a virtual array architecture.

RB Request block.

**RBA** Relative byte address.

**RCDS** Recovery Control Data Set.

## **RDJFCB**

Read job file control block.

#### **RECEIVE** processing

An SMP/E process necessary to install new product libraries. During this process, the code, organized as unloaded partition data sets, is loaded into temporary SMPTLIB data sets. SMP/E RECEIVE processing automatically allocates the temporary partitioned data sets that correspond to the files on the tape, and loads them from the tape.

#### **RECFM**

Record format.

#### recovery

The process of rebuilding data after it has been damaged or destroyed, often by restoring a backup version of the data or by reapplying transactions recorded in a log.

#### **REFDT**

A DFSMSdss keyword used in BY filtering. It indicates the last-referenced date.

## relative byte address (RBA)

The displacement (expressed as a fullword binary integer) of a data record or a control interval from the beginning of the data set to which it belongs, independent of the manner in which the data set is stored.

#### relative record data set (RRDS)

A VSAM data set whose records are loaded into fixed-length slots.

#### **RELEASE** command

The DFSMSdss function that releases the

unused space in sequential and partitioned data sets for use by other data sets.

#### RESERVE

A method of serializing DADSM update accesses to the VTOC. It is also a method of serializing processor accesses to a shared DASD volume.

#### Resource Access Control Facility (RACF)

An IBM program product that provides for access control by identifying and verifying users to the system, authorizing access to DASD data sets, logging the detected unauthorized attempts to enter the system, and logging the detected accesses to protected data sets.

#### **RESTORE** command

The DFSMSdss function used to recover data sets, tracks, and volumes.

**RMID** Replacement module identifier.

RNL Resource name list.

RRDS Relative record data set.

**RVA** RAMAC Virtual Array.

#### run-length data compression

Data compression (run-length).

S

SAF System authorization facility.

SAM Sequential access method.

#### scheduler task

A DFSMSdss subtask that interprets and schedules commands.

SCP System control program.

SEO Sequential or sequential processing.

## sequential data striping

A software implementation of a disk array that distributes data sets across multiple volumes to improve performance.

#### **SEREP**

System environmental recording, editing, and printing

System management facilities. SMF

**SML** MVS Storage Management Library.

**SMP** System Modification Program.

#### SMP/E

System Modification Program/Extended.

SMPE A cataloged procedure that includes the required DD statements for running SMP/E and is used in the RECEIVE, APPLY, and ACCEPT steps of SMP/E processing.

SMS Storage Management Subsystem.

## SnapShot

A function of the RAMAC Virtual Array (RVA) that allows an instantaneous copy to be made of data sets using DFSMS software.

## software support facility (SSF)

An IBM online database that allows for storage and retrieval of information about all current APARs and PTFs.

## sphere

A VSAM cluster with one or more associated alternate indexes and paths. The VSAM cluster (sometimes called the base cluster), alternate indexes, and paths are sometimes referred to as sphere components.

**SSF** Software support facility.

## stand-alone restore program

A DFSMSdss program that allows you to restore a full volume or particular tracks from a dump tape. This program can be used without a host system environment.

#### storage class

A named list of data set storage attributes that identify performance goals and availability requirements, defined by the storage administrator, used to select a device that can meet those goals and requirements.

## storage constructs

The group of predefined models (data class, management class, storage class, and storage group) that are used to classify storage management needs and procedures for data sets under the Storage Management Subsystem. Each data set has construct names associated with it by explicit specification or defaulting.

#### storage group

A named collection of DASD volumes that have been grouped to meet a defined service strategy.

## storage management

The task of managing auxiliary storage resources for an installation.

## Storage Management Subsystem (SMS)

A z/OS subsystem that helps automate and centralize the management of storage. To manage storage, the storage management subsystem provides the storage administrator with control over data class, storage class, management class, storage group, and automatic class selection routine definitions.

stripe In DFSMS, the portion of a striped data set, such as an extended format data set, that resides on one volume. The records in that portion are not always logically consecutive. The system distributes records among the stripes such that the volumes can be read from or written to simultaneously to gain better performance. Whether it is striped is not apparent to the application program.

## striped data set

An extended format data set that occupies multiple volumes. A software implementation of sequential data striping.

## striping

A software implementation of a disk array that distributes a data set across multiple volumes to improve performance.

#### subtask

A task initiated and ended by a higher order task.

**SVC** Supervisor call instruction.

**SVRB** Supervisor request block.

#### **SYSRES**

System residence disk

#### system data

The data sets required by z/OS or its subsystems for initialization.

#### system-managed data set

A data set that has been assigned a storage class.

#### system-managed storage

Storage managed by the Storage Management Subsystem. SMS attempts to deliver required services for availability, performance, space, and security to applications.

## system library

A collection of data sets or files in which the parts of an operating system are stored.

## system link library

System library.

## System Modification Program (SMP)

A program used to install software and software changes on the z/OS system.

## System Modification Program Extended (SMP/E)

An IBM licensed program used to install software and software changes on the z/OS system. In addition to providing the services of SMP, SMP/E consolidates installation data, allows more flexibility in selecting changes to be installed, provides a dialog interface, and supports dynamic allocation of data sets.

T

**TCB** Task control block.

## Time sharing option (TSO)

An option on the operating system for a System/370 that provides interactive time sharing from remote terminals.

TIOT Task input/output table.

TLIB Target library.

#### track packing

A technique used by DFSMSdss that builds target tracks for any DASD device using input physical record information.

TRK A subparameter of the SPACE parameter in a DD statement. It specifies that space is to be allocated by tracks.

TSO Time sharing option.

TSO/E TSO/Extensions.

TTR Track-track-record.

## type-of-failure keyword

In diagnosing program failures, a keyword that identifies the type of program failure that has occurred in DFSMSdss.

U

**UACC** Universal access authority.

**UCB** Unit control block.

UIM User interaction module.

#### unlike devices

Devices that have different track capacities or a different number of tracks per cylinder.

#### used tracks

Tracks from the beginning of data sets to the last-used track.

#### user exit

A programming service provided by an IBM software product that may be requested by an application program for the service of transferring control back to the application program upon the later occurrence of a user-specified event.

**VDRL** Volume restore limits.

VDSS VTOC/Data Set Services.

## virtual concurrent copy

An operation that uses SnapShot to provide a concurrent copy-like function when the source volume supports SnapShot, but not concurrent copy. (Also called CC-compatible SnapShot.)

## virtual storage access method (VSAM)

An access method for direct or sequential processing of fixed and variable-length records on direct access devices. The records in a VSAM data set or file can be organized in logical sequence by a key field (key sequence), in the physical sequence in which they are written on the data set or file (entry-sequence), or by the relative-record number.

VMVirtual machine.

VOLID

Volume ID.

## **VOLSER**

Volume serial number.

#### volume

The storage space on DASD, tape or optical devices, which is identified by a volume label.

#### volume backup

Backup of an entire volume to protect against the loss of the volume.

## volume header record

The record in the DFSMSdss dump tape that identifies and contains data pertinent to the whole volume, and identifies the type of operation that created a dump.

## volume trailer record

The record in the DFSMSdss dump tape that identifies the end of the data for a DASD volume.

#### **VRRDS**

A VSAM variable record RRDS.

#### **VSAM**

Virtual storage access method.

## VSAM volume data set (VVDS)

A data set that describes the VSAM and SMS-managed non-VSAM data sets on a volume. The name of the data set is SYS1.VVDS.Vvolser.

VSE Virtual storage extended.

VTOC Volume table of contents.

#### VTOCIX

The data set on which the location of the data set VTOC entries are kept in an index for quick access by DADSM.

VVDS VSAM volume data set.

VVR VSAM volume record.

W

WAIT In diagnosing program failures, the keyword that identifies DFSMSdss suspended activity, while waiting for some condition to be satisfied. DFSMSdss does not issue a message to tell why it is waiting.

WTO Write to operator.

Z

zFS See *z/OS File System*.

#### z/OS File System (zFS)

A z/OS UNIX file system that can be used in addition to the hierarchical file system (HFS). zFS stores files in VSAM linear data sets. z/OS provides support for zFS in its Distributed File Service element.

## Index

Index		
* (single asterisk) used in partially qualified data set names 21, 260 ** (double asterisk) used in partially qualified data set names 21, 260 % (percent sign) used in partially qualified data set names 21, 260 % (parcent sign) used in partially qualified data set names 21, 260	ADMINISTRATOR parameter 272 ADMINISTRATOR parameter (Stand-Alone BUILDSA command) 272 ADRDSSU 577 ADRDSSU program using for Linux partition 187 ADREID0 data area 607 ADRMCLVL macro 622 ADRTAPB 198	asterisks, in a data set qualifier 260 auditing information 26 authorization checking for EXPORT/IMPORT (IDCAMS commands) 106 authorization installation exit routine 5 authorization levels for BUILDSA command 528 authorization structure 27
Numerics  16 MB virtual storage, storage requirements per command 11, 12  16 megabytes virtual storage buffers above 256  31-bit addressing mode 588  3380 Direct Access Storage 93, 131  3390 Direct Access Storage 93, 131  3494 Tape Library 513  64-bit addressing mode 256  9345 DASD module 93, 131  A  ABEND keyword 254  ABOVE16 keyword 256	ADRUFO, presenting record – eioption 13 595  ADRUIM module 580  ADRXMAIA 581  ADSP (Automatic Data Set Protection) 535, 537  AIX (alternate index), recataloging 315 aliases of non-VSAM data sets 47, 81, 116  ALLDATA keyword  COPY command 311  copying data set to like device 370  copying data set to unlike device 371 DUMP command 399  dumping records past last-used-block pointer 48, 71  PRINT command 434  specified during a dump 70 to control what DFSMSdss copies 98	automatic cartridge loader 516 Automatic Data Set Protection 537 AUTORELBLOCKADDRESS keyword 82, 121 COPY command 312 RESTORE command 460 auxiliary commands continuation errors 510 EOJ 510 IF-THEN-ELSE 507 PARALLEL 504 SERIAL 504 SET 505 WTO 503 WTOR 503 availability 33 availability management 5 availability strategy, planning 33 avoiding lockout 562
access authorization for DFSMSdss commands 547 accessibility 651 contact IBM 651 features 651 ACCESSVOL keyword FlashCopy relationship, volume 135 thawing the frozen, volume 136 ACL (automatic cartridge loader) 516 ACS information 179 ACS variables CONVERTV 181 COPY 179 name/description 179 passed in COPY command 179 passed in RESTORE/ CONVERTV 181 RESTORE 181 ACTIVE state 90, 122 ACTIVE subkeyword of TGTGDS COPY command 356	with preallocated target 128  ALLEXCP keyword COPY command 312 copying data set to like device 370 copying data set to unlike device 371 DUMP command 400 dumping records past last-used-block pointer 48, 71, 188 Linux dumps 188 specified during a DUMP 70, 188 to control what DFSMSdss copies 98, 188 with preallocated target 128, 188 ALLOC keyword 23, 263 allocation space 356, 486 ALTER LOCK, IDCAMS command 79 alternate index, recataloging 315 always-call 535, 536, 537 AMDSADMP (SADMP) service aid 521 AMSGCNT keyword 254 application interface	backing up (dumping) data 391 backing up HFS data sets 44 backing up volumes with incremental FlashCopy 60 backspace physical tape record – eioption 25 603 backup concurrent copy 7, 40, 107 data set 5, 33, 37, 44 DFSMShsm and DFSMSdss 6 disaster recovery 6, 19 incremental 6 integrated catalog facility user catalog 46 migrated data sets 6 reducing time using volume dump and volume
RESTORE command 487  ADMINISTRATOR keyword  COMPRESS command 279  CONSOLIDATE command 285  COPY command 310  DEFRAG command 376  DUMP command 399  FACILITY class profiles for 542  PRINT command 434  RELEASE command 444  RESTORE command 460  with FlashCopy 132  with native SnapShot 138	application interface function 26 invoking 25 module names 28 summary data set processing 607 record processing 606 application program process 625 archive 33, 36 ASIDPTR 579 assignment of class names using the RESTORE and COPY commands 494 assistive technologies 651	copy 51 scenario 43 SMS-managed data sets 49 SMS-managed environment 34 special requirements 44 system volumes 51 vital records 6, 18, 33 volume 5, 6, 33, 50 backup copies, multiple 371 backup-while-open serialization CICS 571 concurrent copy 574 DFSMStvs 571

backup-while-open serialization	CATALOG keyword (continued)	commands (continued)
(continued)	CONVERTV command 295	DFSMSdss commands (continued)
general processing 572	COPY command 314	EOJ 510
IMS data sets 575	during logical restore processing 74	IF-THEN-ELSE 506
overview 571	RESTORE command 462	PARALLEL 504
status definitions 572	with preallocated target 128	PRINT 432
BCSRECOVER keyword	catalog management services 531	RELEASE 441
RESTORE command 460	cataloging non-VSAM data sets during	RESTORE 452
BELOW16 keyword 256	restore 77	SERIAL 504
BLK subkeyword of TGTALLOC	CATLG keyword 22, 263	SET 505
COPY command 356	CGCREATED	Writing to the Operator 503
RESTORE command 486	creating consistent copies,	WTOR 503 DFSMSdss COPYDUMP
BLKSIZE and LRECL keywords, specifying in a print operation 436	volume 135 FlashCopy relationship, volume 135	command 70
block size (DFSMSdss dump data set)	thawing the frozen, volume 136	DFSMSdss DUMP command 69
controlling at dump time 415	verifying the consistency group,	DFSMSdss RESTORE command 70
default when dumping to tape or	volume 136	function 269
DASD 54, 415	CGCREATED command	overview 269
minimum 54	for DFSMSdss 276	compaction 55, 402
with COPYDUMP command 372	changing	compatibility between DFSMSdss
block structure, calling 577	management class with restore 88	versions 649
blocks, application interface 585	storage class with RESTORE 87	COMPRESS
broken data sets 20, 267	characteristics	access authorization for 548
buffers above 16 megabytes 256	data sets 259	subkeyword (DUMP command) 402,
buffers below 2 gigabyte real	filtering by 262	408
storage 256	characteristics of data sets 20	COMPRESS command 20
building a Stand-Alone Services IPL-able	CHECKVTOC keyword	ADMINISTRATOR keyword 279
core image 271	COPY command 315	BY keyword 280
BUILDSA command 272	DUMP command 401	DDNAME keyword 280
for DFSMSdss 271	CHECKVTOC keyword, data	definition 10
BY keyword	integrity 19	DYNALLOC keyword 280
CONSOLIDATE command 286	CICSVR ACVID keyward 42	DYNAM keyword 280, 281
COPY command 212	CICSVRBACKUP keyword 42	EXCLUDE keyword 281
COPY command 313 criteria 20, 259	DFSMSdss 42 CICSVRBACKUP	FILTERDD keyword 281 for DFSMSdss 278
DEFRAG command 376	COPY command 316	INCLUDE keyword 282
DUMP command 400	DUMP command 401	module name 28
filtering criteria 267	CICSVRBACKUP keyword	PASSWORD keyword 282
operator meaning 22	COPY command 42	PDS (partitioned data set) 152
RELEASE command 444	DUMP command 42	sample operations 283
RESTORE command 461	class names	WAIT keyword 282
bypass verification exit - eioption	filter 49	concurrent copy 9, 98
22 597	saved 49	backup 40, 107
BYPASSACS keyword	class selection, process diagram 494	CONCURRENT keyword 41, 108,
COPY command 313	cluster, VSAM, restoring 84	402
RESTORE command 461	coexistence considerations 649	dynamic pacing 350
	combining	full-volume dump 426
•	data set extents 154	initialization 431
C	volume copy and volume dump	initialization complete – eioption
calling block structure 577	functions 51 command	24 602 Moving Data Sata 107
CANCELERROR keyword	IF-THEN-ELSE 508	Moving Data Sets 107 performance considerations 55
CONSOLIDATE command 286	null 508	processing considerations 7
COPY command 314	syntax, general instructions 251	serialization handling 7
DUMP command 400	commands	CONCURRENT keyword
RESTORE command 462	auxiliary 503	COPY command 108, 316
card readers supported 13	DFSMSdss BUILDSA command 514	DUMP command 41, 402
catalog 77	DFSMSdss commands	condition codes
access authority 546	BUILDSA 271	general description 505
during logical restore 74	CGCREATED 276	LASTCC 506
integrated catalog facility 79 locking 79	COMPRESS 278	MAXCC 506
moving 115	CONSOLIDATE 283	setting 505
restoring 79	CONVERTV 294	conditioned volume
standard search order 267	COPY 299	copying 100
temporary copied 16	COPYDUMP 371	description 52
CATALOG keyword	DEFRAG 374	consoles supported 13
CONSOLIDATE command 285	DUMP 391	

CONSOLIDATE command	CONVERTV command (continued)	COPYDUMP command (continued)
access authorization for 548	DDNAME keyword 295	syntax diagram 372
ADMINistrator keyword 285	DEBUG keyword 296	COPYDUMP command, Linux 195
BY keyword 286	DYNAM keyword 296	COPYDUMP, access authorization
CANCELERROR keyword 286	explanation 294	for 553
DATASET keyword 286	for DFSMSdss 294	copying multivolume data sets 117
DEBUG keyword	FORCECP keyword 296	copying the Stand-Alone Services core
FRMSG sub-keyword 287	INCAT keyword 295	image (example) 275
TRACE sub-keyword 287	NONSMS keyword 296	COPYVOLID keyword 94
description 283	PREPARE keyword 297	COPY command 319
diagnosing errors 167	REDETERMINE keyword 297	RESTORE command 463
DYNALLOC keyword 287	sample operations 298	CPVOLUME keyword 51, 94, 140
example 293 EXClude keyword 288	SELECTMULTI keyword 297 serialization 568	COPY command 320 DUMP command 404
FASTREPLICATION keyword 288	SMS keyword 298	PRINT command 434
FCTOPPRCPRIMARY keyword 289	syntax diagram 294	RESTORE command 464
FILTERDD keyword 290	TEST keyword 298	CREDT keyword 22, 263
for DFSMSdss 283	CONVERTV processing, variables passed	criteria for filtering 20, 259
FORCECP keyword 290	to ACS routines 181	critical data sets 35
INCLUDE keyword 290	COPY command	Cross-Memory Application Interface
MAXTIME keyword 291	changing	controlling DFSMSdss
PASSWORD keyword 291	management class 125	ASPACE parameter 584
performance 155	storage class 124	SNAPX parameter 584
PHYSINDDNAME keyword 292	CICSVRBACKUP keyword 42	SRVRTIME parameter 583
PHYSINDYNAM keyword 292	CONCURRENT keyword 108	customer program, invocation 42, 60
PROCESS keyword 292	CONVERT keyword	CYL subkeyword of TGTALLOC
syntax diagram 284	partitioned data set 318	COPY command 356
using 153	partitioned data set extended 318	RESTORE command 486
WAIT keyword 292	data mover selection matrix 105	
WRITECHECK keyword 293	DEBUG keyword 320	<b>D</b>
CONSOLIDATE keyword (DEFRAG	for DFSMSdss 299	D
command)	like devices 8	damaged PDS, restoring 85
obsolete 377	logical processing 17	DASD (direct access storage device)
CONSOLIDATE option 155 contact	logical volume 130 LOGINDYNAM keyword 341	devices supported 13
z/OS 651	module name 28	initialized 13
continuation errors in auxiliary	moving data 8, 98, 116	reclaiming space 151
commands 510	physical volume 131	space fragmentation 155
control area 339, 469	restriction	space utilization 155
control interval 339, 469	copying an extended-format	DASD (direct access storage device) space
controlling DFSMSdss	VSAM data set 118	fragmentation 374
using ISMF 25	SOURCE subkeyword of	dasdfmt utility formatting a Linux for System z
using JCL 25	TGTALLOC 377	volume 186
controlling task processing 504	sphere restrictions 118	DASDVOL
controlling what DFSMSdss copies 98	unlike devices 8	access authority 535, 541, 553
conversion	used to make CICSVR backups 43	authority 532, 544
by data movement 9	user catalog 115	data class 3
from SMS	using volume copy	data compaction
by data movement 143 special requirements 148	for reducing backup time 51, 60	hardware 54
without data movement 148	with volume dump 51, 60 variables passed to ACS routines 179	software 54
GDG data set 148, 149	VSAM data sets 118	data integrity 19
in an SMS-managed environment 86	COPY DATASET, data mover selection	considerations
ineligible data sets 141, 142	matrix 106	COPY command 362
multivolume 147, 149	COPY FULL	DUMP command 425
preparing a volume 144	freeing the sources, volume 135, 136	RESTORE command 454
simulating 144	copy operation for logical data set 300	during data processing 19
to and from SMS management 9, 141	COPY TRACKS CPVOLUME	shared DASD considerations 60 data movement
to SMS	freeing the sources, volume 135, 136	conversion by 9
by data movement 142	COPY, access authorization for 549, 553	criteria for 97
special requirements 146	COPYDUMP command	preparing for 97
without data movement 145	explanation 371	with FlashCopy 132
without data movement 10, 143	for DFSMSdss 371	with native SnapShot 138
CONVERT keyword (COPY	INDDNAME keyword 372, 409	data mover selection matrix for Data Set
command) 318	LOGICALVOLUME keyword 372	Copy 106
CONVERTV command 10 CATALOG keyword 295	OUTDDNAME keyword 373 sample operations 373	data security 163

data set	data-set-changed indicator (continued)	DEFRAG command (continued)
absolute track 78, 81	using for data set backup 6, 22, 24,	FORCECP keyword 382
backup 5, 33, 37, 44	37	FRAGMENTATIONINDEX
broken 20	using for volume backup 34	keyword 382
changed flag	DATABASE 2 14	general hints 160
DUMP command 418	DATACLAS keyword 22, 263	LIST subkeyword 376
characteristics (BY criteria) 20	DATALENGTH keyword (PRINT	MAXMOVE keyword 383
converting to multivolume in an	command) 434	MAXTIME keyword 384
SMS-managed environment 86	DATASET keyword	MMOVPCT keyword 385
critical 35	CONSOLIDATE command 286	operation interrupted 15
DEFRAG, special 15	COPY command 320	options 159
direct access 81, 82, 121	data mover selection matrix for	PASSDELAY subkeyword 383
dummy 16	copy 106	PASSWORD keyword 386
erase table for DEFRAG 164	DUMP command 404	performance 155
expiration date handling 104	PRINT command 435	sample operations 388
extents, combining 154	RESTORE command 464	serialization 161
filtering 17, 20, 21	with logical processing 17	syntax diagram 374
GDG 90, 122	with physical data set restore 76	VERSIOIN1 keyword 387
HFS 44	DB2 (DATABASE 2) data sets 14	WAIT keyword 387
indexed sequential 81	DCB keywords LRECL and BLKSIZE,	when to run 155
last-used-block pointer 48	specifying in a print operation 436	with SnapShot 155
line operator module names 28	DDNAME keyword	WRITECHECK keyword 387
logical dump 35, 38	CONVERTY command 280	DEFRAG data set, special 15
logical restore 71	CONVERTV command 295	DEFRAG/RACF database 159 DELETE keyword
message 15	DEFRAG command 376, 380	3
moving 98 multivolume 45, 116	RELEASE command 444 DDNAME list 577	COPY command 324 DUMP command 404
name	DDNAME/VOLID Pointer 588	DELETECATALOGENTRY keyword 91
fully qualified 20, 260	DDPTR parameter 577	
partially qualified 20, 260	DEBUG keyword 254	using 91 DELETECATALOGENTRY keyword
non-SMS-managed 90	CONSOLIDATE command	(RESTORE command) 464
organizations 14	FRMSG sub-keyword 287	deleting unwanted data sets 152
partitioned (PDS) 14	TRACE sub-keyword 287	description 134
physical Dump 38	CONVERTV command 296	determining version, release, modification
physical restore 76	RESTORE command 464	level using the ADRMCLVL macro 622
preallocated 72, 126	DEBUG(FRMSG	Device Support Facilities utility 13
profiles	FlashCopy, data sets 111	devices supported 13, 93
discrete 536	FlashCopy, volume 133	DEVTYPE parameter (Stand-Alone
generic 536	SnapShot 114, 158	TAPECNTL command) 527
renaming 102	SnapShot, volume 138	DFM 324
restoring 70	decrypting data	DFP segment 540
in an SMS-managed	hardware considerations 67	DFSMSdss
environment 85	software considerations 68	access authorization for
multivolume 78	default block size when dumping to tape	commands 547
to multiple target volumes 78	or DASD 54	backing up Linux for z/Series 185
sequential 14	DEFERRED state 90, 122	backup and DFSMShsm 6
SMS-managed 49, 86, 89	DEFERRED subkeyword of TGTGDS	BUILDSA command 514
SMS-managed data sets	COPY command 356	CICSVR 42
non-VSAM 492	RESTORE command 487	commands
physical restore actions 492	DEFINE function of SAF (system	BUILDSA 271
VSAM 492	authorization facility) 531	CGCREATED 276
special requirements 44, 114	DEFRAG command 20	COMPRESS 278
SYS1 system 48	access authorization for 553	CONSOLIDATE 283
system 115	ADMINISTRATOR keyword 376	CONVERTV 294
temporary copied data set 15	BY keyword 376	COPY 299
temporary names 15, 148	CONSOLIDATE keyword 377	COPYDUMP 371
uncataloged 24	data set erase table 164	DEFRAG 374
undefined DSORG 83	data sets excluded 158	DUMP 391
unmovable 81, 82, 120	DDNAME keyword 377	EOJ 510
VSAM 48	DDNAME subkeyword 376	IF-THEN-ELSE 506
with phantom catalog entries 90	definition 10	PARALLEL 504
data set movement	DYNALLOC keyword 379	PRINT 432
concurrent copy 107	DYNAM keyword 380	RELEASE 441
data-set-changed indicator DFSMSdss handling for a restored	EXCLUDE keyword 380 explanation 374	RESTORE 452 SERIAL 504
data set 76, 92	FASTREPLICATION keyword 380	SET 505
example of use 43	for DFSMSdss 374	Writing to the Operator 503

DECMC 1 (time-t)	DO END	DIIMP
DFSMSdss (continued)	DO-END group of commands	DUMP command (continued)
commands (continued)	condition for processing 507	RESET keyword 418
WTOR 503	syntax 507	sample operations 426
compatibility with older versions 649	double encryption	SELECTMULTI keyword 342, 412
control 25	processing requests for 69	SHARE keyword 419
COPYDUMP command 70	DSCHA keyword 22, 263	special considerations 391
devices supported 13, 93	DSORG keyword 22, 263	SPHERE keyword 420
double encryption 70	dummy data set 16, 539	STORGRP keyword 420
filtering 20	DUMP command 10, 20, 55	syntax diagram 391
9		
function protection 27	access authorization for 554	SYS1 subkeyword 417
interactive 25	ADMINISTRATOR keyword 399	TOLERATE keyword 421
invoking 25	ALLDATA keyword 399	TRACKS keyword 422
invoking with application	ALLEXCP keyword 400	UNCATALOG keyword 423
interface 25	BY keyword 400	VALIDATE keyword 48, 423
line operators 28	CANCELERROR keyword 400	WAIT keyword 424
module names 28	CHECKVTOC keyword 401	with HFS data sets 564
module, main entry point 577	CICSVRBACKUP keyword 42, 401	ZCOMPRESS keyword 425
overview 3	COMPRESS command 402, 408	dump conditioned volume 325
pointer to address-space-identifier	CONCURRENT keyword 41, 402	dump data, multiple copies 371
list 579	CPVOLUME keyword 404	DUMPCONDITIONING keyword
processing option 586	data set changed flag 418	COPY command 325
protecting modules 29		
1 0	data set example 258	dump conditioned volume 325
Stand Alone Restore program 514	DATASET keyword 404	using 52, 100
storage requirements 11	DELETE keyword 404	dumping
system requirements 11	disaster recovery of logical data	data sets 48
volume formats supported 13	sets 35	efficiently 51
DFSMSdss commands	DYNALLOC keyword 405	HFS data sets 44
BUILDSA 271	ENQFAILURE subkeyword 421	indexed VSAM data sets 48
CGCREATED 276	exceptions to	integrated catalog facility user
COMPRESS 278	hardware data compaction 54	catalog 46
CONSOLIDATE 283	software data compaction 54	multivolume data sets 45
CONVERTV 294	EXCLUDE keyword 406	non-VSAM data sets 47
COPY 299	explanation 391	SYS1 system data sets 48
COPYDUMP 371	FCWITHDRAW keyword 406	VSAM spheres 47
DEFRAG 374	FILTERDD keyword 407	DYNALLOC keyword
DUMP 391	for DFSMSdss 391	COMPRESS command 280
EOJ 510	FORCECP keyword 407	CONSOLIDATE command 287
IF-THEN-ELSE 506	FULL keyword 408	COPY command 326
PARALLEL 504	general description 6	DEFRAG command 379
PRINT 432	INCAT keyword 408	DUMP command 405
	*	PRINT command 435
RELEASE 441	INCLUDE keyword 409	
RESTORE 452	INDDNAME keyword 409	RELEASE command 445
SERIAL 504	INDYNAM keyword 409	RESTORE command 467
SET 505	IOERROR subkeyword 421	DYNALLOC option 159
Writing to the Operator 503	logical data set 38	DYNAM keyword
WTOR 503	logical data set disaster recovery 35	COMPRESS command 281
DFSMSdss DUMP	logical volume 50	CONVERTV command 296
NEWNAMEUNCONDITIONAL	LOGINDDNAME keyword 411	DEFRAG command 380
description 39	LOGINDYNAM keyword 412	RELEASE command 445
DFSMShsm and DFSMSdss, backup 6	module name 28	dynamic allocation 566
DFSMStvs	NEWNAMEUNCONDITIONAL	
backup-while-open data sets 571	keyword 413	
backup-while-open status	non-VSAM data sets 47	E
definitions 572	NOVALIDATE keyword 414, 423	<del>_</del>
direct access	ONLYINCAT keyword 408, 414	eioption 00 – function startup 590
data set	OPTIMIZE keyword 55, 414	eioption 01 – reading SYSIN record 591
moving 121	OUTDDNAME keyword 415	eioption 02 – printing SYSPRINT
restoring 82	PASSWORD keyword 416	record 591
9	· · · · · · · · · · · · · · · · · · ·	eioption 03 – reading physical tape
supported 14	performance considerations 55	record 592
storage device 13	physical data set 38	eioption 04 – reading logical tape
direct access data set	physical volume 50	record 592
copying 351	printed output	eioption 05 – writing logical tape
restoring 478	produced by integrated catalog	record 593
disaster recovery 6, 19, 33, 34	facility user catalog 47	eioption 06 – writing physical tape
disk track	PROCESS keyword 417	record 593
reading – eioption 07 593	PURGE keyword 417	eioption 07 – reading disk track 593
writing – eioption 08 593	READIOPACING keyword 417	eioption 08 – writing disk track 593
		1

eioption 09 –reading utility SYSPRINT 593	EXCLUDE keyword COMPRESS command 281	FCNOCOPY keyword (continued) FlashCopy relationship, volume 133,
eioption 10 – writing SYSPRINT record 594	COPY command 326 criteria 259	135 using 52, 53
eioption 11 – writing WTO message 594	DEFRAG command 380	FCSETGTOK keyword 306
eioption 12 – writing WTOR	DUMP command 406	description 334
message 594	RELEASE command 445	FACILITY class profile 533
eioption 13 – presenting ADRUFO	RESTORE command 467	using space efficient FlashCopy 134
record 595 eioption 14 – function ending 595	EXCP data sets, supported 14 EXEC statement 253	FCTOPPRCPRIMARY keyword CONSOLIDATE command 289
eioption 15 – presenting WTOR	EXEC statement PARM information 254	FCWAIT keyword
response 595	exit	using 61
eioption 16 – OPEN/EOV tape volume	identification block 585	FCWITHDRAW keyword
security and verification exit 595	interface, structure 585	DUMP command 406
eioption 17 – OPEN/EOV nonspecific tape volume mount 595	exit functions, User Interaction  Module 26	freeing subsystem resources 112 freeing subsystem resources,
eioption 18 – insert logical VSAM record	exits, installation 5	volume 133
during restore 596	EXPDT keyword 22, 263	initializing the source volume 135
eioption 19 – output tape I/O error 596	expiration date handling 104	using 52, 53
eioption 20 – volume notification 596	EXPORT/IMPORT (IDCAMS commands),	withdrawing FlashCopy
eioption 21– data set verification 597 eioption 22 – bypass verification	authorization checking 106 extended-addressable VSAM KSDS 14	relationship 112 withdrawing FlashCopy relationship,
exit 597	extended-format VSAM data set	volume 133
eioption 23 – data set processed	COPY restriction 118	fdasd utility
notification exit 601	restoring 83	creating Linux partitions 187
eioption 24 – concurrent copy	extended-sequential data set 362, 442,	FILE parameter (Stand-Alone RESTORE
initialization complete 602	491 ovtents combining 154	command) 525
eioption 25 – backspace physical tape record 603	extents, combining 154 EXTNT keyword 22, 263	filter DD, JCL statement 254 filter, class names 49
eioption 26 – IMS volume notification	2,71111 ney word <b>22, 2</b> 66	FILTERDD keyword
user exit 604	_	COMPRESS command 281
eligibility for conversion 142	F	CONSOLIDATE command 290
ELSE command 508	FACILITY class profiles for DFSMSdss	DUMP command 407
empty non-VSAM data sets 114 encryption	keywords 533, 541	RELEASE command 338 RESTORE command 468
for tape backups 63	FAILRELATION sub-keyword	filtering 17
host-based, for tape backups 64	specifying for FCSETGTOK keyword 134, 335	BY 267
END command 508	FASTREPLICATION keyword	characteristics 262
ending function aigntion 14 505	CONSOLIDATE command 288	COMPRESS 20 data set characteristics 21
function – eioption 14 595 your DFSMSdss step 510	COPY command 327	examples 23
ENDTRK parameter (Stand-Alone	DEFRAG command 380	FILTERDD keyword 23
RESTORE command) 524	FlashCopy, data sets 110 FlashCopy, volume 132	general description 20, 259
ENQ keyword 563	native SnapShot 113	logical DUMP 20
ENQFAILURE subkeyword	native SnapShot, volume 138	logical RESTORE 20
COPY command 357 DUMP command 421	FCCGFREEZE keyword	physical DUMP 20 physical RESTORE 20
PRINT command 437	COPY command 328	relative generation 262
RESTORE command 487	FlashCopy relationship, volume 135 freezing the source, volume 136	RELEASE 20
enqueue	FCCGVERIFY keyword	RESTORE command 71
compared to DYNALLOC 566	FlashCopy relationship, volume 135	VSAM data sets 259
exit routine options for non-VSAM data sets 564	verifying the consistency group,	FlashCopy authorization checking 132
scheme 563	volume 136	backing up and restoring volumes 60
enqueue installation exit routine 5	FCFASTREVERSERESTORE keyword	backing up, volume 135
environment, system 11	COPY command 328 FCFULLVOLUMERELATION keyword	creating consistent copies,
EOJ command 510	COPY command 329	volume 135
for DFSMSdss 510	FCINCREMENTAL keyword	DEBUG(FRMSG keyword 111
EQ operator 22, 263 erase-on-scratch 540	using 60	DEBUG(FRMSG keyword, volume 133
ERRORTRACKS keyword (PRINT	FCINCREMENTALLAST keyword	FCNOCOPY keyword
command) 435	using 61 FCINCRVERIFY keyword	relationship 112
ESDS data sets, supported 14	using 61	FCNOCOPY keyword relationship,
EXCLUDE criteria 20 EXClude keyword	FCNOCOPY keyword	volume 133
CONSOLIDATE command 288	COPY command 330, 333, 336, 337 FlashCopy relationship 112	freeing subsystem resources 112 freeing subsystem resources,
		volume 133

FlashCopy (continued)	GDG (generation data group) data set	IMS volume notification user exit -
freezing the source, volume 135	conversion from SMS 149	eioption 26 604
in conjunction with	conversion to SMS 148	INCAT keyword
physical full volume copy 51, 60	moving 122	CONVERTV command 295, 296
moving data sets with	restoring 90	COPY command 339
FlashCopy 109	GE operator 22, 264	DUMP command 408
moving data with FlashCopy 9	generating the Stand-Alone Services	RELEASE command 446
moving volumes with	program 271	INCLUDE criteria 20
FlashCopy 132	generation data group 262	INCLUDE keyword
problem solving 111	generation data sets, moving to	COMPRESS command 282
problem solving, volume 133	non-SMS-managed volumes 123	CORV command 240
reducing backup time 51, 60	global access checking table 535, 537	COPY command 340 criteria 259
thawing the frozen, volume 135 verifying the consistency group,	GT operator 22, 264	DUMP command 409
volume 135		RELEASE command 446
withdrawing the system	Н	RESTORE command 470
relationship 112		incremental backup 6, 37
withdrawing the system relationship,	HFS (hierarchical file system) data	incremental FlashCopy
volume 133	set 14	FCINCREMENTAL keyword 60
FORCE keyword 81, 120, 122	HFS data set	FCINCREMENTALLAST
COPY command 338	DUMP command considerations 419	keyword 61
RESTORE command 468	logical data set COPY 300	FCINCRVERIFY keyword 61
FORCECP keyword	logical dump and serialization 564 physical dumb and serialization 565	FCWAIT keyword 61
CONSOLIDATE command 290	read/write serialization scheme 566	INDDNAME keyword
CONVERTV command 296	RELEASE command	COPY command 340
COPY command 339	consideration 442	COPYDUMP command 372
DEFRAG command 382	HFS data set, dumping 44	DUMP command 409
DUMP command 407	host-based encryption	physical processing 18
RESTORE command 468	considerations 64, 65	PRINT command 435
FRAGI keyword 159, 161	double encryption requests	RESTORE command 471
fragmentation index 161	allowing 70	INDDNAME parameter (Stand-Alone
FRAGMENTATIONINDEX keyword (DEFRAG command) 382	processing 69	BUILDSA command) 272 index, fragmentation 161
free-space fragmentation 155, 374	examples 64, 67	indexed sequential data set
FREESPACE keyword	hardware considerations 64, 67	restoring 81
COPY command 339	ICSF Callable Services 68	indexed VSAM data sets, logical data set
RESTORE command 469	DFSMSdss 64	dump of 48
FROMADDR parameter (Stand-Alone	key management considerations 64	indexed VTOCs 13
RESTORE command) 523	keys and DFSMSdss 65 managing keys 66	INDYNAM keyword
FROMDEV parameter (StandAlone	performance and hardware types 64,	COPY command 341
RESTORE command) 523	68	DUMP command 409
FSIZE keyword 22, 263	securing tape backups 64	physical processing 18
FULL keyword	software requirements 64, 68	PRINT command 435
COPY command 339	types 64	INITIAL state 144
DUMP command 408	using compression with 64, 66	INITIAL status 89
Linux for System z dumps 189	0 1	initialization
Linux for System z restore 189		concurrent copy complete – eioption
physical processing 18		24 602
RESTORE command 469 FULL parameter (Stand-Alone RESTORE	I/O error, output tape – eioption 19 596	from concurrent copy failure 426, 431
command) 524	ICKDSF REFORMAT command 273	initialize all DASD volumes 13
full volume copy	ICKDSF, initialize DASD volumes	input error toleration
FCNOCOPY keyword 53	with 13	COPY command 357
FCWITHDRAW keyword 53	IDCAMS utility 106	DUMP command 421
process 51, 60	IEBCOPY utility 106	PRINT command 437
using the DUMPCONDITIONING	IF command, nesting 509	input to DFSMSdss (in DD
keyword 52, 100	IF-THEN-ELSE command	statement) 253
fully qualified data set names 20, 261	for DFSMSdss 506	input volumes, specifying 99, 100
function	IF-THEN-ELSE group of commands	insert logical VSAM record during restore
ending – eioption 14 595	command sequencing 508	– eioption 18 596
startup – eioption 00 590	description 504	installation exit routines 5
	examples 509	integrated catalog facility user catalog
	syntax 507	backing up a user catalog, example
G	IGWFAMS utility 107	of 46
GDG (generation data group)	IMPORT keyword (RECTORE	dumping 46
data set status assignment 356, 487	IMPORT keyword (RESTORE	printed output for dumping a user
filtering 262	command) 469, 559	catalog 47

integrated catalog facility user catalog	K	logical
(continued) printed output for restoring a user	key sequenced data sets, supported 14	tape record, reading – eioption 04 592
catalog 80	keyboard	tape record, writing – eioption
restore 79	navigation 651	05 593
integrity, data serialization 561	PF keys 651	VSAM record, insert during restore
Interactive Storage Management	shortcut keys 651 KEYLENGTH keyword (PRINT	eioption 18 596
Facility 25	command) 436	logical COPY 97, 130
invocation customer program 42	keyword	logical data set dump of indexed VSAI data sets 48
invocation, from a customer program 60	module protection 29	logical data set restore 71
invoking DFSMSdss	preallocated targets 128	logical dump volume 50
application interface 25	profile names 29	logical processing 17
by ATTACH, LINK, or CALL	KSDS, supported 14	logical restore 85
macro 580		cataloging data sets 74
from an application program 25	1	data sets with phantom catalog
JCL examples 257 using ISMF 25	L ACTOC	entries 90 preformatted empty VSAM data
using JCL 25	LASTCC	set 91
invoking ISMF 25	definition 505 in IF-THEN-ELSE command	renaming data sets 74
IOERROR subkeyword	sequence 507	user catalog aliases 79
COPY command 357	in SET command 506	without preallocated targets 81
DUMP command 421	LDS, supported 14	LOGICALVOLUME keyword 76
PRINT command 437	LE operator 22, 263	COPYDUMP command 372
IPL tame	like devices, moving volumes to 139	RESTORE command 471
tape rewinding and unloading 527	line operators, DFSMSdss/ISMF 28	LOGINDDNAME keyword COPY command 341
IPLing Stand-Alone Services on a	LINECNT keyword 255 Linux copy	DUMP command 411
stand-alone system 518	COPYDUMP command 195	logical processing 17
ISMF (Interactive Storage Management	full volume 195	LOGINDYNAM keyword
Facility)	Linux dumps	COPY command 341
display panels 25	ALLEXCP keyword 189	DUMP command 412
function protection 27	DATASET keyword 189	logical processing 17
invoking 25 line operators 28	FULL keyword 189	LRECL and BLKSIZE keywords, specifying in a print operation 436
logging on 25	using concurrent copy 189	LT operator 22, 263
menu-driven panels 25	Linux for System z authorization 187	21 operator <b>22, 2</b> 00
module names 28	backing up with partitions 185	
online panels 25	DFSMSdss command	M
PERMIT command 29	BUILD STAND-ALONE 185	magnetic tape devices supported 13
protecting modules 29	COPY FULL 185	maintenance 581
RDEFINE command 29 use and examples 25	COPY FULL COPYVOLID	MAKEMULTI keyword
volume list 97	ALLEXCP 185 COPYDUMP 185	COPY command 343
votanie not ">	DUMP DATASET 185	RESTORE command 472
	DUMP FULL 185	management class 3 changing with copy 125
J	DUMP FULL with CONCURRENT	changing with RESTORE 88
JCL (job control language)	COPY 185	mapping macro, ADREID0 607
concurrent copy 426, 431	RESTORE DATASET 185	MAXCC keyword
EXEC statement 253	RESTORE FULL 185	definition 505
filter DD statement 254	disk utility dasdfmt 186	in IF-THEN-ELSE command
input DD statement 253	fdasd 187	sequence 507
invoking DFSMSdss 25, 257 JOB statement 252	hardware environment 185	in SET command 506
output DD statement 253	restoring partitions 185	maximize track utilization by reblocking 164
password DD statement 254	submitting JCL batch jobs to z/OS	MAXMOVE keyword 159
requirements for DFSMSdss 252	using FTP 195	MAXMOVE keyword (DEFRAG
restore integrated catalog facility user	volume serial rules 186	command) 383
catalog 80	LIST subkeyword	MAXSIZE variable 182
SYSIN DD statement 253	DEFRAG command 376, 380 location-dependent data 71, 81	MAXTIME keyword
SYSPRINT DD statement 253	locking a user catalog 79	CONSOLIDATE command 291
volume count subparameter 253	lockout, avoiding 562, 563	MAXTIME keyword (DEFRAG
job control language 25, 252 JOB statement JCL 252	LOGDDNAME keyword (RELEASE	command) 384 MENTITY keyword
JOBCAT DD statement, JCL 77	command) 446	COPY command 344
, , , , , , , , , , , , , , , , , , , ,	logging on to ISMF 25	RESTORE command 472
		message data set 15, 538

MGMTCLAS keyword 22, 86	multivolume data set (continued)	NULLMGMTCLAS keyword (continued)
COPY command 344 RESTORE command 472	conversion 147, 149	COPY command 344 RESTORE command 472
MGMTCLAS profile 263, 540	copying 118 discrete profile 539	NULLSTORCLAS keyword 86
migrated data sets, backup 6	dumping 45	COPY command 355
minivolumes 13	restore 78	RESTORE command 486
MINSECQTY keyword 151	restoring 118	RESTORE Continued 400
MINSECQTY keyword (RELEASE	multivolume VSAM data sets 86, 118	
command) 448	MVOLSER keyword	0
MINTRACKSUNUSED keyword 151	COPY command 344	
MINTRACKSUNUSED keyword	RESTORE command 472	ONLYINCAT keyword
(RELEASE command) 448	MVS environments supported 11	COPY command 339
MMOVPCT keyword (DEFRAG		DUMP command 414 RELEASE command 446
command) 385		OPEN/EOV
MMOVPCT option 160	N	nonspecific tape volume mount –
mode switching 504	names, data set 20	eioption 17 595
module names for data set application	navigation	tape volume security and verification
commands 28	keyboard 651	exit – eioption 16 595
moving	NE operator 22, 264	operating environment 11
catalogs 115	nested IF commands 509	operating in serial or parallel mode 504
damaged PDS 120	NEWNAMEUNCONDITIONAL keyword	OPERATIONS attribute 531, 532
data in an SMS-managed environment 8	description 39	OPERCNSL parameter (Stand-Alone
data sets 98	DUMP command 413	BUILDSA command)
preformatted empty VSAM 129	FACILITY class profile 533	limited validation of 513
special requirements 114	non-SMS authorization 547	purpose of 513
utilities 105	non-SMS-managed data sets,	specifying 273
data sets to unlike devices 121	restoring 90	OPTIMIZE keyword 55
direct access data set 121	non-SMS-managed targets, special	OPTIMIZE keyword (DUMP
empty non-VSAM data sets 114	considerations 149	command) 414
generation data sets	non-SMS-managed volumes, moving generation data sets to 123	option list 577 optional parameters 272
to non-SMS-managed	non-VSAM data sets that have	options for non-VSAM data sets, enqueue
volumes 123	aliases 47, 81, 116	exit routine 564
to SMS-managed volumes 122	non-VSAM data sets, converting to	options installation exit routine 5
multivolume data set 116	multivolume 86	OPTPTR parameter 577
non-VSAM data sets that have aliases 116	non-VSAM data sets, restore actions 492	organizations, data set 14
PDSE 119	non-VSAM preallocation 127	original record length 588
SMS-managed data sets 123	nonindexed VTOC 13	original record pointer 588
system data sets 115	NONSMS keyword (CONVERTV	OUTDDNAME keyword 72, 101
to preallocated data set 126	command) 296	COPY command 346
undefined DSORG data sets 114	NOPACKING keyword	COPYDUMP command 373
unmovable data sets 120	COPY command 345 RESTORE command 473	DUMP command 415
volumes		PRINT command 436 RESTORE command 473
logical volumes 130	restoring to preallocated target data	OUTDYNAM keyword
physical volumes 131	to restore damaged partitioned data	COPY command 346
to devices of equal capacity 139	sets 85	RESTORE command 474
to devices of greater capacity 139	with preallocated target 128	OUTDYNAM parameter (Stand-Alone
to unlike devices 140	NOREADCHECK parameter	BUILDSA command) 274
VM-format volumes 140	(Stand-Alone RESTORE	OUTDYNAME keyword 72, 101
VTOC considerations 130	command) 525	output from DFSMSdss (in DD
moving data with concurrent copy 9	NORUN keyword 255	statement) 253
with FlashCopy 9	Notices 655	output tape I/O error – eioption 19 596
with SnapShot 9	notification	output volume
moving data sets 257, 324	data set processed exit – eioption	selecting 101
moving volumes	23 601	specifying 71, 77, 93
with FlashCopy 132	IMS volume user exit – eioption 26 604	OUTTRACKS keyword COPY command 347
with native SnapShot 138	volume – eioption 20 596	RESTORE command 475
MULTI keyword 22, 263	NOTIFYCONCURRENT keyword 300,	overview of DFSMSdss 3
multiple backup copies 371, 415	316	overview of the Stand-Alone Services
multiple subkeywords 250	NOVALIDATE keyword (DUMP	process 516
multiple target volumes	command) 414, 423	•
restoring 78	NOVERIFY parameter (Stand-Alone	
specifying 128 multiple tracks read, on dump 414	RESTORE command) 524	
multivolume data set 116	null command 508	
	NULLMGMTCLAS keyword 86	

P	physical data set copy	PRINT command (continued)
page ejection, suppressing 255	performing 100	syntax diagram 433
page-number list 578	using a conditioned volume 100	TOLERATE keyword 437
PAGENO keyword 255	physical full volume copy	TRACKS keyword 437
	FCINCREMENTAL keyword 60	VTOC keyword 438
PAGEPTR parameter 578	FCINCREMENTALLAST	WAIT keyword 439
PARALLEL command 11, 504	keyword 61	PRINT, access authorization for 555
for DFSMSdss 504	FCINCRVERIFY keyword 61	printers supported 13
PARALLEL keyword 55	FCWAIT keyword 61	printing SYSPRINT record – eioption
PARAM keyword 579	physical processing 17, 18	02 591
PARM information in the EXEC	physical restore 76, 79, 85	PROCESS keyword 114, 126
statement 254	INITIAL status 89	CONSOLIDATE command 292
partially qualified data set names 20,	output volume selection 77	COPY command 349
260	physical restore of SMS-managed data	DUMP command 417
partitioned data set 12	sets 89	RELEASE command 449
partitioned data set extended 12	physical tape record	RESTORE command 476
PASSDELAY option 160	backspace – eioption 25 603	processing
PASSDELAY subkeyword (DEFRAG	reading – eioption 03 592	logical 17, 18
command) 383	writing – eioption 06 593	physical 17, 18, 19
password DD, JCL statement 254	physical volume dump 50	protect-all 537
PASSWORD keyword	PHYSINDD 416	protected
COMPRESS command 282	PHYSINDDNAME keyword	catalogs 546
CONSOLIDATE command 291	CONSOLIDATE command 292	group data set 535
COPY command 347	PHYSINDYNAM 417	user data set 535
DEFRAG command 386	PHYSINDYNAM keyword	protecting
DUMP command 416	CONSOLIDATE command 292	data sets 533
PRINT command 436	planning an availability strategy 33	passwords 534
RELEASE command 449	preallocated data set	resources 533
RESTORE command 475	COPY command 126	
password protection 534		SMS-managed data sets 540
PATCH parameter definition 505	moving to 126	usage of DFSMSdss 533
PDS (partitioned data set) 14	REPLACE keyword 72 REPLACEUNCONDITIONAL	protection DFSMSdss function 27
abnormal conditions 85		DFSMSdss/ISMF modules 29
compressing 152	keyword 72	
monitoring PDSs during	restoring to 72	functions with RACF 27
compression 120	preallocated targets	ISMF access 27
moving damaged 120	restoring 81	keywords with RACF 29
prevention of 120	restoring without 81	PURGE keyword
repairs by DFSMSdss during	preallocation	COPY command 349
compression 120	non-VSAM 127	DUMP command 417
restoring, damaged 85	VSAM 126	RESTORE command 477
storage requirements 12	PREPARE keyword 10, 144	
supported 14	PREPARE keyword (CONVERTV	
translation during compression 120	command) 297	Q
PDS subkeyword (COPY command) 318	preparing for Stand-Alone Services 269,	qualified data set names 260
PDSE (partitioned data set extended)	528	1
moving 119	presenting	
restoring 84	ADRUFO record – eioption 13 595	R
supported 14	WTOR response – eioption 15 595	
PDSE subkeyword (COPY	PRINT command	RACF (Resource Access Control Facility)
command) 318	ADMINISTRATOR keyword 434	authorization checking 344, 472
PERCENTUTILIZED keyword	ALLDATA keyword 434	data set erase table for DEFRAG 164
COPY command 348	CPVOLUME keyword 434	database 159
RESTORE command 476	DATALENGTH keyword 434	DEFINE function 531
	DATASET keyword 435	keyword profiles 29
with a logical data set restore	DYNALLOC keyword 435	logging 540
operation 72	ENQFAILURE subkeyword 437	protecting keyword modules 29
with preallocated target 128	ERRORTRACKS keyword 435	protecting keywords 29
performance	explanation 432	RACF-indicated, meaning of 536
concurrent copy 55	for DFSMSdss 432	RACF-protected, meaning of 531
CONSOLIDATE command 155	INDDNAME keyword 435	RAMAC Virtual Array (RVA) 9, 41, 57,
DEFRAG command 155	INDYNAM keyword 435	113
DUMP 55	IOERROR subkeyword 437	RDEFINE command 29
read DASD I/O pacing 59	KEYLENGTH keyword 436	read I/O pacing, performance
performing a restore from dump	OUTDDNAME keyword 436	considerations 59
tapes 522	PASSWORD keyword 436	READCHECK parameter (Stand-Alone
PERMIT command 29	sample operations 439	RESTORE command) 525
phantom catalog entries 90	SHARE keyword 437	readers, card, supported 13
physical copy 97, 131		

RELEASE command (continued) RESTORE command (continued) reading disk track - eioption 07 593 module name 28 CATALOG keyword 462 ONLYINCAT keyword 446 logical tape record - eioption 04 592 changing management class 88 physical tape record - eioption PASSWORD keyword 449 changing storage class 87 03 592 PROCESS keyword 449 COPYVOLID keyword 463 SYSIN record - eioption 01 591 sample operations 451 CPVOLUME keyword 464 utility SYSPRINT - eioption 09 593 SPHERE keyword 450 CYL subkeyword of TGTALLOC 486 READIOPACING keyword 300, 303 STORGRP keyword 450 data set example 258 COPY command 350 syntax diagram 442 data sets with phantom catalog DUMP command 417 SYS1 subkeyword 449 entries 90 reblock installation exit routine 5 unused space in data sets 151 DATASET keyword 464 WAIT keyword 451 REBLOCK keyword DEBUG keyword 464 DEFERRED subkeyword of COPY command 350 RELEASE, access authorization for 555 RESTORE command 477 remote site 34 TGTGDS 487 REBLOCK keyword, with preallocated RENAME keyword (RESTORE **DELETECATALOGENTRY** target 129 command) 478 keyword 464 RENAME keyword, during logical restore REBLOCK processing direct data sets 81 processing 74 determining block size 164 DYNALLOC keyword 467 RENAMEUNCONDITIONAL keyword track usage 164 ENQFAILURE subkeyword 487 RECATALOG keyword COPY command 351 EXCLUDE keyword 467 COPY command 314 RESTORE command 480 explanation 452 during logical restore processing 74 with COPY command 102 FILTERDD keyword 468 RESTORE command 462 with preallocated target 129 filtering 71 with preallocated target 128 renaming data sets 102 for DFSMSdss 452 REPLACE keyword FORCE keyword 468 recataloging an alternate index 315 reclaiming DASD space 151 COPY command 352 FORCECP keyword 468 moving to preallocated target data record area length 588 FREESPACE keyword 469 sets 126 record counting for copy, dump, and FULL keyword 469 restore 4 moving VSAM data sets 118 general description 6 IMPORT keyword 469, 559 record level sharing preallocated data set 72 backing up data sets 49 RESTORE command 481 INCLUDE keyword 470 copy operation 129 SMS-managed data set 87 INDDNAME keyword 471 moving data sets 129 unmovable data set 82 indexed sequential data sets 81 REPLACEUNCONDITIONAL keyword time out protection 49 logical 70, 71 records past last-used-block pointer, COPY command 353 LOGICALVOLUME keyword 471 moving to preallocated target data MAKEMULTI keyword 472 dumping 48 MENTITY keyword 472 recovery sets 126 disaster 34 moving VSAM data sets 118 MGMTCLAS keyword 472 SMS-managed environment 34 preallocated data set 72 module name 28 RESTORE command 353, 483 MVOLSER keyword 472 system volumes 94 user catalog 79 SMS-managed data sets 87 non-VSAM data sets 81 REDETERMINE keyword 146 unmovable data set 82 NOPACKING keyword 473 REDETERMINE keyword (CONVERTV REPRO (IDCAMS command) 106 NULLMGMTCLAS keyword 472 command) 297 requirements NULLSTORCLAS keyword 486 REFDT keyword 22, 263 real storage for Stand-Alone Services OUTDDNAME keyword 473 refreshing volumes program operation 511 OUTDYNAM keyword 474 with incremental FlashCopy 60 RESERVE macro OUTTRACKS keyword 475 PASSWORD keyword 475 RESET keyword relative generation filtering 262 RELBLOCKADDRESS keyword 82, 121 RESTORE command 484 PERCENTUTILIZED keyword 476 COPY command 351 RESET keyword (DUMP command) 418 physical 70, 76 RESTORE command 478 Resource Access Control Facility 29, 531 preallocated target data sets 72 RELEASE command 20 resource serialization 570 printed output ADMINISTRATOR keyword 444 RESOWNER field 540 produced by integrated catalog facility user catalog 80 BY keyword 444 RESTORE command 10, 19, 70, 71 PROCESS keyword 476 cross-system serialization 445 absolute track data set 81 DDNAME keyword 444 access authorization for 555 PURGE keyword 477 definition 10, 441 actions on non-VSAM data sets 492 REBLOCK keyword 477 DYNALLOC keyword 445 ACTIVE subkeyword of RECATALOG keyword 462 DYNAM keyword 445 TGTGDS 487 RELBLOCKADDRESS keyword 478 EXCLUDE keyword 445 ADMINISTRATOR keyword 460 RENAME keyword 478 FILTERDD keyword 338 **AUTORELBLOCKADDRESS** RENAMEUNCONDITIONAL keyword 480 for DFSMSdss 441 keyword 460 INCAT keyword 446 BCSRECOVER keyword 460 REPLACE keyword 481 INCLUDE keyword 446 BLK subkeyword of TGTALLOC 486 REPLACEUNCONDITIONAL LOGDDNAME keyword 446 BY keyword 461 keyword 353, 483 BYPASSACS keyword 461 MINSECQTY keyword 448 RESET keyword 484 MINTRACKSUNUSED keyword 448 CANCELERROR keyword 462

Index 683

RESTORE command (continued)	REWIND parameter (Stand-Alone	setting (continued)
ROLLEDOFF subkeyword of	TAPECNTL command) 527	patch bytes with SET PATCH
TGTGDS 487	RIOP keyword 300, 303, 306	command 506
SAM compressed data set 90	RLS quiesce processing 49, 129	SHARE keyword
sample operations 495	ROLLED-OFF state 90, 122	COPY command 354
SHARE keyword 484	ROLLEDOFF subkeyword of TGTGDS	DUMP command 419
SOURCE subkeyword of	COPY command 356	PRINT command 437
TGTALLOC 486	RESTORE command 487	RESTORE command 484
SOURCE subkeyword of	RRDS data sets, supported 14	SHARE keyword, with backup function
TGTGDS 487	running Stand-Alone Services	for HFS 44
special considerations 453	in 370 mode 511	shortcut keys 651
SPHERE keyword 485	in XA or ESA mode 512	simulating conversion 144
STORCLAS keyword 486	program 516	SIZE keyword 255
syntax diagram 454	under VM 512	SIZE variable 182
TGTALLOC keyword 486	with a predefined console 513	SMS
TGTGDS keyword 487	RVA 317	authorization 547
TOLERATE keyword 487	RVA (RAMAC Virtual Array) 9, 41, 57,	keyword (CONVERTV
TRACKS keyword 487	113	command) 298
TRK subkeyword of TGTALLOC 486		managed data sets 540
TTRADDRESS keyword 488		SMS conversion
UNDEFINEDSORG subkeyword 476	S	eligibility 142
unmovable data sets 81		ineligibility 141, 142
variables passed to ACS routines 181	SADMP service aid 521	SMS management
VOLCOUNT keyword 489	SAF (system authorization facility) 531	conversion by data movement 142
WAIT keyword 491	SAM compressed data set, copying 300	conversion from, by data
WRITECHECK keyword 491	SCAN keyword 256	movement 143
restore operation	SDM (system data mover) 57	conversion to and from 9
data set	SDUMP keyword 255	conversion without data
key-sequenced with no secondary	search order, standard catalog 267 security	movement 145
allocation 453	for tape backups 63	converting from, without data
partitioned with secondary	SELECTMULTI keyword	movement 148
allocation of zero 453	CONVERTV command 297	converting to and from 141
RACF-protected VSAM, logical	DUMP command 342, 412	SMS Report 146
restore of 453	with backup function 45	SMS-managed data sets
RENAME,	with conversion function 147, 149	backup 49
RENAMEUNCONDITIONAL,	with COPY DATASET function 101	moving 123
REPLACE keywords 453	with COPY function 17, 116	physical RESTORE 89
restoring	sending comments to IBM xix	restoring 86
backups created with an earlier	separator, definition 249	restoring, GDG data sets 90
release 649	sequential data sets, supported 14	SMS-managed environment
damaged PDS 85	sequential data striping	backup 34
data sets 70	extended sequential 4	moving data 8
direct access data sets 82	VSAM data sets 4	Non-SMS-managed data 34
extended-format VSAM data set	sequential extended-format data sets	recovery 34
stripe count of one 83	processing 4	restoring data sets 85
GDG data sets 90	support for 4	SMS-managed data 34
in an SMS-managed environment 86	SERIAL command 504	SMS-managed volumes, moving data sets
multivolume data sets 118	for DFSMSdss 504	to 122
non-SMS-managed data set 90	serialization 161	SMSGCNT keyword 255
PDSE 84	avoiding lockout 562	SnapShot 9
preallocated targets 72, 81	concurrent copy 7	authorization checking 138
preformatted empty VSAM data set 91	data integrity 561	DEBUG(FRMSG keyword 114, 158
SMS-managed data sets 86, 89	data set 563	DEBUG(FRMSG keyword, volume 138
SMS-managed GDG data sets 90	DYNALLOC keyword 566	in conjunction with
undefined DSORG data sets 83	ENQ keyword 563	physical full volume copy 51
volumes 92	Read/Write scheme 566	moving data sets with SnapShot 113
VSAM cluster 84	RESERVE macro 561	moving volumes with native
VSAM sphere 83	resource 570	SnapShot 138
without preallocated targets 81	volume 561	native mode 9, 113
restoring volumes	WAIT option 563, 569	problem solving 114, 158
with incremental FlashCopy 60	service 581	problem solving, volume 138
restriction	SET command	RAMAC Virtual Array (RVA) 41, 108
copying an extended-format VSAM	for DFSMSdss 505	reducing backup time 51, 87
data set	sample operations 506	virtual concurrent copy 41, 87
stripe count of one 118	setting	virtual concurrent copy mode 41,
•	condition codes 505	108, 113

SOURCE subkeyword of TGTALLOC	Stand-Alone Services feature (continued)	Stand-Alone Services feature (continued)
COPY command 356	core image (continued)	syntax
RESTORE command 486, 487	specifying the output DASD	BUILDSA command 272
SOURCE subkeyword of TGTGDS	volume 274	RESTORE command 523
COPY command 356	DASD	TAPECNTL command 527
source, definition 253	devices in 370 mode 511	tape
space	devices in XA or ESA mode 512	library, setup Stand-Alone
considerations 54	target device address,	feature 514
fragmentation on DASD 155	specifying 524	library, transient mount 515
management 10	dump data set	mount and demount
space allocation 356, 486	device address, specifying 523	procedures 514
space efficient FlashCopy 134, 237	device type, specifying 523	tape library
space efficient volume 134	examples	setup Stand-Alone device
space fragmentation on DASD 374	BUILDSA command 275	feature 514
space utilization, percent	copying the Stand-Alone Services	transient mount feature 514
COPY command 348	core image 275	TAPECNTL command
RESTORE command 476	IPL 519	description 527
SPECIAL attribute 531	RESTORE command 525	DEVTYPE parameter 527
special considerations for	TAPECNTL command 528	example 528
non-SMS-managed target 149	operator console	required parameters 527
special requirements	potential problems 513	REWIND parameter 527
conversion from SMS 148	predefining 511, 512, 513	syntax 527
conversion to SMS 146	optional parameters	UNITADDR parameter 527
data set backup 44	RESTORE command 524	UNLOAD parameter 528
moving data sets 114	predefined console	using
restoring data sets 78	potential problems with 521	tape library 513
specified operating environment 11	purpose of 513	standard catalog search order 267
sphere eligibility 146	required parameters	standard naming conventions 537
SPHERE keyword 47, 83, 118, 119	BUILDSA command 272	STARTTRK parameter (Stand-Alone
COPY command 354	RESTORE command 523	RESTORE command) 524
DUMP command 420	TAPECNTL command 527	startup function – eioption 00 590
RELEASE command 450	RESTORE command	statistical information 26
RESTORE command 485	description 522	status assignment, GDG data sets 356,
sphere processing, VSAM eligibility 146	ENDTRK parameter 524	487
spheres	example 525	STEPCAT DD statement 77
dumping VSAM 47	FILE parameter 525	STGADMIN.ADR.COPY.FCSETGT profile
restoring VSAM 83	FROMADDR parameter 523	FCSETGTOK keyword 533
stand-alone restore program	FULL parameter 524	storage
overview 8	NOREADCHECK parameter 525	administrator 541
physical processing 19	NOVERIFY parameter 524	storage class 3
system volumes, backing up 19	optional parameters 524	changing with COPY 124
system volumes, recovering 94	READCHECK parameter 525	changing with RESTORE 87
used to restore Linux volumes 195	required parameters 523	storage group 4
VM, running on 94	STARTTRK parameter 524	Storage Management Subsystem,
volume dump, physical 51	syntax 523	converting to and from 141
Stand-Alone Services feature 272	TAPEVOLSER parameter 525	storage requirements
BUILDSA command	TOADDR parameter 524	DFSMSdss 11
ADMINISTRATOR parameter 529	VERIFY parameter 524	PARALLEL command, effect of 11
determining authorization	specifying	PDS (partitioned data set) 12
level 528	information for the Stand-Alone	per command
examples 275	Services core image 272	above 16MB 12
INDDNAME parameter 272	the DASD target device	below 16MB 12
IPL parameter 273	address 524	VSAM data set 12
OPERCNSL parameter 273	the dump data set device	STORCLAS keyword 22, 86
OUTDDNAME parameter 274	address 523	COPY command 355
OUTDYNAM parameter 274	the dump data set device	RESTORE command 486
required parameters 272	type 523	STORCLAS profile 540
syntax 272	the input device 518	STORGRP keyword
commands	the JCL output location for	COPY command 355
BUILDSA 271	IPL-able core image 274	DUMP command 420
RESTORE 522	the message output device 518	logical processing 17
TAPECNTL 527	the output DASD volume for	RELEASE command 450
core image	IPL-able core image 274	striped data sets, supported 14
definition of 269, 528	where Stand-Alone Services is	structure, exit interface 585
specifying information for 272	IPLed from 271	subkeywords
specifying the JCL output location	supported	maximum number 250
for 274	platforms 511	multiple 250
	r	

subkeywords (continued)	tape (continued)	TSO FCWITHDRAW (continued)
specifying 250	volume security OPEN/EOV –	withdrawing FlashCopy relationship,
summary of changes xxi	eioption 16 595	volume 133
Summary of changes xxi	writing logical record – eioption	TTRADDRESS keyword 82, 121
supported	05 593	COPY command 359
platforms for Stand-Alone	writing physical record – eioption	RESTORE command 488
Services 511	06 593	TYPRUN keyword 255, 256
supported devices 14, 93	tape devices (with Stand-Alone Services)	111 KOTV Key Word 200, 200
	in 370 mode 511	
suppressing page ejection 255		11
switching modes 504	in XA or ESA mode 512	U
syntax 306	tape devices supported 13	UAPTR parameter 579
syntax diagram	TAPEVOLSER parameter (Stand-Alone	UIMPTR parameter 578
CONSOLIDATE command 284	RESTORE command) 525	UNCATALOG keyword
CONVERTV command 294	target allocation 486	COPY command 359
COPY command 300	target class selection 494	DUMP command 423
COPYDUMP command 372	target definition 253	uncataloged data set 24
DEFRAG command 374	target volume 8, 124	
DUMP command 391	task processing, controlling 504	undefined DSORG data sets
PRINT command 433	TASK-ID 585	moving 114
reading a 251	temporary	restoring 83
RELEASE command 442	data set 538	UNDEFINEDSORG subkeyword
RESTORE command 454	data set names 538	COPY command 349
SYS1 subkeyword	message data set 538	RESTORE command 476
COPY command 349	temporary copied catalogs 16	UNITADDR parameter (Stand-Alone
DUMP command 417		TAPECNTL command) 527
	temporary data set 15, 148	universal access authority (UACC) 27
RELEASE command 449	temporary data set names 15	unlike devices 131
SYS1.ANTMAIN.SNAPnnnn data	temporary work space 98	moving volumes 140
sets 57	TEST keyword 145	UNLOAD parameter (Stand-Alone
SYSALLDA 98	TEST keyword (CONVERTV	TAPECNTL command) 528
SYSDA 98	command) 298	unloading a tape with the TAPECNTL
SYSIN	TGTALLOC keyword	command 527
DD statement, JCL 253	COPY command 356	unmovable data set
record, reading – eioption 01 591	RESTORE command 486	
SYSPRINT	TGTGDS keyword	moving 120
DD statement, JCL 253	COPY command 356	REPLACE keyword 82
reading utility – eioption 09 593	RESTORE command 487	REPLACEUNCONDITIONAL
record printing – eioption 02 591	THEN command 508	keyword 82
writing record – eioption 10 594	TMPMSGDS keyword 255	restoring to preallocated targets 82
system	TOADDR parameter (Stand-Alone	unused space, releasing 151
authorization facility 531	RESTORE command) 524	unwanted data sets, deleting 152
programming information 584	TOL(ENQF) keyword, with backup	USEEXCP keyword 256
1 0 0	function for HFS 44	User
system consoles supported 13		area list 579
system data mover (SDM) 57	TOLERATE keyword	Area Pointer 588
system data set	COPY command 357	Exit Allowance 585
dumping 48	DUMP command 421	Return Code 586
moving 115	PRINT command 437	user catalog, moving 115
system environment 11	RESTORE command 487	User Interaction Module (UIM)
system requirements 11	TRACE keyword 255	example 629
system volumes	track utilization, maximize by	list 578
backing up 51	reblocking 164	sample output 640
recovering 94	TRACKS keyword	* *
	COPY command 358	user interaction module exit
	DUMP command 422	functions 26
T	physical processing 18	user interface
•	PRINT command 437	ISPF 651
tape	RESTORE command 487	TSO/E 651
libraries not supported in 370	tracks read, on dump 414	using SIZE and MAXSIZE variables 182
mode 511	trademarks 657	utilities
mount and demount procedures 514		in data set copy operation 105
output I/O error – eioption 19 596	TRK subkeyword of TGTALLOC	moving data sets 105
physical record backspace – eioption	COPY command 356	utilization, percent
25 603	RESTORE command 486	COPY command 348
reading logical record – eioption	TSO FCWITHDRAW	RESTORE command 476
04 592	freeing subsystem resources 112	UTILMSG keyword 256
reading physical record – eioption	freeing subsystem resources,	
03 592	volume 133	
volume mount OPEN/EVOC	withdrawing FlashCopy	
nonspecific – eigntion 17 595	relationship 112	

nonspecific – eioption 17 595

V	volume dump	writing (continued)
VALIDATE keyword 48	reducing backup with volume	WTOR message – eioption 12 594
record counting 4	copy 51	Writing to the Operator command
VALIDATE keyword (DUMP	volume list, ISMF 97	for DFSMSdss 503
command) 423	volume serial rules	WTO
variable length (VL) parameter 579	for Linux volumes 186	command 503
verification	volumes	message writing – eioption 11 594
bypass exit – eioption 22 597	using incremental FlashCopy 60	WTOR
data set – eioption 21 597	VSAM (virtual storage access method)	command 503
exit, OPEN/EOV – eioption 16 595	cluster, restoring 84 data set	message writing – eioption 12 594, 595
VERIFY parameter (Stand-Alone	converting 86, 118	WTOR command
RESTORE command) 524	copying 118	for DFSMSdss 503
VERSION1 keyword 160	dumping 48	101 101 101 101 101 101 101 101 101 101
DEFRAG command 387	moving 118	
versions of DFSMSdss,	moving preformatted empty 129	X
compatibility 649	restoring preformatted empty 91	= =
virtual concurrent copy 317	storage requirements 12	XABUFF keyword 256
defined 7	preallocation 126	
SnapShot 7	sphere	-
virtual concurrent copy mode 9	dumping 47	Z
virtual concurrent copy working	eligibility 146	ZBUFF64R keyword 256
space 57	restoring 83	ZCOMPRESS keyword
virtual input/output (VIO) device	VSAM (Virtual Storage Access Method)	DUMP command 425
supported 13	data set	zFS data sets
virtual storage access method 47	filtering 259	DUMP command considerations 419
vital records 6, 18, 33, 36	restore actions on 492	logical data set COPY 300
VL parameter 579	VTOC	logical dump and serialization 565
VM minivolumes 41	indexed 13	physical dump and serialization 565
VM-format volumes	keyword (PRINT command) 418, 438	read/write serialization scheme 566
backing up 51	nonindexed 13	RELEASE command
moving 140	VTOC Index 14	consideration 442
recovering 94		
with DFSMSdss 14		
VM, running Stand-Alone Services under 512	W	
	WAIT keyword 160	
VOLCOUNT keyword	WAIT keyword 160 COMPRESS command 282	
VOLCOUNT keyword COPY command 359	WAIT keyword 160 COMPRESS command 282 CONSOLIDATE command 292	
VOLCOUNT keyword COPY command 359 RESTORE command 489	COMPRESS command 282	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume	COMPRESS command 282 CONSOLIDATE command 292	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selection 71, 77	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selection 71, 77 output, specifying 93	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144 selecting target 124	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491 writing	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144 selecting target 124 serialization 561	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491 writing disk track – eioption 08 593	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144 selecting target 124 serialization 561 system, recovering 94	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491 writing disk track – eioption 08 593 logical tape record – eioption 05 593	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144 selecting target 124 serialization 561 system, recovering 94 VM-formatted 14	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491 writing disk track – eioption 08 593 logical tape record – eioption 05 593 physical tape record – eioption	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144 selecting target 124 serialization 561 system, recovering 94 VM-formatted 14 volume consideration 237	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491 writing disk track – eioption 08 593 logical tape record – eioption 05 593 physical tape record – eioption 06 593	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144 selecting target 124 serialization 561 system, recovering 94 VM-formatted 14 volume consideration 237 volume copy	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491 writing disk track – eioption 08 593 logical tape record – eioption 05 593 physical tape record – eioption 10 594	
VOLCOUNT keyword COPY command 359 RESTORE command 489 volume backup 5, 33, 50 broken 19 conversion without data movement 10 copy and dump combining 51 DUMP with concurrent copy 426 formats supported by DFSMSdss 13 input, specifying 99, 100 line operator module names 28 logical copy operation 130 logical dump 50 multiple target 128 multiple target, restore 78 notification – eioption 20 596 output, selecting 101 output, selecting 101 output, specifying 93 physical copy 131 physical dump 50 preparing for conversion 144 selecting target 124 serialization 561 system, recovering 94 VM-formatted 14 volume consideration 237	COMPRESS command 282 CONSOLIDATE command 292 COPY command 361 DEFRAG command 387 DUMP command 424 PRINT command 439 RELEASE command 451 RESTORE command 491 WAIT option 563, 569 wait-state codes for Stand-Alone program 520 when to use logical processing 18 physical processing 19 work space 98 working space data set 57 WORKUNIT keyword 256 WORKVOL keyword 256 WRITECHECK keyword CONSOLIDATE command 293 COPY command 362 DEFRAG command 387 RESTORE command 491 writing disk track – eioption 08 593 logical tape record – eioption 05 593 physical tape record – eioption 06 593	

# IBM.

Product Number: 5650-ZOS

Printed in USA

SC23-6868-02

