

 > WebSphere Service Registry and Repository > WebSphere Service Registry and Repository 7.5.0 > WebSphere Service Registry and Repository > Installing > Configuring Business Space for WSRR 7.5.0.2 > Setting up security for Business Space > Designating HTTP or HTTPS settings for Business Space






## Designating HTTP or HTTPS settings for Business Space Version 7.5.0 ▾


Business Space is configured to be accessed by HTTPS by default. If you want to change to HTTP, or you want to change back to HTTPS from a previous setting, use the `configBSpaceTransport.py` script.

### About this task

 **Start of change** The `configBSpaceTransport.jy` script is located in the `install_root\BusinessSpace\scripts` directory. Use the `allowhttp` value to change the `web.xml` to allow HTTP and HTTPS connections. Use the `httpsonly` value to change `web.xml` to allow only HTTPS and to redirect HTTP to HTTPS. Run the script on your stand-alone server or on the deployment manager for a clustered environment.  **End of change**

### Procedure

-  **Start of change** Locate the script `install_root\BusinessSpace\scripts\configBSpaceTransport.py` for designating HTTP or HTTPS settings.  **End of change**
-  **Start of change** Open a command prompt, and change directories to the following directory: `profile_root\bin`, where `profile_root` represents the directory for the profile where Business Space is installed.  **End of change**
-  **Start of change** Run the `configBSpaceTransport.py` with one the following options.
  - To allow HTTP connections to Business Space, type the following command: `wsadmin -lang jython -user user_name -password password -f configBSpaceTransport.py -allowhttp` (allows both HTTP and HTTPS).
  - To allow only HTTPS connections to Business Space, run: `wsadmin -lang jython -user user_name -password password -f configBSpaceTransport.py -httpsonly` (switches back to the default configuration, which always redirects HTTP to HTTPS).

 **Start of change**

By default, the command applies to the current server name and node name, or on the current cluster, where you are running the command. If you want to designate a different location, use the optional `-serverName` and `-nodeName` parameters or the `-clusterName` parameter.

**Note:** When the path contains a space, for example, if `install_root` is `My install dir`, you must enclose the path names in quotation marks.

 **End of change**  **End of change**

Parent topic: [Setting up security for Business Space](#)