

Updates to DB2 Cloning Tool V3.2 User's Guide

Abstract

Updates that apply to DB2® Cloning Tool Version for z/OS® 3.2 User's Guide (SC27-6556-01)

Content

The most recent update is listed first.

Update 2

Date of change: February 2017

Topics: Multiple

Change description: APAR PI70084 adds an option to the CKZDUTST REXX exec to select which objects in UT* status have the UT status removed. The valid parameter options are ALL and UTXX. ALL includes table and index spaces in UT* status, and UTXX includes only table and index spaces in UTRO, UTUT, and UTRW status.

The following topics were updated:

- Topic: "DB2UTILXCLEAN"
- Topic: "Step JCL example to identify objects with UT status"

Topic 1: "DB2UTILXCLEAN"

Update the following paragraph:

The CKZDUTST member of SCKZJCL can be used to run a REXX exec that identifies the table and index spaces in UT status and generates –STA DB(xxx) SP(yyy) ACCESS(FORCE) commands for the objects. These commands can be run to remove the UT status. The valid parameter options are ALL and UTXX. ALL includes table and index spaces in UT* status, and UTXX includes only table and index spaces in UTRO, UTUT, and UTRW status.

Topic 2: "Step JCL example to identify objects with UT status"

Update the JCL example and annotation of this topic as follows:

```
//?????? JOB , 'CKZ CKZDUTST', CLASS=A, MSGCLASS=X
//S1      EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
      DEL HLQ?.WRK.UTSTCMDS
      SET MAXCC=0
1 //S2      EXEC PGM=IKJEFT01, REGION=6M, PARM='CKZDUTST DB2T,ALL'
2 //STEPLIB  DD DISP=SHR, DSN=DSNXXX?.SDSNLOAD
3 //SYSEXEC  DD DISP=SHR, DSN=HLQ?.SCKZPARM
//SYSTSIN   DD DUMMY
//SYSTSPRT  DD SYSOUT=*
4 //CMDOUT   DD DSN=HLQ?.WRK.UTSTCMDS,
```

```
//          UNIT=SYSDA,DISP=(,CATLG),
//          DSORG=PS,LRECL=80,RECFM=FB,BLKSIZE=0,
//          SPACE=(TRK,(1,1))
///*
//** IF IT IS DESIRED TO EXECUTE THE GENERATED COMMANDS THE
//** FOLLOWING STEP CAN BE UNCOMMENTED AND USED.
///*
//**IF1  IF  (S2.RC LE 4) THEN
5 //S3      EXEC PGM=IKJEFT01,REGION=6M
//STEPLIB  DD  DISP=SHR,DSN=DSNXXX?.SDSNLOAD
//SYSTSPRT DD  SYSOUT=*
//SYSTSIN  DD  DISP=SHR,DSN=HLQ?.WRK.UTSTCMDS
///*
//**IF1  ENDIF
///*
//
```

1. Execution of CKZDUTST REXX exec. DB2T is the target DB2 system to use. ALL is an optional parameter that selects all objects with UT* status. To select only objects with UTRO, UTUT, or UTRW status, specify UTXX. If omitted, ALL is the default.