

IBM AIX 7.2 with Technology Level 5

Release Notes



Note

Before using this information and the product it supports, read the information in [“Notices” on page 19.](#)

First edition (November 2020)

This edition applies to IBM® AIX® 7.2 with Technology Level 5 and to all subsequent release and modifications until otherwise indicated in new editions.

© **Copyright International Business Machines Corporation 2020.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

- About this document.....V**
 - Highlighting.....v
 - Case sensitivity in AIX.....v
 - ISO 9000.....v

- IBM AIX 7.2 with Technology Level 5 Release Notes..... 1**
 - Read before installing..... 1
 - Installation tips.....1
 - Software license agreements.....1
 - Software Maintenance Agreement.....1
 - Fixes and problem-solving databases..... 1
 - Security advisories..... 1
 - Speculative-execution mitigation.....1
 - System requirements.....2
 - Required hardware..... 2
 - Firmware.....2
 - Memory requirements.....3
 - Paging space requirements.....4
 - Disk requirements.....4
 - Disk capacity.....5
 - VPM throughput mode changes for Power10.....5
 - Installing.....6
 - Installing AIX 7 with 7200-05..... 6
 - Network Installation Management..... 7
 - Java Technology Edition.....7
 - New filesets..... 8
 - Fileset changes.....9
 - Migrating..... 10
 - IBM License Metric Tool.....11
 - IBM PowerSC Trusted Surveyor.....11
 - Reliable Scalable Cluster Technology (RSCT)..... 11
 - DSM.....11
 - Thin Servers.....11
 - IBM Subsystem Device Driver.....11
 - Db2 migration.....12
 - Configuring.....12
 - Dynamic queue depth for MPIO devices.....12
 - libusb library.....12
 - Thin provisioning.....12
 - Diagnostics tasks.....13
 - Limitations and restrictions.....13
 - Upgrading IBM Security Verify Directory.....13
 - AIX 7.2 Enterprise Edition 1.1, or later.....13
 - OpenSSL version 3.0.....13
 - OpenSSH Version 8.1p1.....14
 - GSKit version requirement for NIST compliance.....15
 - nmon command changes.....15
 - Perl.....15
 - Code removed from AIX Version 7.2.....15
 - Licensed programs not supported in **AIX Version 7.2**.....15

CIFS client fileset.....	16
Shared processor partition virtual CPU limit.....	16
Additional information.....	16
IBM AIX Version 7.2 Documentation.....	16
IBM Hyperconverged Systems.....	16
AIX Dynamic System Optimizer.....	16
Linux SHA-256 and SHA-512 password cryptographic algorithm.....	16
Server-side support for new Unicode locales.....	17
Common Criteria administration guide.....	17
Notices.....	19
Privacy policy considerations.....	20
Trademarks.....	21

About this document

The Release Notes topics include late technical information that is not included in other topics, and they highlights new functions for the IBM AIX 7.2 with Technology Level 5 licensed program.

Highlighting

The following highlighting conventions are used in this document:

Bold	Identifies commands, subroutines, keywords, files, structures, directories, and other items whose names are predefined by the system. Bold highlighting also identifies graphical objects, such as buttons, labels, and icons that the you select.
<i>Italics</i>	Identifies parameters for actual names or values that you supply.
Monospace	Identifies examples of specific data values, examples of text similar to what you might see displayed, examples of portions of program code similar to what you might write as a programmer, messages from the system, or text that you must type.

Case sensitivity in AIX

Everything in the AIX operating system is case sensitive, which means that it distinguishes between uppercase and lowercase letters. For example, you can use the **ls** command to list files. If you type LS, the system responds that the command is not found. Likewise, **FILEA**, **FiLea**, and **filea** are three distinct file names, even if they reside in the same directory. To avoid causing undesirable actions to be performed, always ensure that you use the correct case.

ISO 9000

ISO 9000 registered quality systems were used in the development and manufacturing of this product.

IBM AIX 7.2 with Technology Level 5 Release Notes

Read before installing

Before you use this software, you must go to the [Fix Central](#) website and install the latest available fixes that address security vulnerabilities and other critical issues.

Installation tips

The latest installation hints and tips are available at the [IBM Power® server bulletins](#) website.

Software license agreements

There are instances where the software license agreements (SLA) might not be displayed correctly. In this event, the license agreements can be viewed for all languages at the [Software license agreements](#) website.

Software Maintenance Agreement

In AIX 7 with 7200-05, a separate Software Maintenance Agreement (SWMA) acceptance window displays during installation immediately after the license acceptance window. The response to the SWMA acceptance (accept or decline) is stored on the system, and either response allows the installation to proceed, unlike license acceptance, which requires an acceptance to proceed.

The **SWMA acceptance** window is displayed during a New Overwrite or Preservation installation from base CD media.

For base CD media New Overwrite or Preservation installations, if a nonprompted installation is wanted, the **ACCEPT_SWMA** field in the control_flow stanza of the bosinst.data file must be set to yes (to accept the SWMA terms) or no (to decline the SWMA terms). The **ACCEPT_SWMA** field is set to blank by default.

For NIM installations, if licenses are accepted either from the choices that are made when initializing the installation, or by using the **ACCEPT_LICENSES** field in a customized bosinst.data file, SWMA acceptance is constituted.

Fixes and problem-solving databases

You can download AIX fixes and search technical databases (including "APARS" and "Tips for AIX administrators") at the [Fix Central](#) website.

Security advisories

Security subscription services are available at the [My notifications](#) website.

After you subscribe to the AIX security advisories, you will receive the advisories by email when they are published.

Speculative-execution mitigation

AIX 7 with 7200-05 includes support for enhancing AIX software with mitigations against speculative-execution vulnerabilities. AIX applications and kernel extensions might use the new [cpu_context_barrier](#) and [cpu_speculation_barrier](#) services to protect against attacks from untrusted sources. For more information about these services, view their description on the IBM Documentation [Technical Reference](#) topic.

System requirements

Review the following information to determine the minimum and recommended system requirements that are needed to run AIX 7 with 7200-05.

Required hardware

Only 64-bit Common Hardware Reference Platform (CHRP) machines that are running selected POWER7®, POWER8®, POWER9™, and Power10 processors that implement the Power Architecture® Platform Requirements (PAPR) are supported.

To see whether you have a supported machine, log in to the machine as the root user, and run the following command:

```
prtconf | grep 'Processor Type'
```

Firmware

I/O devices IPL limitation

Because of a limitation on firmware memory size, only I/O devices in the first 144 I/O slots that are assigned to a logical partition or single system image partition can be used as an IPL (boot) source.

You can use the HMC to identify which devices are in the first 144 I/O slots by performing the following steps:

1. Select **Partition Properties > Hardware > I/O**.
2. Click the Bus column to sort the I/O devices in ascending order.

The first 144 I/O devices in the sorted list are in the bootable adapter slots.

If you are using a partition or single-system image partition with more than 144 assigned I/O slots, the following scenarios and their results and resolutions are possible.

Scenario	Result	Resolution
Attempting to boot from a device beyond the first 144 I/O slots for installation or diagnostic purposes.	The device is not selectable as a boot source from the SMS menus.	Use a device in the first 144 I/O slots.
Booting from a device in the first 144 I/O slots, and then attempt to select a target installation device in a slot beyond the first 144 I/O slots.	The boot succeeds to the installation menus, but devices beyond the first 144 I/O slots are not listed as bootable installation targets in the AIX menus.	Select a device that is available and marked as bootable.
Using an MPIO configuration where one adapter is in the first 144 I/O slots and another adapter is in a slot beyond the first 144 I/O slots. Both adapters are present at boot time.	The boot succeeds to the installation menus, and the device is listed as bootable in the AIX installation menus. The installation proceeds, but it fails with the bootlist command failure unable to set bootpath for all paths.	Use a device in the first 144 I/O slots for all paths.

Table 1. Scenarios for partitions with more than 144 assigned I/O slots (continued)

Scenario	Result	Resolution
Using DLPAR to add an adapter in a slot beyond the first 144 I/O slots, and then attempting to run the alt_disk_install command for the newly added device.	The device is not listed as bootable.	Use a device in the first 144 I/O slots.
Using DLPAR to add an adapter in a slot beyond the first 144 I/O slots, and by using the bootlist command to add the device as a bootable device (for example, by dynamically adding a redundant path to a current boot device or setting up for a network boot). Then removing the original adapter and rebooting.	The bootlist command succeeds, but the boot fails from the specified device, and AIX does not receive control.	Use a device in the first 144 I/O slots.
Using DLPAR to add an adapter whose probe order makes it displace a current bootable device, and then rebooting.	The boot fails, and AIX does not receive control.	Move the boot device to one of the first 144 I/O slots or remove the previously added device.
Selecting a device in a slot beyond the first 144 I/O slots as a dump device for a firmware-assisted dump.	The sysdumpdev command does not allow devices in slots beyond the first 144 I/O slots to be selected as firmware-assisted dump storage devices. An error occurs during the firmware-assisted dump configuration, and a traditional AIX dump automatically becomes available.	Use a device in the first 144 I/O slots for firmware-assisted dumps.
Using DLPAR to add an adapter whose probe order makes it displace a currently valid firmware-assisted dump target device, and then rebooting after the dump.	The firmware-assisted dump process fails during the boot process and displays an error message. The traditional AIX dump still runs to retrieve the dump image.	Avoid displacing the selected firmware-assisted dump target device or reconfiguring the sysdumpdev command for the firmware-assisted selection of dump target device, and specify a device within the first 144 I/O slots.
Using DLPAR to add an adapter whose probe order makes it displace a currently valid firmware-assisted dump target device, and then rebooting.	The sysdumpdev command does not allow devices in slots beyond the first 144 I/O slots to be selected as firmware-assisted dump storage devices. An error occurs during the firmware-assisted dump configuration, and a traditional AIX dump automatically becomes available.	Use a device in the first 144 I/O slots for firmware-assisted dumps.

Memory requirements

AIX 7 with 7200-05 requirements for minimum current memory vary, based on the configuration.

A minimum current memory requirement for AIX 7 with 7200-05 is 2 GB.

AIX 7 with 7200-05 requires the minimum current memory requirement to increase as the maximum memory configuration or the number of devices scales upward, or both. Larger maximum memory configurations or extra devices scale up the minimum current memory requirement. If the minimum memory requirement is not increased along with the maximum memory configuration, the partition hangs during the initial program load (IPL).

Host Ethernet Adapter memory requirements

Configurations containing a Host Ethernet Adapter (HEA) require more memory than the 2 GB minimum. Each logical HEA port that is configured requires an extra 102 MB of memory. The minimum memory requirement for configurations with one or more HEA ports that are configured, where n is the number of HEA ports, is 512 MB + $n \times 102$ MB.

Paging space requirements

AIX 7 with 7200-05 creates a 512 MB paging space (in the /dev/hd6 directory) for all new and complete overwrite installations.

Large page (16 MB/16 GB) zeroing enhancements

The contents of a large page (16 MB/16 GB) in shared memory regions are zeroed when the region is deleted. You can use the `pgz_mode` tunable that is available with the `vmo` command to reduce the time that is needed to zero the pages by zeroing the pages in a nonuniform memory access (NUMA) aware parallel manner by using multiple kernel threads. You can specify the following values for the `pgz_mode` tunable:

Serial mode

The default option for previous releases of the AIX operating system.

Synchronous parallel mode

Pages are deleted in parallel and in the context of the thread that initiated the deletion.

Asynchronous parallel mode

The thread that initiated the deletion, offloads the work of zeroing the pages in parallel to a kernel process and continues with the deletion process.

Large page (16 MB) pool creation and resizing enhancements

A 16 MB page pool is created and resized dynamically. This 16 MB pool is created by using the `lgpg_size` tunable and the `lgpg_regions` tunable that are part of the `vmo` command. You can use the `pgz_lpgrow` tunable that is available with the `vmo` command to reduce the time that is needed to create or resize the 16 MB page pool by zeroing the large pages in parallel and by using multiple kernel threads. You can specify the following values for the `pgz_lpgrow` tunable:

Serial mode

The default option for previous releases of the AIX operating system.

Synchronous parallel mode

Pages are zeroed in parallel and in context of the `vmo` command.

Asynchronous parallel mode

The `vmo` command offloads the work of zeroing the pages in parallel to a kernel process and continues to the next step in the pool creation or resizing process.

Disk requirements

AIX Version 7.2 requires a minimum of 20 GB of physical disk space for a default installation that includes all devices, the Graphics bundle, and the System Management Client bundle.

Disk usage

The following table displays disk usage statistics:

File system	Allocated (Used)
/	128 MB (49 MB)
/usr	2368 MB (2061 MB)
/var	192 MB (34 MB)
/tmp	128 MB (2 MB)
/admin	128 MB (1 MB)
/opt	64 MB (17 MB)
/var/adm/ras/livedump	256 MB (1 MB)

Note:

1. If the /tmp directory has less than 64 MB, it is increased to 64 MB during a migration installation so that the AIX 7 with 7200-05 boot image is successfully created at the end of the migration.
2. The boot logical volume must be of size 32 MB. The pre-migration script in the usr/lpp/bos directory on your media or in your NIM Shared Product Object Tree (SPOT) checks the storage space. During the migration operation, hd5 (the boot logical volume) is increased if necessary. The logical partitions must be contiguous and must be located within the first 4 GB of the disk.

Format the SCSI disk properly before you install the AIX operating system on it. The AIX operating system requires the disk to be formatted to a sector size supported by the attached SCSI controller. All AIX SCSI controllers support 512-byte sector SCSI disks. The 522-byte sector SCSI disks are supported only when they are attached to SCSI RAID controllers. If the disk is formatted for SCSI RAID, but is not attached to a SCSI RAID controller, the disk might not configure. If the disk does configure, it might be unreadable in the AIX environment. In some instances, the certify function and the format function in AIX diagnostics can be used to reformat the disk for the attached SCSI controller.

If any existing file system has a mount point in the /opt directory, or a mount point of /opt itself, the new logical volume, and file system are not created.

The AIX_FCPARRAY driver is not supported in AIX 7 with 7200-05. Before you migrate to AIX 7 with 7200-05, you must use the **manage_disk_drivers** command to convert any FCP array disks from the AIX_FCPARRAY driver to the AIX_AAPCM driver. The AIX_AAPCM driver supports Multiple Path I/O (MPIO) devices.

Disk capacity

SAS RAID controllers and Fibre Channel controllers support attached arrays and disks with capacities, which exceed 2 TB. The maximum supported capacity (beyond 2 TB) is limited by either the attached storage subsystem or the higher-level logical storage management.

For more information about SAS RAID controllers, see the [SAS RAID controller for AIX](#) topic.

For more information about AIX capacity limitations for logical storage, see the [Limitations for logical storage management](#) topic.

VPM throughput mode changes for Power10

When Power10 systems run in shared processor mode, the default value of the throughput mode for the virtual processor management (VPM) is 2. When you migrate the system to or from a Power10 system, and later, the AIX operating system automatically changes the default value of the throughput mode for the VPM. During boot operation, the AIX operating system selects the default value of the **vpm_throughput_mode** tunable parameter of the **schedo** command based on the type of server on which the LPAR is running. The value of the **vpm_throughput_mode** tunable parameter that is selected

by the AIX operating system is preserved and used on the destination server. On Power10 systems, you can switch to the recommended value of 2 for the **vpm_throughput_mode** tunable parameter by using the following command:

```
schedo -d vpm_throughput_mode
```

Note: When you migrate to or from a Power10 system, and later, it is recommended to move the operating system level to 7300-00, 7200-05-03-2147, 7200-04-05-2148, 7100-05-09-2148 or later. Without this feature that enables you to change the **vpm_throughput_mode** tunable parameter by using the **schedo** command, updating the operating system levels to 7200-05-00-2037, 7200-04-03-2038, and 7100-05-07-2037 might override the value set for the **vpm_throughput_mode** tunable parameter.

Installing

This section contains information about installing AIX 7.2 that supplements the information that is contained in the [Installation and Migration](#) topic.

Installing AIX 7 with 7200-05

The following methods can be used to install AIX 7 with 7200-05:

- Complete overwrite installation
- Preservation installation
- Migration installation

Note: After you install or migrate a system to AIX 7 with 7200-05, you can install a previous level of AIX by restoring a system backup or by performing a new and complete overwrite with base media. Preservation installations from AIX 7 with 7200-05 to a previous level of AIX are not supported.

Note:

Using the update media is recommended for updates. If you use the base media to update, install the `bos.dsc` fileset first by using the following command:

```
# installp -e /tmp/install.log -agXd software_source bos.dsc
```

If you use the base media to update, some ODM settings (such as SRC subsystems settings) might be lost. If you use base media, or a software source that is created from base media, for an **update_all** operation, previous history of your software installation is removed. Whenever a base image is installed, the history of the fileset installations is reset. The history is maintained when service updates are used for an **update_all** operation.

The minimum size of the boot logical volume is 24 MB. If your current boot logical volume is 16 MB or less, the installation process tries to increase it. However, partitions in a boot logical volume must be contiguous, and within the first 4 GB on the disk. If your system does not have free space that meets these requirements, a message indicates that there is not enough space to expand hd5 (the boot logical volume).

To install AIX 7 with 7200-05, follow the instructions in the [Installing the base operating system](#) topic.

Installing AIX by using a USB flash drive

AIX 7 with 7200-05 supports installation by using a USB flash drive on POWER8 systems, and later. A USB flash drive that contains an AIX installation image can be created by first downloading the AIX installation image from the [IBM Entitled System Support](#) website. A single volume installation image of AIX 7 with 7200-05 is made available on the IBM Entitled System Support website for writing to USB flash memory. After downloading the AIX installation image, the image can be written to a USB flash drive. IBM recommends using a recently manufactured USB flash drive. The minimum capacity requirement of the USB flash drive for AIX installation is 16 GB. On an AIX or a Linux® based system, the image can be written to a USB flash drive by using the `dd` command.

Additionally, it is possible to create an installable USB flash drive by copying the image directly from AIX DVD installation media by using the `dd` command:

```
$ dd if=/dev/cd0 of=/dev/usbms0 bs=4k
```

Comparable commands exist on Windows-based machines for writing the installation image to a USB flash drive.

After the USB flash drive AIX installation media is created, the media can be used on POWER8 systems, and later, similar to the DVD install media.

Note: The AIX `bootlist` command can recognize only the USB flash drive (`usbmsX`) as a bootable device if the USB flash drive was present during IPL of the AIX partition. On POWER8 systems, and later, the SMS menus can always be used to assign the USB flash drive as the boot source.

AIX and IBM Power Systems USB implementation is compliant with relevant USB standards. In the unlikely event when a USB flash drive is not properly recognized by AIX, IBM recommends using a different brand of device.

NIM installations with updated LPP_SOURCE

NIM installations by using an `LPP_SOURCE` directory that contains base images from a prior release and that contains updates to the current release require that you use an `image_data` resource during operating system installations.

When you use an `LPP_SOURCE` directory that contains base images from a prior release and updates to the current release, create an `image_data` resource to use for any operating system installations. The SPOT must be updated with the updates that are added to the `LPP_SOURCE` directory, or a new SPOT must be created. In that SPOT, copy the `image.template` file that is found at `<SPOT_LOCATION>/lpp/bosinst/image.template` to a new location outside of the SPOT. Create a NIM `image_data` resource that points to that location. Use that NIM `image_data` resource for all operating system installations.

Certain file systems might grow in size, and the default `image.data` file that is used during an operating system installation comes from the bos image in your `LPP_SOURCE` directory, which is the prior release `image.data` file.

> Update Access Keys on Power10

IBM Power10, or later processor-based servers include an AIX update access key (UAK) that is checked when you update the AIX operating system. UAKs include an expiration date. Informational messages are generated when the release date for this AIX operating system passed the expiration date of the UAK. Informational messages are also generated when the server boots or during the live partition mobility (LPM) operation and the current AIX operating system level passed the expiration date of the UAK. Also, the server periodically checks and informs the administrator about UAKs that are about to expire, UAKs that expired, or UAKs that are missing.

Support for Update Access Keys on Power10 processor-based servers is included in IBM AIX 7.2 with Technology Level 5 and Service Pack 7200-05-03-2136, or later, and AIX Version 7.1 with the 7100-05 Technology Level and Service Pack 7100-05-09-2136, or later.

⏪

Network Installation Management

Network Installation Management (NIM) includes a readme file that is installed with the NIM Master `bos.sysmgt.nim.master` file set. The path name of the file is `/usr/lpp/bos.sysmgt/nim/README`.

Java Technology Edition

IBM software development kit (SDK) and Java™ Runtime Environment (JRE) for AIX, Java Technology Edition is released in `JavaV.x` filesets, where *V* represents the version of Java, such as Java 8, and *x* is the individual file set, such as `Java8_64.sdk`.

The following versions of Java Technology Edition are available on the AIX 7.2.5 base media:

Java Version	Base media DVD1	Base media DVD2	Expansion pack
Java Version 5 (32 bit)	None	None	None
Java Version 5 (64 bit)	None	None	None
Java Version 6 (32 bit)	None	None	All
Java Version 6 (64 bit)	None	None	All
Java Version 7 (32 bit)	None	None	All
Java Version 7 (64 bit)	Java7_64.jre and Java7_64.sdk	Remaining Java7_64 software	None
Java Version 7.1 (32 bit)	None	None	All
Java Version 7.1 (64 bit)	None	None	All
Java Version 8 (32 bit)	None	None	All
Java Version 8 (64 bit)	All except non-Japanese message filesets	Remaining message filesets	None

Only Java Version 8 is installed for new overwrite or preservation operating system installation. For these installations, the `PATH` variable in the `/etc/environment` file points to `java8_64`. If you upgrade to AIX 7 with 7200-05 or perform an operating system migration, all previous levels of Java remain on the system, and the `/etc/environment` `PATH` variable is not changed. Later, if you remove the previous levels of Java (Java Version 5, Java Version 6, and Java Version 7), then you must change the `/etc/environment` `PATH` variable to point to `java8_64`.

- By default, Java Version 5 software is removed when you migrate to AIX 7 with 7200-05. However, you can keep Java 5 by changing the selection in the base operating system installation menus, or in the NIM **bosinst_data** resource. After the migration is complete and Java 5 is removed, you must change the `PATH` variable to `java8_64` in the `/etc/environment` file.

Note: Java 5 is not available on the AIX Version 7.2 base media or Expansion Pack media. Other versions of Java are available on the AIX Expansion Pack media.

- There is no support for security vulnerabilities in Java Version 6.

It is recommended to use `java8_64`. There is no support for security vulnerabilities in Java Version 5 and Java Version 6.

To check whether a more recent service refresh is available for a version of Java, see the [AIX Download and service information website](#).

New filesets

bos.xerces.lib

This fileset contains a new library that is called `libxerces.a` in the `/usr/lib` directory. While installing the AIX operating system, you must first install the `bos.xerces.lib` fileset before installing the `bos.net.ipsec.keymgt` and `bos.aixpert.cmds` filesets because the `libxerces.a` library of the `bos.xerces.lib` fileset is used by the IP Security (IPsec) and AIXPert technologies. To include the `bos.xerces.lib` fileset in the `LPP_SOURCE` directory, you must use the `bos.sysmgt.nim` fileset.

bos.decrypt, bos.kmip_client

These filesets are required for logical volume encryption. These filesets are not installed automatically when you run the **smit update_all** command or during an operating system migration operation. You must install it separately from your software source such as a DVD or an ISO image.

bos.net.tcp.cdp

This fileset contains new commands **cdpd** and **cdpctl** that are used to receive Cisco Discovery Protocol (CDP) messages for discovering other Cisco devices that are directly connected to the AIX logical partition. The **cdpd** command runs as a daemon to receive CDP packets that are sent by the resource controller. The **cdpctl** command controls the CDP daemon by configuring the network interface that is physically connected to the Cisco device.

>|bind.rte

This fileset contains BIND 9.16 support for AIX operating system that is available in AIX 7.2, Technology Level 5 Expansion Pack. For more information, see [AIX 7.2 with Technology Level 5 Expansion Pack Release Notes](#).<

Fileset changes

To provide you with more control over the software that is installed on your system, the `bos.net.tcp.client` and `bos.net.tcp.server` filesets are split into 34 new filesets. Beginning with AIX 7 with 7200-05, each of the `bos.net.tcp.*` filesets are shipped as individual images, instead of including them with the `bos.net` image. You can now remove unwanted filesets from a NIM installation that uses an `LPP_SOURCE` directory.

Note: Requisites for installing filesets are unchanged so you must be sure when you remove an image. This image might be required by other filesets that you might want to install.

The core code for each original fileset is in the `bos.net.tcp.client_core` and `bos.net.tcp.server_core` filesets. Requisites for software that is shipped with the AIX operating system (the `bos.net.tcp.client` and `bos.net.tcp.server` filesets) are changed to the `bos.net.tcp.client_core` and `bos.net.tcp.server_core` filesets. More requisites are added to the other new fileset as needed.

The original filesets still exist to satisfy any requisites from other software. The original filesets have requisites to all the new filesets to ensure that all the requirements are met.

To remove any of the new filesets, you must first remove either the `bos.net.tcp.client` fileset or the `bos.net.tcp.server` fileset. To remove the `bos.net.tcp.client` fileset, the `bos.net.tcp.server` fileset, or a new fileset, run the **lspp -d fileset_name** command. If no other software has requisites to the fileset that you want to remove, the removal is possible.

During an operating system migration, code changes occur, so that all the system configuration and user configurable files, which were owned by the `bos.net.tcp.client` and `bos.net.tcp.server` filesets, are merged by the new filesets that now own the files.

The list of new filesets follow:

- `bos.net.tcp.client_core`
- `bos.net.tcp.server_core`
- `bos.net.tcp.bind`
- `bos.net.tcp.bind_utils`
- `bos.net.tcp.bootp`
- `bos.net.tcp.dfpd`
- `bos.net.tcp.dhcp`
- `bos.net.tcp.dhcpd`
- `bos.net.tcp.ftp`
- `bos.net.tcp.ftpd`
- `bos.net.tcp.gated`
- `bos.net.tcp.imapd`
- `bos.net.tcp.mail_utils`
- `bos.net.tcp.ntp`

- bos.net.tcp.ntpd
- bos.net.tcp.pop3d
- bos.net.tcp.pxed
- bos.net.tcp.rcmd
- bos.net.tcp.rcmd_server
- bos.net.tcp.sendmail
- bos.net.tcp.slip
- bos.net.tcp.slp
- bos.net.tcp.snmp
- bos.net.tcp.snmpd
- bos.net.tcp.syslogd
- bos.net.tcp.tcpdump
- bos.net.tcp.telnet
- bos.net.tcp.telnetd
- bos.net.tcp.tftp
- bos.net.tcp.tftpd
- bos.net.tcp.timed
- bos.net.tcp.traceroute
- bos.net.tcp.x500
- bos.net.tcp.cpd

The encoded software in the bos.net.uucp fileset moved to the bos.net.uucode fileset.

Note: After upgrading the operating system to AIX 7.2, Technology Level 5 or later, the /etc/mail directory contains the new /etc/mail/sendmail.cf and /etc/mail/submit.cf files. The existing /etc/mail/sendmail.cf and /etc/mail/submit.cf files from the earlier versions of AIX are copied to the /lpp/save.config/etc/mail directory.

Migrating

You can do an operating system migration to AIX 7 with 7200-05 from any level of the AIX operating system, on a system that supports AIX 7.2 boot. Installing any new level of AIX requires more disk space than previous levels. Verify that you have enough free space in the file systems, or that you have free partitions in the rootvg. Migrating requires slightly more free space than a basic installation.

If you are using a NIM LPP_SOURCE created with a prior level base media and later levels of updates that are added, you must initially create the LPP_SOURCE with the base media at the same release date or later than the level of AIX 5.3, AIX 6.1, or AIX 7.1 that you are migrating from. The last 4 digits of the output of the **oslevel -s** command represent the year and week of the service pack currently installed (YYWW).

The default value of the **j2_inodeCacheSize** tunable parameter was changed from 400[®] to 200. The **j2_inodeCacheSize** tunable parameter allows approximately 50,000 open files per gigabyte (GB) of main memory, and improves system performance. However, the **j2_inodeCacheSize** tunable parameter value of 200 can cause issues in systems that have a small amount of main memory (4 GB or less) and many concurrent users or many concurrent open files. To fix these issues, you can change the values for the **j2_inodeCacheSize** and the **j2_metadataCacheSize** tunable parameters from 200 to the previous value of 400 by running the following command:

Note: When you run the following command, the current value and boot value of both the tunable parameters are reset.

```
ioo -p -o j2_inodeCacheSize=400 -o j2_metadataCacheSize=400
```


If the issues are not fixed after you change the values for the **j2_inodeCacheSize** and the **j2_metadataCacheSize** tunable parameters, you can contact IBM Support.

Restriction:

If you are upgrading from AIX 7.2.4 to AIX 7.2.5 by using HMC V10 R1 M1010, the Live Update operation might result in errors. In this scenario, complete the following steps:

- Run the **installp** command to upgrade from AIX 7.2.4 to AIX 7.2.5.
- Run the **hmcauth** command to authenticate with the HMC.
- Run the **Live Update** operation to check for upcoming interim fixes.

IBM License Metric Tool

The IBM License Metric Tool version 7.2 is no longer supported. To learn more about the replacement version of IBM License Metric Tool Version 9.x, go to [IBM License Metric Tool 9.2](#).

IBM PowerSC Trusted Surveyor

IBM PowerSC Trusted Surveyor is not supported in AIX 7 with 7200-05. If you are migrating to AIX 7 with 7200-05, you must remove the powersc . ts fileset before you start the migration process. If you have WPARs that you are migrating, you must verify that the powersc . ts fileset is not installed on the WPARs.

Reliable Scalable Cluster Technology (RSCT)

When you upgrade to AIX 7 with 7200-05, RSCT Version 3.2.5.0 is installed and replaces the previous version of RSCT. For more information about RSCT, see the IBM Docs for [RSCT 3.2](#).

AIX 7.2 and RSCT Version 3.2.5.0 no longer support the Virtual Shared Disk (VSD) and Low-level application programming interface (LAPI) products. If these products are already installed from an older code level, both the rsct . vsd and rsct . lapi . rte filesets must be removed before migrating to AIX 7 with 7200-05. If you have third-party products that use VSD, you must review the current Spectrum Scale product offerings for a replacement.

DSM

The dsm.core ships a /etc/ibm/sysmgt/dsm/overrides/dsm.properties file, which allows the user to override SSH configuration. If this file was modified, the file needs to be backed up manually before an update or a migration, as it is overwritten.

Thin Servers

If you migrate any previous version of the AIX Common Operating System Image (COSI) and associated AIX Thin Servers to the AIX 7 with 7200-05, it is recommended that you delete any dump device that is associated with the migrated Thin Servers and re-create the Thin Servers.

Also, you must install the devices . tmiscsw . rte fileset on the NIM master for the AIX 7 with 7200-05 Thin Server to create a dump device. The devices . tmiscsw . rte fileset is available in the AIX Expansion Pack.

IBM Subsystem Device Driver

AIX Version 7.2 does not support the IBM Subsystem Device Driver (SDD) for IBM TotalStorage Enterprise Storage Server®, the IBM TotalStorage DS family, and the IBM System Storage® SAN Volume Controller. If you are using SDD, you must transition to Subsystem Device Driver Path Control Module (SDDPCM) or AIX Path Control Module (PCM) for the multipath support on AIX for IBM SAN storage. SDD to SDDPCM migration scripts are available to help you with the transition.

Contact IBM storage technical support to request access to the migration scripts.

For more information about the available multipath I/O solutions and supported AIX versions for IBM SAN storage products, see the [IBM System Storage Interoperation Center \(SSIC\)](#) website.

Db2 migration

IBM Db2® Version 11.1 with FP5 is available on the AIX base media. You can upgrade your Db2 environment from Db2 Version 10.5, 10.1, or 9.7 to Db2 Version 11.1. For more information about upgrading to Db2 Version 11.1, see the [Upgrade to Db2 Version 11.1](#) topic.

Configuring

This section contains information about configuring the AIX operating system.

Dynamic queue depth for MPIO devices

A dynamic change occurs when you change a device attribute while the device is in the opened state. In the AIX operating system, you can change certain device attributes while the device is in the opened state by running the **chdev** command with the **-U** flag. In AIX 7 with 7200-05, you can dynamically change the `queue_depth` attribute for MPIO devices.

For each device that the AIX `scsidisk` device driver manages, a separate command queue is created. This queue is used as a buffer for the SCSI commands that are sent to the device. The `queue_depth` attribute represents the maximum number of SCSI commands that are allowed in the queue. The initial setting for the `queue_depth` attribute is configured in the ODM when the device is installed. In previous releases of the AIX operating system, the `queue_depth` attribute was static when a device was in the opened state. In AIX 7 with 7200-05, you can change the `queue_depth` attribute while the disk is in an opened state by running the **chdev -U -l hdiskX -a queue_depth=NEW_VALUE** command, where **NEW_VALUE** is the new queue depth.

libusb library

The `libusb` library is an open source C library that is supported on AIX 7 with 7200-05. The `libusb` library provides generic access to USB devices. You can run `libusb` applications on AIX 7 with 7200-05 by recompiling the applications with this new `libusb` package. You can download the `libusb` RPM Package Manager (RPM) from the <https://public.dhe.ibm.com/aix/freeSoftware/aixtoolbox/RPMS/ppc/libusb/> website. For more information about using the `libusb` library, see the following topics:

- [usbllibdev Special File](#)
- [USBLIBDD Passthru Driver](#)

Thin provisioning

AIX 7 with 7200-05 includes space reclamation support for thin provisioned disks that were added by using the Logical Volume Manager (LVM). When a sufficiently large amount of disk space from a physical volume is available, LVM releases this disk space back to the storage device. This function is enabled by default and can be turned off by using the **ioo** command. The space reclamation function is supported on only disks that are exposed to the AIX operating system with N_Port ID virtualization (NPIV) or direct attached FC adapters. Thin provisioning is available on the following storage products that support SCSI thin provisioning (Logical Block Provisioning) commands:

- IBM DS8000®
- IBM XIV®
- EMC Symmetric family
- IBM Spectrum® Virtualize

For more information about displaying space reclamation information, see the [lvmstat](#) command.

Diagnostics tasks

AIX 7 with 7200-05 supports scheduling periodic diagnostics multiple times a day instead of only once per day. To schedule periodic diagnostics multiple times a day, run the **diag** command and select **Task Selection > Periodic Diagnostics** and specify a time interval between each test.

AIX 7 with 7200-05 supports formatting and certifying up to 10 disks in parallel instead of a single at a time. To format or certify multiple disks, run the **diag** command and from the **Task Selection** menu, select **Certify Media in Parallel** or **Format Media in Parallel**. All eligible resources are displayed in a list. You can select up to 10 disks from the list. The status of the operation is updated every 5 seconds. The time the operation takes to complete for each disk is based on various factors such as disk type, size, and speed.

Limitations and restrictions

This section lists the restrictions and limitations that apply to AIX 7 with 7200-05.

Upgrading IBM Security Verify Directory

Starting with AIX 7.3 Technology Level 2, IBM Security Directory Server (ISDS) is upgraded and is renamed as IBM Security Verify Directory (ISVD). The fileset for ISDS Version 6.4.0.25 is upgraded to ISVD Version 10.0.0.1. The fileset version and the name change for the directory have no impact on how the ISVD functions. The ISVD Version 10.0.0.1 fileset is shipped with AIX 7.3 Technology Level 2 and AIX 7.2 Technology Level 5 base packs. The AIX 7.3 with Technology Level 2 base pack also includes the latest and stable Lightweight Directory Access Protocol (LDAP) filesets that provide fixes for the earlier issues.

Note: To support clients who are using AIX 7.2 with supported Technology Levels, ISVD version 10.0 will be provided as part of AIX 7.2 base pack as ISDS version 6.4 reaches end of support (EOS) in September 2024.

If you have ISDS Version 6.4, you must upgrade to ISVD Version 10.0. For more information about upgrading to ISVD version 10.0, see [Upgrade an instance of IBM Security Verify Directory](#) page.

Note: For ISVD Version 10.0 to function properly, you must complete the entire process, starting with [Setting the environment before you upgrade an instance to Links to client and server utilities](#).

AIX 7.2 Enterprise Edition 1.1, or later

Previous versions of AIX Enterprise Edition included IBM® Tivoli® Monitoring Version 6.2.3 and Version 6.3.0. However, AIX 7.2 Enterprise Edition 1.1, or later, includes only Tivoli Monitoring Version 6.3.0. To use AIX 7.2 Enterprise Edition 1.1, or later, you must upgrade to Tivoli Monitoring Version 6.3.0.

OpenSSL version 3.0

Starting with AIX 7.2 Technology Level 5, Open Source Secure Sockets Layer (OpenSSL) is updated from version 1.0.2 to 3.0.10. As a result of new updates in AIX 7.2 Technology Level 5, a few APIs are deprecated, weak ciphers are removed, support for Transport Layer Security (TLS) version 1.3 is introduced, and provider concepts are introduced. The OpenSSL version 3.0.10.1001 contains performance optimization for Advanced Encryption Standard (AES) with Galois/Counter Mode (AES-GCM) cipher and ChaCha20 stream cipher on Power10 systems.

Note: Starting with AIX 7.2 Technology Level 5, header files are OpenSSL version 3.0 based. Any new applications that are to be compiled must be compiled with OpenSSL version 3.0.

The AIX operating system ensures that the existing applications do not get impacted by the version update. Hence, the shared objects of OpenSSL 1.0.2 and OpenSSL 1.1 are retained in the OpenSSL library. The applications that depend on OpenSSL libraries must migrate to OpenSSL 3.0 before the end of support for the previous versions.

Note: The support for OpenSSL 1.0.2 ends by the end of year 2023 and the support for OpenSSL 1.1 ends by the end of year 2024. Shared objects of OpenSSL 1.0.2 will be retained beyond the year 2023 for compatibility with earlier OpenSSL versions. The shared objects of OpenSSL version 0.9.8 are no longer supported and the **libcrypto_compat.a** and **libssl_compat.a** libraries are removed since they contain only 0.9.8 shared object. Also the libraries **libcrypto.a** and **libssl.a** does not have 0.9.8 shared objects in them. As a mitigation, customers who depend on these shared objects are now recommended to compile their applications against the latest supported shared objects. OpenSSL 1.1 shared objects that are provided in the OpenSSL 3.0 library are from the corresponding latest release of the library that is provided with strong-cipher support. Customers who prefer to use this shared object are requested to compile applications by using the 1.1 library with strong-cipher support that is provided in AIX Web Download Pack Programs.

The command line tool **openssl** and **openssl164** are linked with the shared object of OpenSSL 3.0. Due to compatibility issues, the commands might not function properly.

Note: Many options are added to OpenSSL 3.0; hence, it is mandatory to validate the command line tools (**openssl** and **openssl164**) before using them.

The OpenSSL 3.0 is compiled by using the following configuration options:

- no-idea
- no-rc5
- no-weak-ssl-ciphers
- no-psk
- no-srp
- no-deprecated

The new symbols that are introduced in the OpenSSL 3.0 configuration file are stored in the `/var/ssl/openssl.cnf` file. It is recommended to backup and save the changes in the old configuration file because the old OpenSSL configuration file is not retained for the use.

To use the legacy providers that are built inside the application, make the following changes in the new configuration file:

```
openssl_conf = openssl_init

[openssl_init]
providers = provider_sect

[provider_sect]
default = default_sect
legacy = legacy_sect

[default_sect]
activate = 1

[legacy_sect]
activate = 1
```

Note: Native AIX applications that used OpenSSL version 1.0.2 shared object are updated to use OpenSSL version 1.1.1 and the preceding shared objects.

For more information about updates between OpenSSL 1.0.2 and OpenSSL 3.0, see the community migration guide (https://www.openssl.org/docs/man3.0/man7/migration_guide.html).

To raise any queries, see [IBM AIX support website](#).

OpenSSH Version 8.1p1

The OpenSSH file set is updated to the open source community 8.1p1 release with VRMF 8.1.112.2000 in AIX.

- The OpenSSH file set includes the patch for GSSAPI Key Exchange feature.
- The OpenSSH file set is compiled with OpenSSL 1.1.1t version.

- All the vulnerabilities reported in the higher version of OpenSSH (including the 8.7p1 release) are back ported to this fileset.

Note: All OpenSSH versions with VRMF 8.1.102.xxxx are no longer supported as support for OpenSSL 1.0.2 version ended in the year 2023. You must update to OpenSSH versions with VRMF 8.1.112.2000 or a later version. You can download the latest version of the OpenSSH fileset from the [AIX Web Download Pack Programs](#) website.

OpenSSH 6.0p1 with VRMF 6.0.0.6204, or earlier, OpenSSH 7.1p1 with VRMF 7.1.102.1100, or earlier, and OpenSSH 7.5p1 with VRMF 7.5.102.1600 or earlier are no longer supported. You can download the latest version of the OpenSSH fileset from the [AIX Web Download Pack Programs](#) website.

GSKit version requirement for NIST compliance

GSKit version 8.0.55.11 is provided on the AIX 7 with 7200-05 Expansion Pack media.

Use GSKit version 8.0.50.10, or later, when you use IP Security with Rivest-Shamir-Adleman (RSA) key lengths that are greater than 2048 bits. The minimum RSA key length of 2048 bits is a requirement for complying with the National Institute of Standards and Technology (NIST) standard as defined in Special Publication 800-131A. When you generate certificates for IP security (IPsec), consider the requirements that are listed in [Installing the IP security feature](#).

nmon command changes

The behavior of the nmon recordings for the PCPU and SCPU sections are not recorded by default in AIX Version 7.2. To enable the recording of the PCPU and SCPU sections, run the nmon recording with the **-y PCPU=on, SCPU=on** options. When the PCPU and SCPU sections are enabled, the recorded format is the same as the format in previous versions of the AIX operating system. For more information about the **nmon** command, see the [nmon command](#) topic.

Perl

The previous version of Perl was upgraded to Perl Version 5.28.1 in IBM AIX 7.2 with Technology Level 5. Perl is a separate 3rd-party open source package that is not owned by IBM. The Perl package might not preserve full compatibility across all versions. If you are moving Perl scripts to version 5.28.1, you must complete an evaluation of the scripts to verify that they continue to work as expected. For more information about Perl, see the [Perl Programming Documentation](#) website.

Code removed from AIX Version 7.2

The following code and functions were removed from AIX Version 7.2, or later:

- Fcarrayhead driver
- graPHIGS programming interface
- Network computing System 1.5.1 (bos.net.ncs fileset)
- Network Data Administration Facility (NDAF)
- Network Information Services + (NIS+)

Note: NIS is still available.

- IBM Systems Director Console for AIX
- IP over Fibre Channel (FC) driver

Licensed programs not supported in AIX Version 7.2

The following licensed programs are not supported in AIX Version 7.2:

- AIX Fast Connect
- Performance Toolbox for AIX

- IBM PowerSC Trusted Surveyor
- AIX Profile Manager

CIFS client fileset

The `bos.cifs_fs` software package is moved to the AIX Version 7.2 Expansion Pack media. The Common Internet File System (CIFS) client is provided as-is (without support).

Note: AIX Version 7.2 supports SMB client file system that is based on Server Message Block (SMB) protocol version 2.1. The SMB client file system is a replacement of the CIFS client. The CIFS client is based on SMB protocol version 1. For more information, see [SMB client file system](#).

Shared processor partition virtual CPU limit

The shared processor partitions in the AIX operating system are limited to a maximum of 128 virtual processors. Each virtual processor contains up to eight hardware threads and allows up to 1024 logical processors for POWER8 systems that run in SMT8 mode. If your configuration requires more AIX LPAR processors, you must use dedicated processors.

Additional information

IBM AIX Version 7.2 Documentation

To view the most current version of the AIX Version 7.2 information, see the [IBM Documentation for AIX website](#).

IBM Hyperconverged Systems

AIX on IBM Hyperconverged Systems that are powered by Nutanix provides simplified management through a hyperconverged infrastructure. You can run AIX Version 7.2.2 with Service Pack 2, or later, and APAR IJ05283 on IBM Hyperconverged Systems with POWER8 based CS821 and CS822 nodes.

AIX Version 7.2.2 with Service Pack 2, or later, runs fully virtualized on the Nutanix Acropolis Hypervisor and the corresponding virtual machine (VM) lifecycle is managed by the Nutanix PRISM graphical user interface (GUI). IBM Hyperconverged Systems support is integrated into the same version of the AIX 7.2.2 operating system that runs on IBM PowerVM® platforms. IBM Hyperconverged Systems are binary compatible with the AIX operating system that runs on PowerVM per the AIX binary compatibility guarantee.

Note: AIX Version 7.3 is not supported on IBM Hyperconverged Systems.

For more information about IBM Hyperconverged Systems, see the [IBM Hyperconverged Systems topic](#).

AIX Dynamic System Optimizer

The IBM AIX Dynamic System Optimizer (DSO) extends the features that are provided by the Active System Optimizer (ASO) to automatically adjust some system settings to maximize the efficiency of your system. This optimizer automates the difficult job of manually tuning those system settings to optimize eligible workloads. The additional features that are provided by DSO are large page optimization and data stream prefetch optimization.

DSO is no longer a stand-alone feature and is included in AIX Version 7.2, or later, as part of ASO. For more information about DSO and ASO, see the [AIX Dynamic System Optimizer topic](#).

Linux SHA-256 and SHA-512 password cryptographic algorithm

A Loadable Password Algorithm (LPA) model is available that supports the Linux SHA-256 and SHA-512 password cryptographic algorithm. The Linux SHA-256 and SHA-512 password cryptographic algorithm is supported by other operating systems and was published in the public domain by Ulrich Drepper (<https://www.akkadia.org/drepper/SHA-crypt.txt>).

The LPA model is included in the pvmmod licensed program product (LPP) package. You can get the pvmmod package from the [AIX Web Download Pack website](#).

Server-side support for new Unicode locales

For more information about server-side support for new Unicode locales, see the [Supported languages and locales](#) topic.

Common Criteria administration guide

The **Common Criteria administration guide** for AIX 7.2.5.3 is available for use.

Visit the following URL to access the document that provides instructions to configure and operate AIX 7.2 Technology Level 5 (TL5) Service Pack 3 (SP3) in the Common Criteria evaluated configuration to meet the National Information Assurance Partnership (NIAP) Protection Profile for General Purpose Operating Systems version 4.2.1 (also known as OSPP) and Extended Package for Secure Shell v1.0.

<https://www.ibm.com/support/pages/common-criteria-administration-guidance-aix-7253>

Use the following links to view the certificate that has an expiration date of 7 July 2027.

- Certification by BSI (Bundesamt für Sicherheit in der Informationstechnik), also known as Federal Office for Information Security.

https://www.bsi.bund.de/SharedDocs/Zertifikate_CC/CC/Betriebssysteme/1165.html?nn=513260

- Certification by Common Criteria Portal. You can check the certification under the operating system section.

<https://www.commoncriteriaportal.org/products/>

Notices

This information was developed for products and services offered in the US.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year).

Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. _enter the year or years_.

Privacy policy considerations

IBM Software products, including software as a service solutions, (“Software Offerings”) may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering’s use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as the customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at [Copyright and trademark information at www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Windows is a trademark of Microsoft Corporation in the United States, other countries, or both.

