

IBM Security zSecure Admin and Audit for RACF

Line Commands and Primary Commands Summary

SC27-6581-05

July 2021

This edition applies to version 2, release 5 of IBM Security zSecure™ Admin and Audit for RACF™ (product numbers 5655-N16 and 5655-N17) and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright IBM Corporation 2021

US Government Users Restricted Rights - Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

<u>Line commands</u> on <u>record</u> level that can be used in the zSecure user interface



|--|

/ View available line commands

C Copy profile or entry

S Show details

X, XX Exclude from FORALL processing

Z, ZZ Select for FORALL processing

User profile displays

A Permits and connects

AC Access check

CO Add connect

D, DD Delete

E Events, SMF reports

L Generates LISTUSER command

M Move

MI Manage IDs in segments

ML Manage logon

MR Manage CKGRACF authorization

requirement

MS Manage CKGRACF resume schedules

MT Manage TSO information

MU Manage user data

P On base segment: change password and resume. On application segment: show

user profile

PE Add or delete permit

R, RR Recreate

SE Show application segments

SR Show relevant profilesTR Trust bestowed on user

34 Data set list utility

Group profile display

A Group authorization

AC Access check

CO Add connect

D, DD Delete

E Events, SMF reports

L Generates LISTGRP command

MI Manage INSTDATA and APPLDATA
MR Manage CKGRACF authority requirements

MU Manage user data

P Show profile (on segment displays)

PE Add or delete permit

R, RR Recreate

SE Show application segments

SR Show relevant profiles

34 Data set list utility

DATASET profile displays

AC Access check

D, DD Delete

E Events, SMF reports

L Generates LISTDSD command

LD Generates LISTDSD DSNS command LR Lists data sets covered via Report

LR Lists data sets covered via ReportMI Manage INSTDATA or APPLDATA

MR CKGRACF multiple authority requirements

Manage USRDATA

P Show profile (on segment display)

PE Add or delete PERMIT

R, RR Recreate

MU

SE Show application segments

34 Data set list utility

RESOURCE profile (GENERAL) displays

AC Access check

CC Copy to different class

D, DD Delete

E Events, SMF reports

K Manage APPCLU and PTKDATA keys

L Generates RLIST command

MI Manage INSTDATA or APPLDATA

MR CKGRACF multiple authority requirements

MU Manage user data

P Show profile (on segment displays)

PE Add or delete PERMIT

R, RR Recreate

SE Show application segments

Certificates

BI Bind a certificate to a TKDS token

CO Connect a certificate to a key ring

EX Export a certificate

GR Generate a certificate request based on

the specified certificate

L Generates RACDCERTLIST

LC View information on all certificates in a

certificate chain

RK Rekey (replicate) a certificate with a new

key pair

RO Supersede a ticket with a new ticket and

retire the old certificate

UB Unbind a certificate from a TKDS token

Class settings displays

E Events, SMF reports

P Display profiles

R Refresh

<u>Line commands</u> on <u>detail</u> level that can be used in the zSecure user interface



Standard line commands

/ View available line commands

C Copy entry

D Delete entry

L List

S Show details

ACL

C Copy

D Delete

I Insert

L List user or group

P Show profile

R Recreate

S Select or modify

CONNECT

C Copy

D Delete or remove

L List

P Show profile

Certificates in user display

D Delete or remove

L List

USR fields

R

C Copy USERDATA field

D Delete USERDATA field

I Add USERDATA field

Repeat USERDATA field

S Set USERDATA field

CKGRACF USR fields

A Approve queued command

C Copy queued command or set schedule

D Deny queued command or clear schedule

H Hold queued command

I Add another command and queue for

approval or schedule action

R Edit current command and queue for approval or schedule action

RACLINK fields

A Approve pending association

C Copy current RACLINK association

D Generates RACLINK id (userid) undefine

(linked.node.user) command

I Copy or insert RACLINK association for

current user

Data set

B Browse

Resource

S Select or modify

Started task RACF user or group

L List

P Show profile

<u>Primary (ISPF) commands</u> that can be used in the zSecure user interface



ACCESS – Shows access for an ID on a resource

ACL EFFECTIVE - Shows an effective access list

ACL EXPLODE – Shows exploded access list

ACL NORMAL, ASIS - Shows actual access list

ACL NOSCOPE – Deactivates display of administrative authorities as part of the access list display

ACL NOUNIVERSAL – Deactivates the UNIVERSAL option

ACL RESOLVE - Shows resolved access list

ACL SCOPE – Activates display of administrative authorities as part of the access list

ACL SORT ACCESS – Sorts access list from OWNER to NONE

ACL SORT ID – Sorts access list by ID

ACL SORT USER – Sorts access list by user (with resolve/explode)

ACL TRUST – Shows trust relations of the profile

ACL UNIVERSAL – Takes system-wide operations and users with a default connection to a universal group into consideration when building the access list

C2RIMENU - Displays the results of the authority checks for the menu options to be shown and the actions to be shown on the menus

CANCEL - Resets pending administrative changes in displays that support overtype

CARLA, COMM - Types CARLa commands

CKNSERVE - Displays information about the zSecure Servers that are known to the zSecure Server address space identified by the ServerToken parameter on the CARLA OPTION command

CKXDEBUG - Displays CKX diagnostic information

CKXLOG – Set or view the current ticket ID and description

COLS - Shows a ruler in the top of your screen

FIELDS - Shows all fields that can be used in CARLa queries

FIND - Performs a character string search for text in a display panel

FORALL - Issues a command for all or selected profiles on a record-level display

HELP - Equivalent to the PF1 key

MESSAGES, MSG, MSGS - Shows the message library or look up a message

MODIFY - Enables or disables the ability to change values of modifiable fields

PRT, PRTLIST - Creates a hardcopy of a display, written to the standard ISPF LIST data set

RACF - Opens the RACF ISPF panels

RA.G – Same as entering ID or pattern into the group ID selection field in the RA.G selection panel, and entering the COMPLEX name to which the current row belongs

RA.U – Same as copy and paste of the ID or pattern into the user ID selection field in the RA.U selection panel, and entering the COMPLEX name to which the current row belongs

REFRESH - Resets changes in modified fields

RESET - Removes all pending updates from display panels and cancel pending commands

RESULTS - Shows resulting files from last query

RFIND - Repeats the previous FIND command from the current cursor position

SET - An alternative way to change some options on the Setup - View and Setup - Confirm display panels

SETUP - Invokes the SETUP application

SORT - SORT field [A,D] field [A,D]....

STARTPAN - Specifies the panel that opens when zSecure starts

SYSPREV - Browses the SYSPRINT message file of a recursive query

TEMPLATE - Shows the contents of the RACF database templates

 ${\bf X}$ – Find all records in the table that match the search argument and exclude those from the display

XF – Exclude all records from the display and then find and include all records that match the search arguments